Osi

trunk

Generated by Doxygen 1.8.1.2

Mon Mar 16 2015 20:12:08

CONTENTS

Contents

1	Dep	recated List	ı
2	Nam	nespace Index	1
	2.1	Namespace List	1
3	Clas	ss Index	1
	3.1	Class Hierarchy	1
4	Clas	ss Index	
	4.1	Class List	E
5	File	Index	É
	5.1	File List	E
6	Nam	nespace Documentation	c
U		OsiUnitTest Namespace Reference	
	6.1	·	
		6.1.1 Detailed Description	
		6.1.2 Function Documentation	
		6.1.3 Variable Documentation	1
7	Clas	ss Documentation 1	1
	7.1	OsiSolverInterface::ApplyCutsReturnCode Class Reference	1
		7.1.1 Detailed Description	2
	7.2	OsiCuts::const_iterator Class Reference	2
		7.2.1 Detailed Description	2
	7.3	glp_prob Struct Reference	3
		7.3.1 Detailed Description	3
	7.4	OsiCuts::iterator Class Reference	3
		7.4.1 Detailed Description	3
	7.5	OsiAuxInfo Class Reference	3
		7.5.1 Detailed Description	4
	7.6	OsiBabSolver Class Reference	1
		7.6.1 Detailed Description	E
		7.6.2 Member Function Documentation	
		7.6.3 Member Data Documentation	Ε
	7.7	OsiBranchingInformation Class Reference	
		7.7.1 Detailed Description	
		7.7.2 Member Data Documentation	

CONTENTS

7.8	OsiBrar	nchingObject Class Reference	20
	7.8.1	Detailed Description	23
	7.8.2	Member Function Documentation	23
	7.8.3	Member Data Documentation	23
7.9	OsiCho	poseStrong Class Reference	23
	7.9.1	Detailed Description	25
	7.9.2	Member Function Documentation	25
7.10	OsiCho	poseVariable Class Reference	26
	7.10.1	Detailed Description	29
	7.10.2	Member Function Documentation	30
7.11	OsiCol	Cut Class Reference	30
	7.11.1	Detailed Description	32
	7.11.2	Member Function Documentation	32
	7.11.3	Friends And Related Function Documentation	33
7.12	OsiCpx	SolverInterface Class Reference	33
	7.12.1	Detailed Description	40
	7.12.2	Member Enumeration Documentation	40
	7.12.3	Member Function Documentation	41
	7.12.4	Friends And Related Function Documentation	47
7.13	OsiCut	Class Reference	47
	7.13.1	Detailed Description	48
	7.13.2	Member Function Documentation	49
7.14	OsiCuts	s Class Reference	49
	7.14.1	Detailed Description	52
	7.14.2	Member Function Documentation	52
	7.14.3	Friends And Related Function Documentation	53
7.15	OsiGlpl	kSolverInterface Class Reference	53
	7.15.1	Detailed Description	59
	7.15.2	Member Enumeration Documentation	59
	7.15.3	Member Function Documentation	60
	7.15.4	Friends And Related Function Documentation	66
7.16	OsiGrb	SolverInterface Class Reference	67
	7.16.1	Detailed Description	74
	7.16.2	Member Enumeration Documentation	74
	7.16.3	Member Function Documentation	75
	7.16.4	Friends And Related Function Documentation	82
7.17	OsiHotI	Info Class Reference	82

CONTENTS

	7.17.1 Detailed Description	. 84
	7.17.2 Member Function Documentation	. 85
7.18	OsiIntegerBranchingObject Class Reference	. 85
	7.18.1 Detailed Description	. 87
	7.18.2 Constructor & Destructor Documentation	. 87
	7.18.3 Member Function Documentation	. 87
7.19	OsiLotsize Class Reference	. 87
	7.19.1 Detailed Description	. 89
	7.19.2 Member Function Documentation	. 89
7.20	OsiLotsizeBranchingObject Class Reference	. 90
	7.20.1 Detailed Description	. 92
	7.20.2 Constructor & Destructor Documentation	. 92
	7.20.3 Member Function Documentation	. 92
7.21	OsiMskSolverInterface Class Reference	. 93
	7.21.1 Detailed Description	. 100
	7.21.2 Member Enumeration Documentation	. 101
	7.21.3 Member Function Documentation	. 101
7.22	OsiObject Class Reference	. 107
	7.22.1 Detailed Description	. 110
	7.22.2 Member Function Documentation	. 110
	7.22.3 Member Data Documentation	. 111
7.23	OsiObject2 Class Reference	. 111
	7.23.1 Detailed Description	. 113
7.24	OsiPresolve Class Reference	. 113
	7.24.1 Detailed Description	. 114
	7.24.2 Member Function Documentation	. 115
7.25	OsiPseudoCosts Class Reference	. 116
	7.25.1 Detailed Description	. 117
7.26	OsiRowCut Class Reference	. 117
	7.26.1 Detailed Description	. 120
	7.26.2 Constructor & Destructor Documentation	. 120
	7.26.3 Member Function Documentation	. 121
	7.26.4 Friends And Related Function Documentation	. 121
7.27	OsiRowCut2 Class Reference	. 121
	7.27.1 Detailed Description	. 123
7.28	OsiRowCutDebugger Class Reference	. 123
	7.28.1 Detailed Description	. 124

CONTENTS iv

	7.28.2 Constructor & Destructor Documentation	25
	7.28.3 Member Function Documentation	25
	7.28.4 Friends And Related Function Documentation	26
7.29	OsiSimpleInteger Class Reference	26
	7.29.1 Detailed Description	28
	7.29.2 Member Function Documentation	28
7.30	OsiSolverBranch Class Reference	29
	7.30.1 Detailed Description	29
7.31	OsiSolverInterface Class Reference	30
	7.31.1 Detailed Description	43
	7.31.2 Member Typedef Documentation	43
	7.31.3 Member Function Documentation	43
	7.31.4 Friends And Related Function Documentation	64
	7.31.5 Member Data Documentation	64
7.32	OsiSolverResult Class Reference	65
	7.32.1 Detailed Description	65
7.33	OsiSOS Class Reference	66
	7.33.1 Detailed Description	68
	7.33.2 Constructor & Destructor Documentation	68
	7.33.3 Member Function Documentation	68
	7.33.4 Member Data Documentation	69
7.34	OsiSOSBranchingObject Class Reference	69
	7.34.1 Detailed Description	70
7.35	OsiSpxSolverInterface Class Reference	70
	7.35.1 Detailed Description	76
	7.35.2 Member Function Documentation	76
	7.35.3 Friends And Related Function Documentation	80
7.36	OsiTwoWayBranchingObject Class Reference	81
	7.36.1 Detailed Description	82
	7.36.2 Constructor & Destructor Documentation	82
	7.36.3 Member Function Documentation	82
7.37	OsiXprSolverInterface Class Reference	82
	7.37.1 Detailed Description	89
	7.37.2 Member Function Documentation	89
	7.37.3 Friends And Related Function Documentation	95
7.38	OsiUnitTest::TestOutcome Class Reference	95
	7.38.1 Detailed Description	97

1 Deprecated List

	7.39	OsiUni	tTest::TestOutcomes Class Reference	197
		7.39.1	Detailed Description	198
		7.39.2	Member Function Documentation	198
8	File	Docume	entation	199
	8.1	OsiRov	vCutDebugger.hpp File Reference	199
		8.1.1	Detailed Description	199
	8.2	OsiUni	tTests.hpp File Reference	199
		8.2.1	Detailed Description	202
		8.2.2	Macro Definition Documentation	202
		8.2.3	Function Documentation	202
1	De	precat	ed List	
Ме		· <mark>OsiSol</mark> #getCol	verInterface::columnType (bool refresh=false) const Type	
2	Naı	mespa	ce Index	
2.1	Na	mespac	ee List	
Не	re is a	a list of a	Ill documented namespaces with brief descriptions:	
		InitTest \ names	pace so we can define a few 'global' variables to use during tests	9
3	Cla	ıss Ind	ex	
3.1	Cla	ass Hier	archy	
Thi	s inhe	eritance	list is sorted roughly, but not completely, alphabetically:	
	doub forcin remo	leton_ad ng_cons ve_fixed	<pre>[external] ction::action[external] traint_action::action[external] d_action::action[external] on::action[external]</pre>	
	std::b std::b std::b std::b	pasic_fst pasic_fst pasic_ifs pasic_ifs pasic_ios	terface::ApplyCutsReturnCode tream< char > tream< wchar_t > tream< char > tream< wchar_t > s< char > s< wchar_t >	11

3.1 Class Hierarchy 2

```
std::basic_iostream< char >
std::basic iostream< wchar t >
std::basic istream < char >
std::basic istream< wchar t >
std::basic istringstream< char >
std::basic istringstream< wchar t >
std::basic ofstream < char >
std::basic ofstream< wchar t >
std::basic ostream < char >
std::basic ostream< wchar t >
std::basic_ostringstream < char >
std::basic_ostringstream< wchar_t >
std::basic string < char >
std::basic_string< wchar_t >
std::basic stringstream < char >
std::basic_stringstream< wchar_t >
BitVector128[external]
CoinAbsFltEq[external]
CoinArrayWithLength [external]
   CoinArbitraryArrayWithLength [external]
   CoinBigIndexArrayWithLength [external]
   CoinDoubleArrayWithLength [external]
   CoinFactorizationDoubleArrayWithLength [external]
   CoinFactorizationLongDoubleArrayWithLength [external]
   CoinIntArrayWithLength [external]
   CoinUnsignedIntArrayWithLength [external]
   CoinVoidStarArrayWithLength [external]
CoinBaseModel[external]
   CoinModel[external]
   CoinStructuredModel[external]
CoinBuild[external]
CoinDenseVector< T > [external]
CoinError[external]
CoinExternalVectorFirstGreater 2< class, class, class > [external]
CoinExternalVectorFirstGreater_3 < class, class, class, class > [external]
CoinExternalVectorFirstLess 2< class, class, class > [external]
CoinExternalVectorFirstLess 3< class, class, class, class > [external]
CoinFactorization [external]
CoinFileIOBase [external]
   CoinFileInput[external]
   CoinFileOutput[external]
CoinFirstAbsGreater 2< class, class > [external]
CoinFirstAbsGreater 3< class, class, class > [external]
CoinFirstAbsLess_2< class, class > [external]
CoinFirstAbsLess_3< class, class, class > [external]
CoinFirstGreater_2< class, class > [external]
CoinFirstGreater_3< class, class, class > [external]
CoinFirstLess 2< class, class > [external]
CoinFirstLess 3 < class, class, class > [external]
CoinLpIO::CoinHashLink[external]
CoinMpsIO::CoinHashLink[external]
CoinIndexedVector[external]
   CoinPartitionedVector[external]
CoinLpIO [external]
```

3.1 Class Hierarchy 3

```
CoinMessageHandler[external]
CoinMessages [external]
   CoinMessage [external]
CoinModelHash[external]
CoinModelHash2[external]
CoinModelHashLink[external]
CoinModelInfo2[external]
CoinModelLink[external]
CoinModelLinkedList[external]
CoinModelTriple [external]
CoinMpsCardReader[external]
CoinMpsIO[external]
CoinOneMessage [external]
CoinOtherFactorization [external]
  CoinDenseFactorization [external]
  CoinOslFactorization [external]
   CoinSimpFactorization[external]
CoinPackedMatrix[external]
CoinPackedVectorBase [external]
   CoinPackedVector[external]
   CoinShallowPackedVector[external]
CoinPair < S, T > [external]
CoinParam [external]
CoinPrePostsolveMatrix [external]
   CoinPostsolveMatrix[external]
   CoinPresolveMatrix [external]
CoinPresolveAction[external]
  do_tighten_action[external]
  doubleton_action[external]
  drop_empty_cols_action[external]
  drop_empty_rows_action[external]
  drop zero coefficients action[external]
  dupcol_action[external]
  duprow action[external]
  forcing_constraint_action[external]
  gubrow action[external]
  implied free action[external]
  isolated constraint action[external]
  make fixed action[external]
  remove dual action[external]
  remove_fixed_action[external]
  slack doubleton action[external]
  slack singleton action[external]
  subst_constraint_action[external]
  tripleton_action[external]
  twoxtwo_action[external]
  useless_constraint_action[external]
CoinPresolveMonitor[external]
CoinRational[external]
CoinRelFltEq[external]
CoinSearchTreeBase [external]
   CoinSearchTree < class > [external]
CoinSearchTreeCompareBest[external]
CoinSearchTreeCompareBreadth [external]
```

3.1 Class Hierarchy 4

CoinSearchTreeComparePreferred[external]	
CoinSearchTreeManager[external]	
CoinSet[external]	
CoinSosSet[external]	
<pre>CoinSnapshot[external] CoinThreadRandom[external]</pre>	
CoinTimer[external]	
CoinTreeNode [external]	
CoinTreeSiblings [external]	
CoinTriple < S, T, U > [external]	
CoinWarmStart[external]	
CoinWarmStartBasis [external]	
CoinWarmStartDual[external]	
CoinWarmStartPrimalDual[external]	
<pre>CoinWarmStartVector< T > [external]</pre>	
<pre>CoinWarmStartVectorPair< T, U > [external]</pre>	
CoinWarmStartDiff[external]	
CoinWarmStartBasisDiff[external]	
CoinWarmStartDualDiff[external]	
CoinWarmStartPrimalDualDiff[external]	
<pre>CoinWarmStartVectorDiff< T > [external] CoinWarmStartVectorPairDiff< T, U > [external]</pre>	
CoinYacr[external]	
Oil 1400 [CACCINAL]	
OsiCuts::const_iterator	12
dropped_zero[external]	
EKKHlink[external]	
<pre>EKKHlink[external] FactorPointers[external]</pre>	
FactorPointers [external]	13
	13
FactorPointers [external]	13 13
<pre>FactorPointers[external] glp_prob</pre>	
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome >	13
FactorPointers [external] glp_prob OsiCuts::iterator	
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo	13
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome >	13
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo	13
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation	13 13 14 18
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation OsiBranchingObject	13 13 14
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation	13 13 14 18
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation OsiBranchingObject	13 13 14 18 20
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation OsiBranchingObject OsiTwoWayBranchingObject OsiIntegerBranchingObject	13 14 18 20 181 85
FactorPointers [external] glp_prob OsiCuts::iterator std::list < TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation OsiBranchingObject OsiTwoWayBranchingObject	13 14 18 20 181
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation OsiBranchingObject OsiTwoWayBranchingObject OsiIntegerBranchingObject	13 14 18 20 181 85
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation OsiBranchingObject OsiTwoWayBranchingObject OsiIntegerBranchingObject OsiLotsizeBranchingObject	13 14 18 20 181 85 90
FactorPointers [external] glp_prob OsiCuts::iterator std::list < TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation OsiBranchingObject OsiTwoWayBranchingObject OsiIntegerBranchingObject OsiLotsizeBranchingObject OsiSOSBranchingObject OsiChooseVariable	13 13 14 18 20 181 85 90 169 26
FactorPointers [external] glp_prob OsiCuts::iterator std::list< TestOutcome > OsiAuxInfo OsiBabSolver OsiBranchingInformation OsiBranchingObject OsiTwoWayBranchingObject OsiLotsizeBranchingObject OsiSOSBranchingObject	13 13 14 18 20 181 85 90 169

4 Class Index 5

OsiColCut	30
OsiRowCut	117
OsiRowCut2	121
OsiCuts	49
OsiHotInfo	82
OsiObject	107
OsiObject2	111
OsiLotsize	87
OsiSimpleInteger	126
OsiSOS	166
OsiPresolve	113
OsiPseudoCosts	116
OsiRowCutDebugger	123
OsiSolverBranch	129
OsiSolverInterface	130
OsiCpxSolverInterface	33
OsiGlpkSolverInterface	53
OsiGrbSolverInterface	67
OsiMskSolverInterface	93
OsiSpxSolverInterface	170
OsiXprSolverInterface	182
<pre>OsiSolverResult presolvehlink[external] ReferencedObject[external] SmartPtr< T > [external] symrec[external]</pre>	165
OsiUnitTest::TestOutcome	195
OsiUnitTest::TestOutcomes	197

Generated on Mon Mar 16 2015 20:12:05 for Osi by Doxygen

4 Class Index

4.1 Class List 6

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

OsiSolverInterface::ApplyCutsReturnCode	
Internal class for obtaining status from the applyCuts method	11
OsiCuts::const_iterator Const Iterator	12
glp_prob	13
OsiCuts::iterator Iterator	13
OsiAuxInfo This class allows for a more structured use of algorithmic tweaking to an OsiSolverInterface	13
OsiBabSolver This class allows for the use of more exotic solvers e.g	14
OsiBranchingInformation	18
OsiBranchingObject Abstract branching object base class	20
OsiChooseStrong This class chooses a variable to branch on	23
OsiChooseVariable This class chooses a variable to branch on	26
OsiColCut Column Cut Class	30
OsiCpxSolverInterface CPLEX Solver Interface	33
OsiCut	47
OsiCuts Collections of row cuts and column cuts	49
OsiGlpkSolverInterface	53
OsiGrbSolverInterface Gurobi Solver Interface	67
OsiHotInfo This class contains the result of strong branching on a variable When created it stores enough information for strong branching	82
OsilntegerBranchingObject Simple branching object for an integer variable	85
OsiLotsize Lotsize class	87

4.1 Class List 7

OsiLotsizeBranchingObject Lotsize branching object	90
OsiMskSolverInterface	93
OsiObject Abstract base class for 'objects'	107
OsiObject2 Define a class to add a bit of complexity to OsiObject This assumes 2 way branching	111
OsiPresolve OSI interface to COIN problem simplification capabilities	113
OsiPseudoCosts This class is the placeholder for the pseudocosts used by OsiChooseStrong	116
OsiRowCut Row Cut Class	117
OsiRowCut2 Row Cut Class which refers back to row which created it	121
OsiRowCutDebugger Validate cuts against a known solution	123
OsiSimpleInteger Define a single integer class	126
OsiSolverBranch Solver Branch Class	129
OsiSolverInterface Abstract Base Class for describing an interface to a solver	130
OsiSolverResult Solver Result Class	165
OsiSOS Define Special Ordered Sets of type 1 and 2	166
OsiSOSBranchingObject Branching object for Special ordered sets	169
OsiSpxSolverInterface SoPlex Solver Interface Instantiation of OsiSpxSolverInterface for SoPlex	170
OsiTwoWayBranchingObject This just adds two-wayness to a branching object	181
OsiXprSolverInterface XPRESS-MP Solver Interface	182
OsiUnitTest::TestOutcome A single test outcome record	195

5 File Index 8

	Utility class to maintain a list of test outcomes	197
5	File Index	
5.1	File List	
Не	re is a list of all documented files with brief descriptions:	
	config_default.h	??
	config_osi_default.h	??
	OsiAuxInfo.hpp	??
	OsiBranchingObject.hpp	??
	OsiChooseVariable.hpp	??
	OsiColCut.hpp	??
	OsiCollections.hpp	??
	OsiConfig.h	??
	OsiCpxSolverInterface.hpp	??
	OsiCut.hpp	??
	OsiCuts.hpp	??
	OsiGlpkSolverInterface.hpp	??
	OsiGrbSolverInterface.hpp	??
	OsiMskSolverInterface.hpp	??
	OsiPresolve.hpp	??
	OsiRowCut.hpp	??
	OsiRowCutDebugger.hpp Provides a facility to validate cut constraints to ensure that they do not cut off a given solution	199
	OsiSolverBranch.hpp	??
	OsiSolverInterface.hpp	??
	OsiSolverParameters.hpp	??
	OsiSpxSolverInterface.hpp	??
	OsiUnitTests.hpp Utility methods for OSI unit tests	199
	OsiXprSolverInterface.hpp	??

6 Namespace Documentation

6.1 OsiUnitTest Namespace Reference

A namespace so we can define a few 'global' variables to use during tests.

Classes

· class TestOutcome

A single test outcome record.

· class TestOutcomes

Utility class to maintain a list of test outcomes.

Functions

• void failureMessage (const std::string &solverName, const std::string &message)

Print an error message.

- void failureMessage (const OsiSolverInterface &si, const std::string &message)
- void failureMessage (const std::string &solverName, const std::string &testname, const std::string &testcond)

Print an error message, specifying the test name and condition.

- void failureMessage (const OsiSolverInterface &si, const std::string &testname, const std::string &testcond)
- void testingMessage (const char *const msg)

Print a message.

• bool equivalentVectors (const OsiSolverInterface *si1, const OsiSolverInterface *si2, double tol, const double *v1, const double *v2, int size)

Utility method to check equality.

bool compareProblems (OsiSolverInterface *osi1, OsiSolverInterface *osi2)

Compare two problems for equality.

bool isEquivalent (const CoinPackedVectorBase &pv, int n, const double *fv)

Compare a packed vector with an expanded vector.

• bool processParameters (int argc, const char **argv, std::map< std::string, std::string > &parms, const std::map< std::string, int > &ignorekeywords=std::map< std::string, int >())

Process command line parameters.

Variables

unsigned int verbosity

Verbosity level of unit tests.

· unsigned int haltonerror

Behaviour on failing a test.

· TestOutcomes outcomes

Test outcomes.

6.1.1 Detailed Description

A namespace so we can define a few 'global' variables to use during tests.

6.1.2 Function Documentation

6.1.2.1 void OsiUnitTest::failureMessage (const std::string & solverName, const std::string & message)

Print an error message.

Formatted as "XxxSolverInterface testing issue: message" where Xxx is the string provided as solverName.

Flushes std::cout before printing to std::cerr.

6.1.2.2 void OsiUnitTest::failureMessage (const OsiSolverInterface & si, const std::string & message)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

6.1.2.3 void OsiUnitTest::failureMessage (const std::string & solverName, const std::string & testname, const std::string & testcond)

Print an error message, specifying the test name and condition.

Formatted as "XxxSolverInterface testing issue: testname failed: testcond" where Xxx is the OsiStrParam::OsiSolver-Name parameter of the si. Flushes std::cout before printing to std::cerr.

6.1.2.4 void OsiUnitTest::failureMessage (const OsiSolverInterface & si, const std::string & testname, const std::string & testcond)

This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

6.1.2.5 void OsiUnitTest::testingMessage (const char *const msg)

Print a message.

Prints the message as given. Flushes std::cout before printing to std::cerr.

6.1.2.6 bool OsiUnitTest::equivalentVectors (const OsiSolverInterface * si1, const OsiSolverInterface * si2, double tol, const double * v1, const double * v2, int size)

Utility method to check equality.

Tests for equality using **CoinRelFitEq** with tolerance tol. Understands the notion of solver infinity and obtains the value for infinity from the solver interfaces supplied as parameters.

6.1.2.7 bool OsiUnitTest::compareProblems (OsiSolverInterface * osi1, OsiSolverInterface * osi2)

Compare two problems for equality.

Compares the problems held in the two solvers: constraint matrix, row and column bounds, column type, and objective. Rows are checked using upper and lower bounds and using sense, bound, and range.

6.1.2.8 bool OsiUnitTest::isEquivalent (const CoinPackedVectorBase & pv, int n, const double * fv)

Compare a packed vector with an expanded vector.

Checks that all values present in the packed vector are present in the full vector and checks that there are no extra entries in the full vector. Uses **CoinRelFitEq** with the default tolerance.

7 Class Documentation 11

6.1.2.9 bool OsiUnitTest::processParameters (int *argc*, const char ** *argv*, std::map< std::string, std::string > & *parms*, const std::map< std::string, int > ())

Process command line parameters.

An unrecognised keyword which is not in the <code>ignorekeywords</code> map will trigger the help message and a return value of false. For each keyword in <code>ignorekeywords</code>, you can specify the number of following parameters that should be ignored.

This should be replaced with the one of the standard CoinUtils parameter mechanisms.

- 6.1.3 Variable Documentation
- 6.1.3.1 unsigned int OsiUnitTest::verbosity

Verbosity level of unit tests.

0 (default) for minimal output; larger numbers produce more output

6.1.3.2 unsigned int OsiUnitTest::haltonerror

Behaviour on failing a test.

- 0 (= default) continue
- 1 press any key to continue
- · 2 stop with abort()

6.1.3.3 TestOutcomes OsiUnitTest::outcomes

Test outcomes.

A global TestOutcomes object to store test outcomes during the run of the unit test for an OSI.

7 Class Documentation

7.1 OsiSolverInterface::ApplyCutsReturnCode Class Reference

Internal class for obtaining status from the applyCuts method.

```
#include <OsiSolverInterface.hpp>
```

Public Member Functions

Constructors and desctructors

- ApplyCutsReturnCode ()
 - Default constructor.
- ApplyCutsReturnCode (const ApplyCutsReturnCode &rhs)

Copy constructor.

- ApplyCutsReturnCode & operator= (const ApplyCutsReturnCode &rhs)
 - Assignment operator.
- ∼ApplyCutsReturnCode ()

Destructor.

Accessing return code attributes

• int getNumInconsistent () const

Number of logically inconsistent cuts.

int getNumInconsistentWrtIntegerModel () const

Number of cuts inconsistent with the current model.

• int getNumInfeasible () const

Number of cuts that cause obvious infeasibility.

• int getNumIneffective () const

Number of redundant or ineffective cuts.

• int getNumApplied () const

Number of cuts applied.

Friends

- · class OsiSolverInterface
- class OsiGrbSolverInterface

7.1.1 Detailed Description

Internal class for obtaining status from the applyCuts method.

Definition at line 74 of file OsiSolverInterface.hpp.

The documentation for this class was generated from the following file:

OsiSolverInterface.hpp

7.2 OsiCuts::const_iterator Class Reference

Const Iterator.

```
#include <OsiCuts.hpp>
```

Friends

· class OsiCuts

7.2.1 Detailed Description

Const Iterator.

This is a class for iterating over the collection of cuts.

Definition at line 74 of file OsiCuts.hpp.

The documentation for this class was generated from the following file:

· OsiCuts.hpp

7.3 glp_prob Struct Reference

7.3.1 Detailed Description

Definition at line 30 of file OsiGlpkSolverInterface.hpp.

The documentation for this struct was generated from the following file:

• OsiGlpkSolverInterface.hpp

7.4 OsiCuts::iterator Class Reference

Iterator.

#include <OsiCuts.hpp>

Friends

· class OsiCuts

7.4.1 Detailed Description

Iterator.

This is a class for iterating over the collection of cuts.

Definition at line 30 of file OsiCuts.hpp.

The documentation for this class was generated from the following file:


· OsiCuts.hpp

7.5 OsiAuxInfo Class Reference

This class allows for a more structured use of algorithmic tweaking to an OsiSolverInterface.

```
#include <OsiAuxInfo.hpp>
```

Inheritance diagram for OsiAuxInfo:



Public Member Functions

• virtual OsiAuxInfo * clone () const

Clone

OsiAuxInfo & operator= (const OsiAuxInfo &rhs)

Assignment operator.

void * getApplicationData () const

Get application data.

Protected Attributes

void * appData

Pointer to user-defined data structure.

7.5.1 Detailed Description

This class allows for a more structured use of algorithmic tweaking to an OsiSolverInterface.

It is designed to replace the simple use of appData_pointer.

This has been done to make it easier to use NonLinear solvers and other exotic beasts in a branch and bound mode. After this class definition there is one for a derived class for just such a purpose.

Definition at line 21 of file OsiAuxInfo.hpp.

The documentation for this class was generated from the following file:


· OsiAuxInfo.hpp

7.6 OsiBabSolver Class Reference


This class allows for the use of more exotic solvers e.g.

#include <OsiAuxInfo.hpp>

Inheritance diagram for OsiBabSolver:



Collaboration diagram for OsiBabSolver:



Public Member Functions

virtual OsiAuxInfo * clone () const

Clone

OsiBabSolver & operator= (const OsiBabSolver &rhs)

Assignment operator.

void setSolver (const OsiSolverInterface *solver)

Update solver.

void setSolver (const OsiSolverInterface &solver)

Update solver.

int solution (double &objectiveValue, double *newSolution, int numberColumns)

returns 0 if no heuristic solution, 1 if valid solution with better objective value than one passed in Sets solution values if good, sets objective value numberColumns is size of newSolution

void setSolution (const double *solution, int numberColumns, double objectiveValue)

Set solution and objective value.

bool hasSolution (double &solutionValue, double *solution)

returns true if the object stores a solution, false otherwise.

void setSolverType (int value)

Sets solver type 0 - normal LP solver 1 - DW - may also return heuristic solutions 2 - NLP solver or similar - can't compute objective value just from solution check solver to see if feasible and what objective value is.

int solverType () const

gets solver type 0 - normal LP solver 1 - DW - may also return heuristic solutions 2 - NLP solver or similar - can't compute objective value just from solution check this (rather than solver) to see if feasible and what objective value is

· bool solutionAddsCuts () const

Return true if getting solution may add cuts so hot start etc will be obsolete.

bool alwaysTryCutsAtRootNode () const

Return true if we should try cuts at root even if looks satisfied.

• bool solverAccurate () const

Returns true if can use solver objective or feasible values, otherwise use mipBound etc.

• bool reducedCostsAccurate () const

Returns true if can use reduced costs for fixing.

• double mipBound () const

Get objective (well mip bound)

· bool mipFeasible () const

Returns true if node feasible.

void setMipBound (double value)

Set mip bound (only used for some solvers)

· double bestObjectiveValue () const

Get objective value of saved solution.

bool tryCuts () const

Says whether we want to try cuts at all.

bool warmStart () const

Says whether we have a warm start (so can do strong branching)

• int extraCharacteristics () const

Get bit mask for odd actions of solvers 1 - solution or bound arrays may move in mysterious ways e.g.

void setExtraCharacteristics (int value)

Set bit mask for odd actions of solvers 1 - solution or bound arrays may move in mysterious ways e.g.

• const double * beforeLower () const

Pointer to lower bounds before branch (only if extraCharacteristics set)

void setBeforeLower (const double *array)

Set pointer to lower bounds before branch (only if extraCharacteristics set)

const double * beforeUpper () const

Pointer to upper bounds before branch (only if extraCharacteristics set)

void setBeforeUpper (const double *array)

Set pointer to upper bounds before branch (only if extraCharacteristics set)

Protected Attributes

double bestObjectiveValue

Objective value of best solution (if there is one) (minimization)

double mipBound

Current lower bound on solution (if > 1.0e50 infeasible)

const OsiSolverInterface * solver

Solver to use for getting/setting solutions etc.

double * bestSolution

Best integer feasible solution.

const double * beforeLower

Pointer to lower bounds before branch (only if extraCharacteristics set)

const double * beforeUpper_

Pointer to upper bounds before branch (only if extraCharacteristics set)

int solverType_

Solver type 0 - normal LP solver 1 - DW - may also return heuristic solutions 2 - NLP solver or similar - can't compute objective value just from solution check this (rather than solver) to see if feasible and what objective value is.

· int sizeSolution_

Size of solution.

int extraCharacteristics_

Bit mask for odd actions of solvers 1 - solution or bound arrays may move in mysterious ways e.g.

7.6.1 Detailed Description

This class allows for the use of more exotic solvers e.g.

Non-Linear or Volume.

You can derive from this although at present I can't see the need.

Definition at line 49 of file OsiAuxInfo.hpp.

7.6.2 Member Function Documentation

7.6.2.1 void OsiBabSolver::setSolution (const double * solution, int numberColumns, double objectiveValue)

Set solution and objective value.

Number of columns and optimization direction taken from current solver. Size of solution is numberColumns (may be padded or truncated in function)

7.6.2.2 bool OsiBabSolver::hasSolution (double & solutionValue, double * solution)

returns true if the object stores a solution, false otherwise.

If there is a solution then solution Value and solution will be filled out as well. In that case the user needs to allocate solution to be a big enough array.

7.6.2.3 void OsiBabSolver::setSolverType (int value) [inline]

Sets solver type 0 - normal LP solver 1 - DW - may also return heuristic solutions 2 - NLP solver or similar - can't compute objective value just from solution check solver to see if feasible and what objective value is.

```
- may also return heuristic solution
```

- 3 NLP solver or similar can't compute objective value just from solution check this (rather than solver) to see if feasible and what objective value is. Using Outer Approximation so called lp based
 - · may also return heuristic solution 4 normal solver but cuts are needed for integral solution

Definition at line 102 of file OsiAuxInfo.hpp.

```
7.6.2.4 int OsiBabSolver::solverType() const [inline]
```

gets solver type 0 - normal LP solver 1 - DW - may also return heuristic solutions 2 - NLP solver or similar - can't compute objective value just from solution check this (rather than solver) to see if feasible and what objective value is

```
- may also return heuristic solution
```

- 3 NLP solver or similar can't compute objective value just from solution check this (rather than solver) to see if feasible and what objective value is. Using Outer Approximation so called lp based
 - · may also return heuristic solution 4 normal solver but cuts are needed for integral solution

Definition at line 116 of file OsiAuxInfo.hpp.

```
7.6.2.5 int OsiBabSolver::extraCharacteristics ( ) const [inline]
```

Get bit mask for odd actions of solvers 1 - solution or bound arrays may move in mysterious ways e.g.

cplex 2 - solver may want bounds before branch

Definition at line 152 of file OsiAuxInfo.hpp.

```
7.6.2.6 void OsiBabSolver::setExtraCharacteristics (int value) [inline]
```

Set bit mask for odd actions of solvers 1 - solution or bound arrays may move in mysterious ways e.g.

cplex 2 - solver may want bounds before branch

Definition at line 158 of file OsiAuxInfo.hpp.

7.6.3 Member Data Documentation

7.6.3.1 int OsiBabSolver::solverType_ [protected]

Solver type 0 - normal LP solver 1 - DW - may also return heuristic solutions 2 - NLP solver or similar - can't compute objective value just from solution check this (rather than solver) to see if feasible and what objective value is.

```
- may also return heuristic solution
```

- 3 NLP solver or similar can't compute objective value just from solution check this (rather than solver) to see if feasible and what objective value is. Using Outer Approximation so called lp based
 - · may also return heuristic solution

Definition at line 196 of file OsiAuxInfo.hpp.

7.6.3.2 int OsiBabSolver::extraCharacteristics_ [protected]

Bit mask for odd actions of solvers 1 - solution or bound arrays may move in mysterious ways e.g.

cplex 2 - solver may want bounds before branch

Definition at line 203 of file OsiAuxInfo.hpp.

The documentation for this class was generated from the following file:

· OsiAuxInfo.hpp

7.7 OsiBranchingInformation Class Reference

Collaboration diagram for OsiBranchingInformation:



Public Member Functions

OsiBranchingInformation ()

Default Constructor.

• OsiBranchingInformation (const OsiSolverInterface *solver, bool normalSolver, bool copySolution=false)

Useful Constructor (normalSolver true if has matrix etc etc) copySolution true if constructot should make a copy.

OsiBranchingInformation (const OsiBranchingInformation &)

Copy constructor.

OsiBranchingInformation & operator= (const OsiBranchingInformation &rhs)

Assignment operator.

virtual OsiBranchingInformation * clone () const

Clone.

virtual ∼OsiBranchingInformation ()

Destructor.

Public Attributes

int stateOfSearch

data

double objectiveValue

Value of objective function (in minimization sense)

double cutoff

Value of objective cutoff (in minimization sense)

double direction

Direction 1.0 for minimization, -1.0 for maximization.

double integerTolerance_

Integer tolerance.

double primalTolerance_

Primal tolerance.

double timeRemaining_

Maximum time remaining before stopping on time.

double defaultDual

Dual to use if row bound violated (if negative then pseudoShadowPrices off)

const OsiSolverInterface * solver_

Pointer to solver.

int numberColumns

The number of columns.

const double * lower_

Pointer to current lower bounds on columns.

const double * solution

Pointer to current solution.

const double * upper_

Pointer to current upper bounds on columns.

• const double * hotstartSolution_

Highly optional target (hot start) solution.

const double * pi_

Pointer to duals.

const double * rowActivity_

Pointer to row activity.

const double * objective_

Objective.

const double * rowLower_

Pointer to current lower bounds on rows.

const double * rowUpper

Pointer to current upper bounds on rows.

const double * elementByColumn_

Elements in column copy of matrix.

const CoinBigIndex * columnStart

Column starts.

• const int * columnLength_

Column lengths.

const int * row

Row indices.

double * usefulRegion

Useful region of length CoinMax(numberColumns,2*numberRows) This is allocated and deleted before OsiObject::infeasibility It is zeroed on entry and should be so on exit It only exists if defaultDual_>=0.0.

int * indexRegion_

Useful index region to go with usefulRegion .

int numberSolutions

Number of solutions found.

• int numberBranchingSolutions_

Number of branching solutions found (i.e. exclude heuristics)

· int depth_

Depth in tree.

bool owningSolution_

TEMP.

7.7.1 Detailed Description

Definition at line 367 of file OsiBranchingObject.hpp.

7.7.2 Member Data Documentation

7.7.2.1 int OsiBranchingInformation::stateOfSearch_

data

State of search 0 - no solution 1 - only heuristic solutions 2 - branched to a solution 3 - no solution but many nodes Definition at line 402 of file OsiBranchingObject.hpp.

The documentation for this class was generated from the following file:


OsiBranchingObject.hpp

7.8 OsiBranchingObject Class Reference


Abstract branching object base class.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiBranchingObject:



Collaboration diagram for OsiBranchingObject:



Public Member Functions

• OsiBranchingObject ()

Default Constructor.

• OsiBranchingObject (OsiSolverInterface *solver, double value)

Constructor.

• OsiBranchingObject (const OsiBranchingObject &)

Copy constructor.

• OsiBranchingObject & operator= (const OsiBranchingObject &rhs)

Assignment operator.

• virtual OsiBranchingObject * clone () const =0

Clone.

virtual ∼OsiBranchingObject ()

Destructor.

• int numberBranches () const

The number of branch arms created for this branching object.

· int numberBranchesLeft () const

The number of branch arms left for this branching object.

void incrementNumberBranchesLeft ()

Increment the number of branch arms left for this branching object.

void setNumberBranchesLeft (int)

Set the number of branch arms left for this branching object Just for forcing.

void decrementNumberBranchesLeft ()

Decrement the number of branch arms left for this branching object.

virtual double branch (OsiSolverInterface *solver)=0

Execute the actions required to branch, as specified by the current state of the branching object, and advance the object's state.

virtual double branch ()

Execute the actions required to branch, as specified by the current state of the branching object, and advance the object's state.

· virtual bool boundBranch () const

Return true if branch should fix variables.

• int branchIndex () const

Get the state of the branching object This is just the branch index.

void setBranchingIndex (int branchIndex)

Set the state of the branching object.

• double value () const

Current value.

const OsiObject * originalObject () const

Return pointer back to object which created.

void setOriginalObject (const OsiObject *object)

Set pointer back to object which created.

• virtual void checklsCutoff (double)

Double checks in case node can change its mind! Returns objective value Can change objective etc.

• int columnNumber () const

For debug.

virtual void print (const OsiSolverInterface *=NULL) const

Print something about branch - only if log level high.

Protected Attributes

double value

Current value - has some meaning about branch.

const OsiObject * originalObject_

Pointer back to object which created.

int numberBranches_

Number of branches.

short branchIndex

The state of the branching object.

7.8.1 Detailed Description

Abstract branching object base class.

In the abstract, an OsiBranchingObject contains instructions for how to branch. We want an abstract class so that we can describe how to branch on simple objects (*e.g.*, integers) and more exotic objects (*e.g.*, cliques or hyperplanes).

The branch() method is the crucial routine: it is expected to be able to step through a set of branch arms, executing the actions required to create each subproblem in turn. The base class is primarily virtual to allow for a wide range of problem modifications.

See OsiObject for an overview of the two classes (OsiObject and OsiBranchingObject) which make up Osi's branching model.

Definition at line 254 of file OsiBranchingObject.hpp.

7.8.2 Member Function Documentation

```
7.8.2.1 virtual double OsiBranchingObject::branch ( OsiSolverInterface * solver ) [pure virtual]
```

Execute the actions required to branch, as specified by the current state of the branching object, and advance the object's state.

Returns change in guessed objective on next branch

Implemented in OsiLotsizeBranchingObject, OsiSOSBranchingObject, OsiIntegerBranchingObject, and OsiTwoWay-BranchingObject.

```
7.8.2.2 virtual double OsiBranchingObject::branch() [inline], [virtual]
```

Execute the actions required to branch, as specified by the current state of the branching object, and advance the object's state.

Returns change in guessed objective on next branch

Definition at line 309 of file OsiBranchingObject.hpp.

7.8.3 Member Data Documentation

7.8.3.1 short OsiBranchingObject::branchIndex_ [protected]

The state of the branching object.

i.e. branch index This starts at 0 when created

Definition at line 360 of file OsiBranchingObject.hpp.

The documentation for this class was generated from the following file:


OsiBranchingObject.hpp

7.9 OsiChooseStrong Class Reference

This class chooses a variable to branch on.

#include <OsiChooseVariable.hpp>

Inheritance diagram for OsiChooseStrong:



Collaboration diagram for OsiChooseStrong:



Public Member Functions

OsiChooseStrong ()

Default Constructor.

OsiChooseStrong (const OsiSolverInterface *solver)

Constructor from solver (so we can set up arrays etc)

OsiChooseStrong (const OsiChooseStrong &)

Copy constructor.

• OsiChooseStrong & operator= (const OsiChooseStrong &rhs)

Assignment operator.

virtual OsiChooseVariable * clone () const

Clone.

virtual ∼OsiChooseStrong ()

Destructor.

virtual int setupList (OsiBranchingInformation *info, bool initialize)

Sets up strong list and clears all if initialize is true.

virtual int chooseVariable (OsiSolverInterface *solver, OsiBranchingInformation *info, bool fixVariables)

Choose a variable Returns - -1 Node is infeasible 0 Normal termination - we have a candidate 1 All looks satisfied - no candidate 2 We can change the bound on a variable - but we also have a strong branching candidate 3 We can change the bound on a variable - but we have a non-strong branching candidate 4 We can change the bound on a variable - no other candidates We can pick up branch from bestObjectIndex() and bestWhichWay() We can pick up a forced branch (can change bound) from firstForcedObjectIndex() and firstForcedWhichWay() If we have a solution then we can pick up from goodObjectiveValue() and goodSolution() If fixVariables is true then 2,3,4 are all really same as problem changed.

• int shadowPriceMode () const

Pseudo Shadow Price mode 0 - off 1 - use if no strong info 2 - use if strong not trusted 3 - use even if trusted.

void setShadowPriceMode (int value)

Set Shadow price mode.

const OsiPseudoCosts & pseudoCosts () const

Accessor method to pseudo cost object.

OsiPseudoCosts & pseudoCosts ()

Accessor method to pseudo cost object.

int numberBeforeTrusted () const

A feww pass-through methods to access members of pseudoCosts as if they were members of OsiChooseStrong object.

Protected Member Functions

 int doStrongBranching (OsiSolverInterface *solver, OsiBranchingInformation *info, int numberToDo, int return-Criterion)

This is a utility function which does strong branching on a list of objects and stores the results in OsiHotInfo.objects.

void resetResults (int num)

Clear out the results array.

Protected Attributes

int shadowPriceMode

Pseudo Shadow Price mode 0 - off 1 - use and multiply by strong info 2 - use.

OsiPseudoCosts pseudoCosts

The pseudo costs for the chooser.

OsiHotInfo * results_

The results of the strong branching done on the candidates where the pseudocosts were not sufficient.

int numResults

The number of OsiHotInfo objetcs that contain information.

7.9.1 Detailed Description

This class chooses a variable to branch on.

This chooses the variable and direction with reliability strong branching.

The flow is: a) initialize the process. This decides on strong branching list and stores indices of all infeasible objects b) do strong branching on list. If list is empty then just choose one candidate and return without strong branching. If not empty then go through list and return best. However we may find that the node is infeasible or that we can fix a variable. If so we return and it is up to user to call again (after fixing a variable).

Definition at line 318 of file OsiChooseVariable.hpp.

7.9.2 Member Function Documentation

7.9.2.1 virtual int OsiChooseStrong::setupList (OsiBranchingInformation * info, bool initialize) [virtual]

Sets up strong list and clears all if initialize is true.

Returns number of infeasibilities. If returns -1 then has worked out node is infeasible!

Reimplemented from OsiChooseVariable.

7.9.2.2 int OsiChooseStrong::doStrongBranching (OsiSolverInterface * solver, OsiBranchingInformation * info, int numberToDo, int returnCriterion) [protected]

This is a utility function which does strong branching on a list of objects and stores the results in OsiHotInfo.objects.

On entry the object sequence is stored in the OsiHotInfo object and maybe more. It returns - -1 - one branch was infeasible both ways 0 - all inspected - nothing can be fixed 1 - all inspected - some can be fixed (returnCriterion==0) 2 - may be returning early - one can be fixed (last one done) (returnCriterion==1) 3 - returning because max time

The documentation for this class was generated from the following file:


· OsiChooseVariable.hpp

7.10 OsiChooseVariable Class Reference

This class chooses a variable to branch on.

#include <OsiChooseVariable.hpp>

Inheritance diagram for OsiChooseVariable:



Collaboration diagram for OsiChooseVariable:



Public Member Functions

• OsiChooseVariable ()

Default Constructor.

• OsiChooseVariable (const OsiSolverInterface *solver)

Constructor from solver (so we can set up arrays etc)

OsiChooseVariable (const OsiChooseVariable &)

Copy constructor.

OsiChooseVariable & operator= (const OsiChooseVariable &rhs)

Assignment operator.

virtual OsiChooseVariable * clone () const

Clone.

virtual ∼OsiChooseVariable ()

Destructor.

virtual int setupList (OsiBranchingInformation *info, bool initialize)

Sets up strong list and clears all if initialize is true.

virtual int chooseVariable (OsiSolverInterface *solver, OsiBranchingInformation *info, bool fixVariables)

Choose a variable Returns - -1 Node is infeasible 0 Normal termination - we have a candidate 1 All looks satisfied - no candidate 2 We can change the bound on a variable - but we also have a strong branching candidate 3 We can change the bound on a variable - but we have a non-strong branching candidate 4 We can change the bound on a variable - no other candidates We can pick up branch from bestObjectIndex() and bestWhichWay() We can pick up a forced branch (can change bound) from firstForcedObjectIndex() and firstForcedWhichWay() If we have a solution then we can pick up from goodObjectiveValue() and goodSolution() If fixVariables is true then 2,3,4 are all really same as problem changed.

 virtual bool feasibleSolution (const OsiBranchingInformation *info, const double *solution, int numberObjects, const OsiObject **objects)

Returns true if solution looks feasible against given objects.

void saveSolution (const OsiSolverInterface *solver)

Saves a good solution.

· void clearGoodSolution ()

Clears out good solution after use.

virtual void updateInformation (const OsiBranchingInformation *info, int branch, OsiHotInfo *hotInfo)

Given a candidate fill in useful information e.g. estimates.

virtual void updateInformation (int whichObject, int branch, double changeInObjective, double changeInValue, int status)

Given a branch fill in useful information e.g. estimates.

double goodObjectiveValue () const

Objective value for feasible solution.

• double upChange () const

Estimate of up change or change on chosen if n-way.

• double downChange () const

Estimate of down change or max change on other possibilities if n-way.

const double * goodSolution () const

Good solution - deleted by finalize.

int bestObjectIndex () const

Index of chosen object.

void setBestObjectIndex (int value)

Set index of chosen object.

int bestWhichWay () const

Preferred way of chosen object.

void setBestWhichWay (int value)

Set preferred way of chosen object.

int firstForcedObjectIndex () const

Index of forced object.

void setFirstForcedObjectIndex (int value)

Set index of forced object.

int firstForcedWhichWay () const

Preferred way of forced object.

void setFirstForcedWhichWay (int value)

Set preferred way of forced object.

· int numberUnsatisfied () const

Get the number of objects unsatisfied at this node - accurate on first pass.

• int numberStrong () const

Number of objects to choose for strong branching.

void setNumberStrong (int value)

Set number of objects to choose for strong branching.

• int numberOnList () const

Number left on strong list.

int numberStrongDone () const

Number of strong branches actually done.

· int numberStrongIterations () const

Number of strong iterations actually done.

int numberStrongFixed () const

Number of strong branches which changed bounds.

• const int * candidates () const

List of candidates.

bool trustStrongForBound () const

Trust results from strong branching for changing bounds.

void setTrustStrongForBound (bool yesNo)

Set trust results from strong branching for changing bounds.

bool trustStrongForSolution () const

Trust results from strong branching for valid solution.

void setTrustStrongForSolution (bool yesNo)

Set trust results from strong branching for valid solution.

void setSolver (const OsiSolverInterface *solver)

Set solver and redo arrays.

• int status () const

Return status - -1 Node is infeasible 0 Normal termination - we have a candidate 1 All looks satisfied - no candidate 2 We can change the bound on a variable - but we also have a strong branching candidate 3 We can change the bound on a variable - but we have a non-strong branching candidate 4 We can change the bound on a variable - no other candidates We can pick up branch from bestObjectIndex() and bestWhichWay() We can pick up a forced branch (can change bound) from firstForcedObjectIndex() and firstForcedWhichWay() If we have a solution then we can pick up from goodObjectiveValue() and goodSolution()

Protected Attributes

double goodObjectiveValue_

Objective value for feasible solution.

double upChange_

Estimate of up change or change on chosen if n-way.

double downChange_

Estimate of down change or max change on other possibilities if n-way.

double * goodSolution_

Good solution - deleted by finalize.

int * list

List of candidates.

double * useful

Useful array (for sorting etc)

const OsiSolverInterface * solver

Pointer to solver.

int bestObjectIndex

Index of chosen object.

int bestWhichWay

Preferred way of chosen object.

int firstForcedObjectIndex

Index of forced object.

int firstForcedWhichWay_

Preferred way of forced object.

int numberUnsatisfied

The number of objects unsatisfied at this node.

int numberStrong

Number of objects to choose for strong branching.

int numberOnList

Number left on strong list.

int numberStrongDone_

Number of strong branches actually done.

• int numberStrongIterations_

Number of strong iterations actually done.

int numberStrongFixed_

Number of bound changes due to strong branching.

bool trustStrongForBound_

List of unsatisfied objects - first numberOnList_ for strong branching Trust results from strong branching for changing bounds.

bool trustStrongForSolution

Trust results from strong branching for valid solution.

7.10.1 Detailed Description

This class chooses a variable to branch on.

The base class just chooses the variable and direction without strong branching but it has information which would normally be used by strong branching e.g. to re-enter having fixed a variable but using same candidates for strong branching.

The flow is: a) initialize the process. This decides on strong branching list and stores indices of all infeasible objects b) do strong branching on list. If list is empty then just choose one candidate and return without strong branching. If not empty then go through list and return best. However we may find that the node is infeasible or that we can fix a variable. If so we return and it is up to user to call again (after fixing a variable).

Definition at line 33 of file OsiChooseVariable.hpp.

7.10.2 Member Function Documentation

7.10.2.1 virtual int OsiChooseVariable::setupList (OsiBranchingInformation * info, bool initialize) [virtual]

Sets up strong list and clears all if initialize is true.

Returns number of infeasibilities. If returns -1 then has worked out node is infeasible!

Reimplemented in OsiChooseStrong.

The documentation for this class was generated from the following file:


· OsiChooseVariable.hpp

7.11 OsiColCut Class Reference


Column Cut Class.

#include <OsiColCut.hpp>

Inheritance diagram for OsiColCut:



Collaboration diagram for OsiColCut:



Public Member Functions

Setting column bounds

void setLbs (int nElements, const int *colIndices, const double *lbElements)

Set column lower bounds.

void setLbs (const CoinPackedVector &lbs)

Set column lower bounds from a packed vector.

void setUbs (int nElements, const int *colIndices, const double *ubElements)

Set column upper bounds.

void setUbs (const CoinPackedVector &ubs)

Set column upper bounds from a packed vector.

Getting column bounds

• const CoinPackedVector & lbs () const

Get column lower bounds.

const CoinPackedVector & ubs () const

Get column upper bounds.

Comparison operators

virtual bool operator== (const OsiColCut &rhs) const

```
equal - true if lower bounds, upper bounds, and OsiCut are equal.
```

virtual bool operator!= (const OsiColCut &rhs) const

not equal

Sanity checks on cut

virtual bool consistent () const

Returns true if the cut is consistent with respect to itself.

· virtual bool consistent (const OsiSolverInterface &im) const

Returns true if cut is consistent with respect to the solver interface's model.

• virtual bool infeasible (const OsiSolverInterface &im) const

Returns true if the cut is infeasible with respect to its bounds and the column bounds in the solver interface's models.

virtual double violated (const double *solution) const

Returns infeasibility of the cut with respect to solution passed in i.e.

Constructors and destructors

OsiColCut & operator= (const OsiColCut &rhs)

Assignment operator.

OsiColCut (const OsiColCut &)

Copy constructor.

• OsiColCut ()

Default Constructor.

virtual OsiColCut * clone () const

Clone.

virtual ∼OsiColCut ()

Destructor.

Debug stuff

· virtual void print () const

Print cuts in collection.

Friends

• void OsiColCutUnitTest (const OsiSolverInterface *baseSiP, const std::string &mpsDir)

A function that tests the methods in the OsiColCut class.

Additional Inherited Members

7.11.1 Detailed Description

Column Cut Class.

Column Cut Class has:

- · a sparse vector of column lower bounds
- · a sparse vector of column upper bounds

Definition at line 23 of file OsiColCut.hpp.

7.11.2 Member Function Documentation

7.11.2.1 bool OsiColCut::consistent() const [inline], [virtual]

Returns true if the cut is consistent with respect to itself.

This checks to ensure that:

- · The bound vectors do not have duplicate indices,
- The bound vectors indices are >=0

Implements OsiCut.

Definition at line 226 of file OsiColCut.hpp.

7.11.2.2 bool OsiColCut::consistent (const OsiSolverInterface & im) const [inline], [virtual]

Returns true if cut is consistent with respect to the solver

interface's model.

This checks to ensure that the lower & upperbound packed vectors:

• do not have an index >= the number of column is the model.

Implements OsiCut.

Definition at line 239 of file OsiColCut.hpp.

7.11.2.3 bool OsiColCut::infeasible (const OsiSolverInterface & im) const [inline], [virtual]

Returns true if the cut is infeasible with respect to its bounds and the

column bounds in the solver interface's models.

This checks whether:

• the maximum of the new and existing lower bounds is strictly greater than the minimum of the new and existing upper bounds.

Implements OsiCut.

Definition at line 290 of file OsiColCut.hpp.

7.11.2.4 virtual double OsiColCut::violated (const double * solution) const [virtual]

Returns infeasibility of the cut with respect to solution passed in i.e.

is positive if cuts off that solution. solution is getNumCols() long..

Implements OsiCut.

7.11.3 Friends And Related Function Documentation

7.11.3.1 void OsiColCutUnitTest (const OsiSolverInterface * baseSiP, const std::string & mpsDir) [friend]

A function that tests the methods in the OsiColCut class.

The documentation for this class was generated from the following file:


· OsiColCut.hpp

7.12 OsiCpxSolverInterface Class Reference

CPLEX Solver Interface.

#include <OsiCpxSolverInterface.hpp>

 $Inheritance\ diagram\ for\ OsiCpxSolverInterface:$



Collaboration diagram for OsiCpxSolverInterface:



Public Member Functions

virtual void setObjSense (double s)

Set objective function sense (1 for min (default), -1 for max,)

virtual void setColSolution (const double *colsol)

Set the primal solution column values.

virtual void setRowPrice (const double *rowprice)

Set dual solution vector.

const char * getCtype () const

return a vector of variable types (continous, binary, integer)

Solve methods

• virtual void initialSolve ()

Solve initial LP relaxation.

virtual void resolve ()

Resolve an LP relaxation after problem modification.

• virtual void branchAndBound ()

Invoke solver's built-in enumeration algorithm.

Parameter set/get methods

The set methods return true if the parameter was set to the given value, false otherwise.

There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the volume algorithm), the parameter is not yet implemented for the solver or simply the value of the parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.

The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.

bool setIntParam (OsiIntParam key, int value)

Set an integer parameter.

• bool setDblParam (OsiDblParam key, double value)

Set a double parameter.

• bool setStrParam (OsiStrParam key, const std::string &value)

Set a string parameter.

· bool getIntParam (OsiIntParam key, int &value) const

Get an integer parameter.

• bool getDblParam (OsiDblParam key, double &value) const

Get a double parameter.

bool getStrParam (OsiStrParam key, std::string &value) const

Get a string parameter.

- void setMipStart (bool value)
- bool getMipStart () const

Methods returning info on how the solution process terminated

· virtual bool isAbandoned () const

Are there a numerical difficulties?

virtual bool isProvenOptimal () const

Is optimality proven?

• virtual bool isProvenPrimalInfeasible () const

Is primal infeasiblity proven?

virtual bool isProvenDualInfeasible () const

Is dual infeasiblity proven?

virtual bool isPrimalObjectiveLimitReached () const

Is the given primal objective limit reached?

virtual bool isDualObjectiveLimitReached () const

Is the given dual objective limit reached?

virtual bool isIterationLimitReached () const

Iteration limit reached?

WarmStart related methods

CoinWarmStart * getEmptyWarmStart () const

Get an empty warm start object.

• virtual CoinWarmStart * getWarmStart () const

Get warmstarting information.

virtual bool setWarmStart (const CoinWarmStart *warmstart)

Set warmstarting information.

Hotstart related methods (primarily used in strong branching).

 tr>

The user can create a hotstart (a snapshot) of the optimization process then reoptimize over and over again always starting from there.

NOTE: between hotstarted optimizations only bound changes are allowed.

virtual void markHotStart ()

Create a hotstart point of the optimization process.

virtual void solveFromHotStart ()

Optimize starting from the hotstart.

· virtual void unmarkHotStart ()

Delete the snapshot.

Methods related to querying the input data

• virtual int getNumCols () const

Get number of columns.

virtual int getNumRows () const

Get number of rows.

virtual int getNumElements () const

Get number of nonzero elements.

virtual const double * getColLower () const

Get pointer to array[getNumCols()] of column lower bounds.

virtual const double * getColUpper () const

Get pointer to array[getNumCols()] of column upper bounds.

virtual const char * getRowSense () const

Get pointer to array[getNumRows()] of row constraint senses.

virtual const double * getRightHandSide () const

Get pointer to array[getNumRows()] of rows right-hand sides.

virtual const double * getRowRange () const

Get pointer to array[getNumRows()] of row ranges.

virtual const double * getRowLower () const

Get pointer to array[getNumRows()] of row lower bounds.

virtual const double * getRowUpper () const

Get pointer to array[getNumRows()] of row upper bounds.

virtual const double * getObjCoefficients () const

Get pointer to array[getNumCols()] of objective function coefficients.

virtual double getObjSense () const

Get objective function sense (1 for min (default), -1 for max)

virtual bool isContinuous (int colNumber) const

Return true if column is continuous.

virtual const CoinPackedMatrix * getMatrixByRow () const

Get pointer to row-wise copy of matrix.

virtual const CoinPackedMatrix * getMatrixByCol () const

Get pointer to column-wise copy of matrix.

virtual double getInfinity () const

Get solver's value for infinity.

Methods related to querying the solution

virtual const double * getColSolution () const

Get pointer to array[getNumCols()] of primal solution vector.

virtual const double * getRowPrice () const

Get pointer to array[getNumRows()] of dual prices.

virtual const double * getReducedCost () const

Get a pointer to array[getNumCols()] of reduced costs.

virtual const double * getRowActivity () const

Get pointer to array[getNumRows()] of row activity levels (constraint matrix times the solution vector.

virtual double getObjValue () const

Get objective function value.

virtual int getIterationCount () const

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

virtual std::vector< double * > getDualRays (int maxNumRays, bool fullRay=false) const

Get as many dual rays as the solver can provide.

virtual std::vector< double * > getPrimalRays (int maxNumRays) const

Get as many primal rays as the solver can provide.

Changing bounds on variables and constraints

virtual void setObjCoeff (int elementIndex, double elementValue)

Set an objective function coefficient.

virtual void setObjCoeffSet (const int *indexFirst, const int *indexLast, const double *coeffList)

Set a a set of objective function coefficients.

• virtual void setColLower (int elementIndex, double elementValue)

Set a single column lower bound

Use -COIN_DBL_MAX for -infinity.

virtual void setColUpper (int elementIndex, double elementValue)

Set a single column upper bound

Use COIN_DBL_MAX for infinity.

virtual void setColBounds (int elementIndex, double lower, double upper)

Set a single column lower and upper bound

The default implementation just invokes setColLower() and setColUpper()

virtual void setColSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of columns simultaneously

The default implementation just invokes setCollower() and setColupper() over and over again.

virtual void setRowLower (int elementIndex, double elementValue)

Set a single row lower bound

Use -COIN_DBL_MAX for -infinity.

virtual void setRowUpper (int elementIndex, double elementValue)

Set a single row upper bound

Use COIN DBL MAX for infinity.

virtual void setRowBounds (int elementIndex, double lower, double upper)

Set a single row lower and upper bound

The default implementation just invokes setRowLower() and setRowUpper()

• virtual void setRowType (int index, char sense, double rightHandSide, double range)

Set the type of a single row

virtual void setRowSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

 virtual void setRowSetTypes (const int *indexFirst, const int *indexLast, const char *senseList, const double *rhsList, const double *rangeList)

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType () and over and over again.

Integrality related changing methods

virtual void setContinuous (int index)

Set the index-th variable to be a continuous variable.

virtual void setInteger (int index)

Set the index-th variable to be an integer variable.

virtual void setContinuous (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be continuous variables.

virtual void setInteger (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be integer variables.

Methods to expand a problem.

Note that if a column is added then by default it will correspond to a continuous variable.

virtual void addCol (const CoinPackedVectorBase &vec, const double collb, const double collb, const double collb, const double collb)

Add a column (primal variable) to the problem.

virtual void addCols (const int numcols, const CoinPackedVectorBase *const *cols, const double *collb, const double *collb, const double *obj)

Add a set of columns (primal variables) to the problem.

virtual void deleteCols (const int num, const int *colIndices)

Remove a set of columns (primal variables) from the problem.

virtual void addRow (const CoinPackedVectorBase &vec, const double rowlb, const double rowlb)

Add a row (constraint) to the problem.

 virtual void addRow (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng)

Add a row (constraint) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const double *rowlb, const double *rowub)

Add a set of rows (constraints) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const char *rowsen, const double *rowrhs, const double *rowrng)

Add a set of rows (constraints) to the problem.

virtual void deleteRows (const int num, const int *rowIndices)

Delete a set of rows (constraints) from the problem.

Methods to input a problem

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowlb, const double *rowlb)

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, double *&rowlb, double *&rowlb)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *collb, const double *rowrng)

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

 virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, char *&rowsen, double *&rowrhs, double *&rowrng)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowlb, const double *rowlb,

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

 virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *colub, const double *obj, const char *rowsen, const double *rowrhs, const double *rowrng)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

virtual int readMps (const char *filename, const char *extension="mps")

Read an mps file from the given filename.

• virtual void writeMps (const char *filename, const char *extension="mps", double objSense=0.0) const Write the problem into an mps file of the given filename.

Message handling

void passInMessageHandler (CoinMessageHandler *handler)

Pass in a message handler It is the client's responsibility to destroy a message handler installed by this routine; it will not be destroyed when the solver interface is destroyed.

Constructors and destructor

• OsiCpxSolverInterface ()

Default Constructor.

virtual OsiSolverInterface * clone (bool copyData=true) const

Clone.

OsiCpxSolverInterface (const OsiCpxSolverInterface &)

Copy constructor.

OsiCpxSolverInterface & operator= (const OsiCpxSolverInterface &rhs)

Assignment operator.

virtual ∼OsiCpxSolverInterface ()

Destructor.

• virtual void reset ()

Resets as if default constructor.

OsiSimplexInterface methods

Cplex adds a slack with coeff +1 in "<=" and "=" constraints, with coeff -1 in ">=", slack being non negative.

We switch in order to get a "Clp tableau" where all the slacks have coefficient +1 in the original tableau.

If a slack for ">=" is non basic, invB is not changed; column of the slack in the optimal tableau is flipped.

If a slack for ">=" is basic, corresp. row of invB is flipped; whole row of the optimal tableau is flipped; then whole column for the slack in opt tableau is flipped.

Ranged rows are not supported. It might work, but no garantee is given.

Code implemented only for Cplex9.0 and higher, lower version number of Cplex will abort the code.

virtual int canDoSimplexInterface () const

Returns 1 if can just do getBlnv etc 2 if has all OsiSimplex methods and 0 if it has none.

virtual void enableSimplexInterface (int doingPrimal)

Useless function, defined only for compatibility with OsiSimplexInterface.

virtual void disableSimplexInterface ()

Useless function, defined only for compatibility with OsiSimplexInterface.

· virtual void enableFactorization () const

Useless function, defined only for compatibility with OsiSimplexInterface.

virtual void disableFactorization () const

Useless function, defined only for compatibility with OsiSimplexInterface.

virtual bool basisIsAvailable () const

Returns true if a basis is available.

virtual void getBasisStatus (int *cstat, int *rstat) const

Returns a basis status of the structural/artificial variables At present as warm start i.e 0: free, 1: basic, 2: upper, 3: lower.

virtual void getBInvARow (int row, double *z, double *slack=NULL) const

Get a row of the tableau (slack part in slack if not NULL)

virtual void getBlnvRow (int row, double *z) const

Get a row of the basis inverse.

virtual void getBInvACol (int col, double *vec) const

Get a column of the tableau.

virtual void getBlnvCol (int col, double *vec) const

Get a column of the basis inverse.

virtual void getBasics (int *index) const

Get indices of the pivot variable in each row (order of indices corresponds to the order of elements in a vector retured by getBlnvACol() and getBlnvCol()).

void switchToLP ()

switches CPLEX to prob type LP

void switchToMIP ()

switches CPLEX to prob type MIP

Protected Member Functions

Protected methods

virtual void applyRowCut (const OsiRowCut &rc)

Apply a row cut. Return true if cut was applied.

virtual void applyColCut (const OsiColCut &cc)

Apply a column cut (bound adjustment).

Friends

void OsiCpxSolverInterfaceUnitTest (const std::string &mpsDir, const std::string &netlibDir)

A function that tests the methods in the OsiCpxSolverInterface class.

CPLEX specific public interfaces

enum keepCachedFlag {
 KEEPCACHED_NONE = 0, KEEPCACHED_COLUMN = 1, KEEPCACHED_ROW = 2, KEEPCACHED_MATRIX
 = 4,

KEEPCACHED_RESULTS = 8, KEEPCACHED_PROBLEM = KEEPCACHED_COLUMN | KEEPCACHED_ROW | KEEPCACHED_MATRIX, KEEPCACHED_ALL = KEEPCACHED_PROBLEM | KEEPCACHED_RESULTS, FREECACHED_COLUMN = KEEPCACHED_PROBLEM & ~KEEPCACHED_COLUMN, FREECACHED_ROW = KEEPCACHED_PROBLEM & ~KEEPCACHED_ROW, FREECACHED_MATRIX = K-EEPCACHED_PROBLEM & ~KEEPCACHED_MATRIX, FREECACHED_RESULTS = KEEPCACHED_ALL & ~KEEPCACHED_RESULTS }

Get pointer to CPLEX model and free all specified cached data entries (combined with logical or-operator '|'):

- CPXLPptr getLpPtr (int keepCached=KEEPCACHED NONE)
- CPXENVptr getEnvironmentPtr ()

Method to access CPLEX environment pointer.

Additional Inherited Members

7.12.1 Detailed Description

CPLEX Solver Interface.

Instantiation of OsiCpxSolverInterface for CPLEX

Definition at line 29 of file OsiCpxSolverInterface.hpp.

7.12.2 Member Enumeration Documentation

7.12.2.1 enum OsiCpxSolverInterface::keepCachedFlag

Get pointer to CPLEX model and free all specified cached data entries (combined with logical or-operator '|'):

Enumerator:

KEEPCACHED_NONE discard all cached data (default)

KEEPCACHED_COLUMN column information: objective values, lower and upper bounds, variable types **KEEPCACHED_ROW** row information: right hand sides, ranges and senses, lower and upper bounds for row

KEEPCACHED_MATRIX problem matrix: matrix ordered by column and by row

KEEPCACHED_RESULTS LP solution: primal and dual solution, reduced costs, row activities.

KEEPCACHED_PROBLEM only discard cached LP solution

KEEPCACHED_ALL keep all cached data (similar to getMutableLpPtr())

FREECACHED_COLUMN free only cached column and LP solution information

FREECACHED_ROW free only cached row and LP solution information

FREECACHED_MATRIX free only cached matrix and LP solution information

FREECACHED RESULTS free only cached LP solution information

Definition at line 614 of file OsiCpxSolverInterface.hpp.

7.12.3 Member Function Documentation

```
7.12.3.1 CoinWarmStart* OsiCpxSolverInterface::getEmptyWarmStart( ) const [virtual]
```

Get an empty warm start object.

This routine returns an empty **CoinWarmStartBasis** object. Its purpose is to provide a way to give a client a warm start basis object of the appropriate type, which can resized and modified as desired.

Implements OsiSolverInterface.

```
7.12.3.2 virtual bool OsiCpxSolverInterface::setWarmStart ( const CoinWarmStart * warmstart ) [virtual]
```

Set warmstarting information.

Return true/false depending on whether the warmstart information was accepted or not.

Implements OsiSolverInterface.

```
7.12.3.3 virtual const char* OsiCpxSolverInterface::getRowSense() const [virtual]
```

Get pointer to array[getNumRows()] of row constraint senses.

- 'L': <= constraint
- 'E': = constraint
- 'G': >= constraint
- · 'R': ranged constraint
- · 'N': free constraint

Implements OsiSolverInterface.

```
7.12.3.4 virtual const double* OsiCpxSolverInterface::getRightHandSide( ) const [virtual]
```

Get pointer to array[getNumRows()] of rows right-hand sides.

- if rowsense()[i] == 'L' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'G' then rhs()[i] == rowlower()[i]
- if rowsense()[i] == 'R' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'N' then rhs()[i] == 0.0

Implements OsiSolverInterface.

7.12.3.5 virtual const double* OsiCpxSolverInterface::getRowRange() const [virtual]

Get pointer to array[getNumRows()] of row ranges.

- if rowsense()[i] == 'R' then rowrange()[i] == rowupper()[i] rowlower()[i]
- if rowsense()[i] != 'R' then rowrange()[i] is 0.0

Implements OsiSolverInterface.

7.12.3.6 virtual int OsiCpxSolverInterface::getIterationCount() const [virtual]

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

Implements OsiSolverInterface.

7.12.3.7 virtual std::vector<double*> OsiCpxSolverInterface::getDualRays (int maxNumRays, bool fullRay = false) const [virtual]

Get as many dual rays as the solver can provide.

(In case of proven primal infeasibility there should be at least one.)

The first getNumRows() ray components will always be associated with the row duals (as returned by getRowPrice()). If fullRay is true, the final getNumCols() entries will correspond to the ray components associated with the nonbasic variables. If the full ray is requested and the method cannot provide it, it will throw an exception.

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumRows() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

7.12.3.8 virtual std::vector<double*> OsiCpxSolverInterface::getPrimalRays (int maxNumRays) const [virtual]

Get as many primal rays as the solver can provide.

(In case of proven dual infeasibility there should be at least one.)

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumCols() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

7.12.3.9 virtual void OsiCpxSolverInterface::setColLower (int elementIndex, double elementValue) [virtual]

Set a single column lower bound

Use -COIN_DBL_MAX for -infinity.

Implements OsiSolverInterface.

7.12.3.10 virtual void OsiCpxSolverInterface::setColUpper (int elementIndex, double elementValue) [virtual]

Set a single column upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.12.3.11 virtual void OsiCpxSolverInterface::setColSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of columns simultaneously

The default implementation just invokes setCollower() and setColupper() over and over again.

Parameters

	contains the indices of the constraints whose either bound changes
<code>[indexfirst,</code>	index-
Last]	
boundList	the new lower/upper bound pairs for the variables

Reimplemented from OsiSolverInterface.

7.12.3.12 virtual void OsiCpxSolverInterface::setRowLower(int elementIndex, double elementValue) [virtual]

Set a single row lower bound

Use -COIN_DBL_MAX for -infinity.

Implements OsiSolverInterface.

7.12.3.13 virtual void OsiCpxSolverInterface::setRowUpper(int elementIndex, double elementValue) [virtual]

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.12.3.14 virtual void OsiCpxSolverInterface::setRowSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

Parameters

Ī		contains the indices of the constraints whose either bound changes
	<code>[indexfirst,</code>	index-
	Last]	
İ	boundList	the new lower/upper bound pairs for the constraints

Reimplemented from OsiSolverInterface.

7.12.3.15 virtual void OsiCpxSolverInterface::setRowSetTypes (const int * indexFirst, const int * indexLast, const char * senseList, const double * rhsList, const double * rangeList) [virtual]

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType () and over and over again.

Parameters

	contains the indices of the constraints whose type changes
<code>[indexfirst,</code>	index-
Last]	
senseList	the new senses
rhsList	the new right hand sides
rangeList	the new ranges

Reimplemented from OsiSolverInterface.

7.12.3.16 virtual void OsiCpxSolverInterface::setColSolution (const double * colsol) [virtual]

Set the primal solution column values.

colsol[numcols()] is an array of values of the problem column variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of colsol() until changed by another call to setColsol() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.12.3.17 virtual void OsiCpxSolverInterface::setRowPrice (const double * rowprice) [virtual]

Set dual solution vector.

rowprice[numrows()] is an array of values of the problem row dual variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of rowprice() until changed by another call to setRowprice() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.12.3.18 virtual void OsiCpxSolverInterface::addCol (const CoinPackedVectorBase & vec, const double collb, const double collb, const double obj) [virtual]

Add a column (primal variable) to the problem.

Implements OsiSolverInterface.

7.12.3.19 virtual void OsiCpxSolverInterface::addCols (const int *numcols*, const CoinPackedVectorBase *const * cols, const double * collb, const double * collb, const double * obj) [virtual]

Add a set of columns (primal variables) to the problem.

The default implementation simply makes repeated calls to addCol().

Reimplemented from OsiSolverInterface.

7.12.3.20 virtual void OsiCpxSolverInterface::deleteCols (const int num, const int * colIndices) [virtual]

Remove a set of columns (primal variables) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted variables are nonbasic.

Implements OsiSolverInterface.

7.12.3.21 virtual void OsiCpxSolverInterface::addRow (const CoinPackedVectorBase & vec, const double rowlb, const double rowub) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.12.3.22 virtual void OsiCpxSolverInterface::addRow(const CoinPackedVectorBase & vec, const char rowsen, const double rowrns, const double rowrng) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.12.3.23 virtual void OsiCpxSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * *rows*, const double * *rowlb*, const double * *rowub*) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.12.3.24 virtual void OsiCpxSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * *rows*, const char * *rowsen*, const double * *rowrhs*, const double * *rowrng*) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.12.3.25 virtual void OsiCpxSolverInterface::deleteRows (const int num, const int * rowIndices) [virtual]

Delete a set of rows (constraints) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted rows are loose. Implements OsiSolverInterface.

```
7.12.3.26 virtual void OsiCpxSolverInterface::loadProblem ( const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowlb, const double * rowlb, const double * rowlb ) [virtual]
```

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- · rowub: all rows have upper bound infinity
- rowlb: all rows have lower bound -infinity
- obj: all variables have 0 objective coefficient

Implements OsiSolverInterface.

7.12.3.27 virtual void OsiCpxSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& rowlb, double *& rowlb) [virtual]

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions.

Implements OsiSolverInterface.

```
7.12.3.28 virtual void OsiCpxSolverInterface::loadProblem ( const CoinPackedMatrix & matrix, const double * collb, const double * colub, const double * colub, const double * rowrns, const double * rowrns )

[virtual]
```

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets). If a pointer is 0 then the following values are the default:

colub: all columns have upper bound infinity

• collb: all columns have lower bound 0

• obj: all variables have 0 objective coefficient

• rowsen: all rows are >=

• rowrhs: all right hand sides are 0

rowrng: 0 for the ranged rows

Implements OsiSolverInterface.

```
7.12.3.29 virtual void OsiCpxSolverInterface::assignProblem ( CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowrng ) [virtual]
```

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

```
7.12.3.30 virtual void OsiCpxSolverInterface::loadProblem ( const int numcols, const int numrows, const int * start, const int * index, const double * value, const double * collb, const double * collb, const double * obj, const double * rowlb, const double * rowub ) [virtual]
```

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

```
7.12.3.31 virtual void OsiCpxSolverInterface::loadProblem ( const int numcols, const int numrows, const int * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const char * rowsen, const double * rowrhs, const double * rowrng ) [virtual]
```

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

```
7.12.3.32 virtual void OsiCpxSolverInterface::writeMps ( const char * filename, const char * extension = "mps", double objSense = 0.0 ) const [virtual]
```

Write the problem into an mps file of the given filename.

If objSense is non zero then -1.0 forces the code to write a maximization objective and +1.0 to write a minimization one. If 0.0 then solver can do what it wants

Implements OsiSolverInterface.

7.12.3.33 virtual void OsiCpxSolverInterface::applyColCut (const OsiColCut & cc) [protected], [virtual]

Apply a column cut (bound adjustment).

Return true if cut was applied.

Implements OsiSolverInterface.

7.12.4 Friends And Related Function Documentation

7.12.4.1 void OsiCpxSolverInterfaceUnitTest (const std::string & mpsDir, const std::string & netlibDir) [friend]


A function that tests the methods in the OsiCpxSolverInterface class.

The documentation for this class was generated from the following file:

• OsiCpxSolverInterface.hpp

7.13 OsiCut Class Reference

Inheritance diagram for OsiCut:



Public Member Functions

Effectiveness

- void setEffectiveness (double e)
 - Set effectiveness.
- double effectiveness () const

Get effectiveness.

GloballyValid

void setGloballyValid (bool trueFalse)

Set globallyValid (nonzero true)

- void setGloballyValid ()
- void setNotGloballyValid ()
- bool globallyValid () const

Get globally Valid.

void setGloballyValidAsInteger (int trueFalse)

Set globally Valid as integer (nonzero true)

int globallyValidAsInteger () const

Get globally Valid.

Debug stuff

virtual void print () const

Print cuts in collection.

Comparison operators

• virtual bool operator== (const OsiCut &rhs) const

equal. 2 cuts are equal if there effectiveness are equal

virtual bool operator!= (const OsiCut &rhs) const

not equal

virtual bool operator< (const OsiCut &rhs) const

less than. True if this.effectiveness < rhs.effectiveness

virtual bool operator> (const OsiCut &rhs) const

less than. True if this.effectiveness > rhs.effectiveness

Sanity checks on cut

virtual bool consistent () const =0

Returns true if the cut is consistent with respect to itself, without considering any data in the model.

virtual bool consistent (const OsiSolverInterface &si) const =0

Returns true if cut is consistent when considering the solver interface's model.

virtual bool infeasible (const OsiSolverInterface &si) const =0

Returns true if the cut is infeasible "with respect to itself" and cannot be satisfied.

virtual double violated (const double *solution) const =0

Returns infeasibility of the cut with respect to solution passed in i.e.

Protected Member Functions

Constructors and destructors

• OsiCut ()

Default Constructor.

• OsiCut (const OsiCut &)

Copy constructor.

• OsiCut & operator= (const OsiCut &rhs)

Assignment operator.

virtual ∼OsiCut ()

Destructor.

7.13.1 Detailed Description

Definition at line 36 of file OsiCut.hpp.

7.13.2 Member Function Documentation

```
7.13.2.1 virtual bool OsiCut::consistent ( ) const [inline], [pure virtual]
```

Returns true if the cut is consistent with respect to itself, without considering any data in the model.

For example, it might check to ensure that a column index is not negative.

Implemented in OsiRowCut, and OsiColCut.

```
7.13.2.2 virtual bool OsiCut::consistent (const OsiSolverInterface & si) const [inline], [pure virtual]
```

Returns true if cut is consistent when considering the solver interface's model.

For example, it might check to ensure that a column index is not greater than the number of columns in the model. Assumes consistent() is true.

Implemented in OsiRowCut, and OsiColCut.

```
7.13.2.3 virtual bool OsiCut::infeasible (const OsiSolverInterface & si) const [inline], [pure virtual]
```

Returns true if the cut is infeasible "with respect to itself" and cannot be satisfied.

This method does NOT check whether adding the cut to the solver interface's model will make the -model- infeasible. A cut which returns !infeasible(si) may very well make the model infeasible. (Of course, adding a cut with returns infeasible(si) will make the model infeasible.)

The "with respect to itself" is in quotes becaues in the case where the cut simply replaces existing bounds, it may make sense to test infeasibility with respect to the current bounds held in the solver interface's model. For example, if the cut has a single variable in it, it might check that the maximum of new and existing lower bounds is greater than the minium of the new and existing upper bounds.

Assumes that consistent(si) is true.

Infeasible cuts can be a useful mechanism for a cut generator to inform the solver interface that its detected infeasibility of the problem.

Implemented in OsiRowCut, and OsiColCut.

```
7.13.2.4 virtual double OsiCut::violated ( const double * solution ) const [pure virtual]
```

Returns infeasibility of the cut with respect to solution passed in i.e.

is positive if cuts off that solution. solution is getNumCols() long..

Implemented in OsiRowCut, and OsiColCut.

The documentation for this class was generated from the following file:

· OsiCut.hpp

7.14 OsiCuts Class Reference

Collections of row cuts and column cuts.

```
#include <OsiCuts.hpp>
```

Classes

· class const iterator

Const Iterator.

· class iterator

Iterator.

class OsiCutCompare

Public Member Functions

Inserting a cut into collection

void insert (const OsiRowCut &rc)

Insert a row cut.

void insertlfNotDuplicate (OsiRowCut &rc, CoinAbsFltEq treatAsSame=CoinAbsFltEq(1.0e-12))

Insert a row cut unless it is a duplicate - cut may get sorted.

void insertIfNotDuplicate (OsiRowCut &rc, CoinRelFltEq treatAsSame)

Insert a row cut unless it is a duplicate - cut may get sorted.

void insert (const OsiColCut &cc)

Insert a column cut.

void insert (OsiRowCut *&rcPtr)

Insert a row cut.

void insert (OsiColCut *&ccPtr)

Insert a column cut.

• void insert (const OsiCuts &cs)

Insert a set of cuts.

Number of cuts in collection

• int sizeRowCuts () const

Number of row cuts in collection.

• int sizeColCuts () const

Number of column cuts in collection.

• int sizeCuts () const

Number of cuts in collection.

Debug stuff

• void printCuts () const

Print cuts in collection.

Get a cut from collection

• OsiRowCut * rowCutPtr (int i)

Get pointer to i'th row cut.

• const OsiRowCut * rowCutPtr (int i) const

Get const pointer to i'th row cut.

OsiColCut * colCutPtr (int i)

Get pointer to i'th column cut.

const OsiColCut * colCutPtr (int i) const

Get const pointer to i'th column cut.

OsiRowCut & rowCut (int i)

Get reference to i'th row cut.

const OsiRowCut & rowCut (int i) const

Get const reference to i'th row cut.

OsiColCut & colCut (int i)

Get reference to i'th column cut.

· const OsiColCut & colCut (int i) const

Get const reference to i'th column cut.

const OsiCut * mostEffectiveCutPtr () const

Get const pointer to the most effective cut.

OsiCut * mostEffectiveCutPtr ()

Get pointer to the most effective cut.

Deleting cut from collection

• void eraseRowCut (int i)

Remove i'th row cut from collection.

void eraseColCut (int i)

Remove i'th column cut from collection.

OsiRowCut * rowCutPtrAndZap (int i)

Get pointer to i'th row cut and remove ptr from collection.

void dumpCuts ()

Clear all row cuts without deleting them.

void eraseAndDumpCuts (const std::vector< int > to_erase)

Selective delete and clear for row cuts.

Sorting collection

• void sort ()

Cuts with greatest effectiveness are first.

Iterators

Example of using an iterator to sum effectiveness of all cuts in the collection.

• iterator begin ()

Get iterator to beginning of collection.

const_iterator begin () const

Get const iterator to beginning of collection.

• iterator end ()

Get iterator to end of collection.

· const_iterator end () const

Get const iterator to end of collection.

Constructors and destructors

• OsiCuts ()

Default constructor.

• OsiCuts (const OsiCuts &)

Copy constructor.

OsiCuts & operator= (const OsiCuts &rhs)

Assignment operator.

virtual ∼OsiCuts ()

Destructor.

Friends

void OsiCutsUnitTest ()

A function that tests the methods in the OsiCuts class.

7.14.1 Detailed Description

Collections of row cuts and column cuts.

Definition at line 19 of file OsiCuts.hpp.

7.14.2 Member Function Documentation

7.14.2.1 void OsiCuts::insertlfNotDuplicate (OsiRowCut & rc, CoinAbsFltEq treatAsSame = CoinAbsFltEq (1.0e-12))

Insert a row cut unless it is a duplicate - cut may get sorted.

Duplicate is defined as CoinAbsFItEq says same

7.14.2.2 void OsiCuts::insertIfNotDuplicate (OsiRowCut & rc, CoinRelFltEq treatAsSame)

Insert a row cut unless it is a duplicate - cut may get sorted.

Duplicate is defined as CoinRelFItEq says same

7.14.2.3 void OsiCuts::insert (OsiRowCut *& rcPtr) [inline]

Insert a row cut.

The OsiCuts object takes control of the cut object. On return, rcPtr is NULL.

Definition at line 319 of file OsiCuts.hpp.

```
7.14.2.4 void OsiCuts::insert ( OsiColCut *& ccPtr ) [inline]
```

Insert a column cut.

The OsiCuts object takes control of the cut object. On return ccPtr is NULL.

Definition at line 324 of file OsiCuts.hpp.

```
7.14.2.5 void OsiCuts::dumpCuts() [inline]
```

Clear all row cuts without deleting them.

Handy in case one wants to use CGL without managing cuts in one of the OSI containers. Client is ultimately responsible for deleting the data structures holding the row cuts.

Definition at line 461 of file OsiCuts.hpp.

7.14.2.6 void OsiCuts::eraseAndDumpCuts (const std::vector < int > to_erase) [inline]

Selective delete and clear for row cuts.

Deletes the cuts specified in to_erase then clears remaining cuts without deleting them. A hybrid of eraseRowCut(int) and dumpCuts(). Client is ultimately responsible for deleting the data structures for row cuts not specified in to_erase .

Definition at line 465 of file OsiCuts.hpp.

7.14.3 Friends And Related Function Documentation

7.14.3.1 void OsiCutsUnitTest() [friend]


A function that tests the methods in the OsiCuts class.

The documentation for this class was generated from the following file:


· OsiCuts.hpp

7.15 OsiGlpkSolverInterface Class Reference

Inheritance diagram for OsiGlpkSolverInterface:



Collaboration diagram for OsiGlpkSolverInterface:



Public Member Functions

- virtual void setObjSense (double s)
 - Set objective function sense (1 for min (default), -1 for max,)
- virtual void setColSolution (const double *colsol)

Set the primal solution column values.

virtual void setRowPrice (const double *rowprice)

Set dual solution vector.

Solve methods

• virtual void initialSolve ()

Solve initial LP relaxation.

• virtual void resolve ()

Resolve an LP relaxation after problem modification.

virtual void branchAndBound ()

Invoke solver's built-in enumeration algorithm.

Parameter set/get methods

The set methods return true if the parameter was set to the given value, false otherwise.

There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the volume algorithm), the parameter is not yet implemented for the solver or simply the value of the parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.

The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.

bool setIntParam (OsiIntParam key, int value)

Set an integer parameter.

bool setDblParam (OsiDblParam key, double value)

Set a double parameter.

bool setStrParam (OsiStrParam key, const std::string &value)

Set a string parameter.

- bool setHintParam (OsiHintParam key, bool sense=true, OsiHintStrength strength=OsiHintTry, void *info=0)
 Set a hint parameter.
- bool getIntParam (OsiIntParam key, int &value) const

Get an integer parameter.

• bool getDblParam (OsiDblParam key, double &value) const

Get a double parameter.

• bool getStrParam (OsiStrParam key, std::string &value) const

Get a string parameter.

Methods returning info on how the solution process terminated

· virtual bool isAbandoned () const

Are there a numerical difficulties?

• virtual bool isProvenOptimal () const

Is optimality proven?

• virtual bool isProvenPrimalInfeasible () const

Is primal infeasiblity proven?

virtual bool isProvenDualInfeasible () const

Is dual infeasiblity proven?

virtual bool isPrimalObjectiveLimitReached () const

Is the given primal objective limit reached?

· virtual bool isDualObjectiveLimitReached () const

Is the given dual objective limit reached?

virtual bool isIterationLimitReached () const

Iteration limit reached?

virtual bool isTimeLimitReached () const

Time limit reached?

• virtual bool isFeasible () const

(Integer) Feasible solution found?

WarmStart related methods

CoinWarmStart * getEmptyWarmStart () const

Get an empty warm start object.

virtual CoinWarmStart * getWarmStart () const

Get warmstarting information.

virtual bool setWarmStart (const CoinWarmStart *warmstart)

Set warmstarting information.

Hotstart related methods (primarily used in strong branching).

 tr>

The user can create a hotstart (a snapshot) of the optimization process then reoptimize over and over again always starting from there.

NOTE: between hotstarted optimizations only bound changes are allowed.

virtual void markHotStart ()

Create a hotstart point of the optimization process.

• virtual void solveFromHotStart ()

Optimize starting from the hotstart.

virtual void unmarkHotStart ()

Delete the snapshot.

Methods related to querying the input data

• virtual int getNumCols () const

Get number of columns.

· virtual int getNumRows () const

Get number of rows.

virtual int getNumElements () const

Get number of nonzero elements.

virtual const double * getColLower () const

Get pointer to array[getNumCols()] of column lower bounds.

virtual const double * getColUpper () const

Get pointer to array[getNumCols()] of column upper bounds.

virtual const char * getRowSense () const

Get pointer to array[getNumRows()] of row constraint senses.

virtual const double * getRightHandSide () const

Get pointer to array[getNumRows()] of rows right-hand sides.

virtual const double * getRowRange () const

Get pointer to array[getNumRows()] of row ranges.

virtual const double * getRowLower () const

Get pointer to array[getNumRows()] of row lower bounds.

virtual const double * getRowUpper () const

Get pointer to array[getNumRows()] of row upper bounds.

virtual const double * getObjCoefficients () const

Get pointer to array[getNumCols()] of objective function coefficients.

virtual double getObjSense () const

Get objective function sense (1 for min (default), -1 for max)

virtual bool isContinuous (int colNumber) const

Return true if column is continuous.

virtual const CoinPackedMatrix * getMatrixByRow () const

Get pointer to row-wise copy of matrix.

virtual const CoinPackedMatrix * getMatrixByCol () const

Get pointer to column-wise copy of matrix.

· virtual double getInfinity () const

Get solver's value for infinity.

Methods related to querying the solution

virtual const double * getColSolution () const

Get pointer to array[getNumCols()] of primal solution vector.

virtual const double * getRowPrice () const

Get pointer to array[getNumRows()] of dual prices.

virtual const double * getReducedCost () const

Get a pointer to array[getNumCols()] of reduced costs.

virtual const double * getRowActivity () const

Get pointer to array[getNumRows()] of row activity levels (constraint matrix times the solution vector.

virtual double getObjValue () const

Get objective function value.

virtual int getIterationCount () const

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

virtual std::vector< double * > getDualRays (int maxNumRays, bool fullRay=false) const

Get as many dual rays as the solver can provide.

virtual std::vector< double * > getPrimalRays (int maxNumRays) const

Get as many primal rays as the solver can provide.

Changing bounds on variables and constraints

virtual void setObjCoeff (int elementIndex, double elementValue)

Set an objective function coefficient.

virtual void setColLower (int elementIndex, double elementValue)

Set a single column lower bound

Use -COIN_DBL_MAX for -infinity.

virtual void setColUpper (int elementIndex, double elementValue)

Set a single column upper bound

Use COIN_DBL_MAX for infinity.

virtual void setColBounds (int elementIndex, double lower, double upper)

Set a single column lower and upper bound

The default implementation just invokes setColLower() and setColUpper()

virtual void setColSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of columns simultaneously

The default implementation just invokes setColLower() and setColUpper() over and over again.

virtual void setRowLower (int elementIndex, double elementValue)

Set a single row lower bound

Use -COIN DBL MAX for -infinity.

virtual void setRowUpper (int elementIndex, double elementValue)

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

virtual void setRowBounds (int elementIndex, double lower, double upper)

Set a single row lower and upper bound

The default implementation just invokes setRowLower() and setRowUpper()

virtual void setRowType (int index, char sense, double rightHandSide, double range)

Set the type of a single row

virtual void setRowSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

 virtual void setRowSetTypes (const int *indexFirst, const int *indexLast, const char *senseList, const double *rhsList, const double *rangeList)

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType() over and over again.

Integrality related changing methods

virtual void setContinuous (int index)

Set the index-th variable to be a continuous variable.

virtual void setInteger (int index)

Set the index-th variable to be an integer variable.

virtual void setContinuous (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be continuous variables.

virtual void setInteger (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be integer variables.

Methods to expand a problem. < br>

Note that if a column is added then by default it will correspond to a continuous variable.

virtual void addCol (const CoinPackedVectorBase &vec, const double collb, const double colub, const double obj)

Add a column (primal variable) to the problem.

virtual void addCols (const int numcols, const CoinPackedVectorBase *const *cols, const double *collb, const double *collb

Add a set of columns (primal variables) to the problem.

virtual void deleteCols (const int num, const int *colIndices)

Remove a set of columns (primal variables) from the problem.

• virtual void addRow (const CoinPackedVectorBase &vec, const double rowlb, const double rowlb)

Add a row (constraint) to the problem.

 virtual void addRow (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng)

Add a row (constraint) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const double *rowlb, const double *rowlb)

Add a set of rows (constraints) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const char *rowsen, const double *rowrhs, const double *rowrng)

Add a set of rows (constraints) to the problem.

virtual void deleteRows (const int num, const int *rowIndices)

Delete a set of rows (constraints) from the problem.

Methods to input a problem

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowlb, const double *rowlb

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&colub, double *&rowlb, double *&rowlb)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

• virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *collb, const double *rowrng)

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

 virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, char *&rowsen, double *&rowrhs, double *&rowrng)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowlb, const double *rowlb, const double *rowlb)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

 virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *colub, const double *obj, const char *rowsen, const double *rowrhs, const double *rowrng)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

virtual int readMps (const char *filename, const char *extension="mps")

Read an mps file from the given filename.

• virtual void writeMps (const char *filename, const char *extension="mps", double objSense=0.0) const Write the problem into an mps file of the given filename.

Methods for row and column names.

Only the set methods need to be overridden to ensure consistent names between OsiGlpk and the OSI base class.

void setObjName (std::string name)

Set the objective function name.

void setRowName (int ndx, std::string name)

Set a row name.

void setColName (int ndx, std::string name)

Set a column name.

Constructors and destructor

· OsiGlpkSolverInterface ()

Default Constructor.

virtual OsiSolverInterface * clone (bool copyData=true) const

Clone

OsiGlpkSolverInterface (const OsiGlpkSolverInterface &)

Copy constructor.

OsiGlpkSolverInterface & operator= (const OsiGlpkSolverInterface &rhs)

Assignment operator.

virtual ∼OsiGlpkSolverInterface ()

Destructor.

virtual void reset ()

Resets as if default constructor.

Static Public Member Functions

Static instance counter methods

static void incrementInstanceCounter ()

GLPK has a context which must be freed after all GLPK LPs (or MIPs) are freed.

static void decrementInstanceCounter ()

GLPK has a context which must be freed after all GLPK LPs (or MIPs) are freed.

static unsigned int getNumInstances ()

Return the number of LP/MIP instances of instantiated objects using the GLPK environment.

Protected Member Functions

Protected methods

virtual void applyRowCut (const OsiRowCut &rc)

Apply a row cut. Return true if cut was applied.

virtual void applyColCut (const OsiColCut &cc)

Apply a column cut (bound adjustment).

LPX * getMutableModelPtr () const

Pointer to the model.

Friends

void OsiGlpkSolverInterfaceUnitTest (const std::string &mpsDir, const std::string &netlibDir)

A function that tests the methods in the OsiGlpkSolverInterface class.

GLPK specific public interfaces

enum keepCachedFlag {
 KEEPCACHED_NONE = 0, KEEPCACHED_COLUMN = 1, KEEPCACHED_ROW = 2, KEEPCACHED_MATRIX
 = 4,
 KEEPCACHED_RESULTS = 8, KEEPCACHED_PROBLEM = KEEPCACHED_COLUMN | KEEPCACHED_RO-

KEEPCACHED_RESULTS = 8, KEEPCACHED_PROBLEM = KEEPCACHED_COLUMN | KEEPCACHED_RO-W | KEEPCACHED_MATRIX, KEEPCACHED_ALL = KEEPCACHED_PROBLEM | KEEPCACHED_RESULTS, FREECACHED_COLUMN = KEEPCACHED_PROBLEM & ~KEEPCACHED_COLUMN, FREECACHED_ROW = KEEPCACHED_PROBLEM & ~KEEPCACHED_ROW, FREECACHED_MATRIX = K-EEPCACHED_PROBLEM & ~KEEPCACHED_MATRIX, FREECACHED_RESULTS = KEEPCACHED_ALL & ~KEEPCACHED_RESULTS }

LPX * getModelPtr ()

Get pointer to GLPK model.

Additional Inherited Members

7.15.1 Detailed Description

Definition at line 34 of file OsiGlpkSolverInterface.hpp.

7.15.2 Member Enumeration Documentation

7.15.2.1 enum OsiGlpkSolverInterface::keepCachedFlag

Enumerator:

KEEPCACHED_NONE discard all cached data (default)

KEEPCACHED COLUMN column information: objective values, lower and upper bounds, variable types

KEEPCACHED ROW row information: right hand sides, ranges and senses, lower and upper bounds for row

KEEPCACHED_MATRIX problem matrix: matrix ordered by column and by row

KEEPCACHED_RESULTS LP solution: primal and dual solution, reduced costs, row activities.

KEEPCACHED_PROBLEM only discard cached LP solution

KEEPCACHED_ALL keep all cached data (similar to getMutableLpPtr())

FREECACHED_COLUMN free only cached column and LP solution information
FREECACHED_ROW free only cached row and LP solution information
FREECACHED_MATRIX free only cached matrix and LP solution information
FREECACHED_RESULTS free only cached LP solution information

Definition at line 635 of file OsiGlpkSolverInterface.hpp.

7.15.3 Member Function Documentation

```
7.15.3.1 bool OsiGlpkSolverInterface::setHintParam ( OsiHintParam key, bool yesNo = true, OsiHintStrength strength = OsiHintTry, void * = 0 ) [virtual]
```

Set a hint parameter.

The otherInformation parameter can be used to pass in an arbitrary block of information which is interpreted by the OSI and the underlying solver. Users are cautioned that this hook is solver-specific.

Implementors: The default implementation completely ignores otherInformation and always throws an exception for OsiForceDo. This is almost certainly not the behaviour you want; you really should override this method.

Reimplemented from OsiSolverInterface.

```
7.15.3.2 CoinWarmStart* OsiGlpkSolverInterface::getEmptyWarmStart( )const [inline], [virtual]
```

Get an empty warm start object.

This routine returns an empty **CoinWarmStartBasis** object. Its purpose is to provide a way to give a client a warm start basis object of the appropriate type, which can resized and modified as desired.

Implements OsiSolverInterface.

Definition at line 117 of file OsiGlpkSolverInterface.hpp.

```
7.15.3.3 virtual bool OsiGlpkSolverInterface::setWarmStart ( const CoinWarmStart * warmstart ) [virtual]
```

Set warmstarting information.

Return true/false depending on whether the warmstart information was accepted or not.

Implements OsiSolverInterface.

```
\textbf{7.15.3.4} \quad \textbf{virtual const char} * \textbf{OsiGlpkSolverInterface::getRowSense ( ) const} \quad [\texttt{virtual}]
```

Get pointer to array[getNumRows()] of row constraint senses.

- 'L': <= constraint
- 'E': = constraint
- 'G': >= constraint
- · 'R': ranged constraint
- · 'N': free constraint

Implements OsiSolverInterface.

7.15.3.5 virtual const double* OsiGlpkSolverInterface::getRightHandSide() const [virtual]

Get pointer to array[getNumRows()] of rows right-hand sides.

- if rowsense()[i] == 'L' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'G' then rhs()[i] == rowlower()[i]
- if rowsense()[i] == 'R' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'N' then rhs()[i] == 0.0

Implements OsiSolverInterface.

```
7.15.3.6 virtual const double* OsiGlpkSolverInterface::getRowRange( ) const [virtual]
```

Get pointer to array[getNumRows()] of row ranges.

- if rowsense()[i] == 'R' then rowrange()[i] == rowupper()[i] rowlower()[i]
- if rowsense()[i] != 'R' then rowrange()[i] is 0.0

Implements OsiSolverInterface.

```
7.15.3.7 virtual int OsiGlpkSolverInterface::getIterationCount ( ) const [virtual]
```

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

Implements OsiSolverInterface.

```
7.15.3.8 virtual std::vector<double*> OsiGlpkSolverInterface::getDualRays ( int maxNumRays, bool fullRay = false ) const [virtual]
```

Get as many dual rays as the solver can provide.

(In case of proven primal infeasibility there should be at least one.)

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumRows() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

```
7.15.3.9 virtual std::vector < double* > OsiGlpkSolverInterface::getPrimalRays(int maxNumRays) const [virtual]
```

Get as many primal rays as the solver can provide.

(In case of proven dual infeasibility there should be at least one.)

The first getNumRows() ray components will always be associated with the row duals (as returned by getRowPrice()). If fullRay is true, the final getNumCols() entries will correspond to the ray components associated with the nonbasic variables. If the full ray is requested and the method cannot provide it, it will throw an exception.

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumCols() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

7.15.3.10 virtual void OsiGlpkSolverInterface::setColLower(int elementIndex, double elementValue) [virtual]

Set a single column lower bound

Use -COIN DBL MAX for -infinity.

Implements OsiSolverInterface.

7.15.3.11 virtual void OsiGlpkSolverInterface::setColUpper (int elementIndex, double elementValue) [virtual]

Set a single column upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.15.3.12 virtual void OsiGlpkSolverInterface::setColSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of columns simultaneously

The default implementation just invokes setColLower() and setColUpper() over and over again.

Parameters

ſ	indexFirst,index-	pointers to the beginning and after the end of the array of the indices of the variables whose either
	Last	bound changes
Ī	boundList	the new lower/upper bound pairs for the variables

Reimplemented from OsiSolverInterface.

7.15.3.13 virtual void OsiGlpkSolverInterface::setRowLower (int elementIndex, double elementValue) [virtual]

Set a single row lower bound

Use -COIN DBL MAX for -infinity.

Implements OsiSolverInterface.

7.15.3.14 virtual void OsiGlpkSolverInterface::setRowUpper(int elementIndex, double elementValue) [virtual]

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.15.3.15 virtual void OsiGlpkSolverInterface::setRowSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

Parameters

Ī	indexFirst,index-	pointers to the beginning and after the end of the array of the indices of the constraints whose
	Last	either bound changes
Ī	boundList	the new lower/upper bound pairs for the constraints

Reimplemented from OsiSolverInterface.

7.15.3.16 virtual void OsiGlpkSolverInterface::setRowSetTypes (const int * indexFirst, const int * indexLast, const char * senseList, const double * rhsList, const double * rangeList) [virtual]

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType() over and over again.

Parameters

indexFirst,index-	pointers to the beginning and after the end of the array of the indices of the constraints whose any
Last	characteristics changes
senseList	the new senses
rhsList	the new right hand sides
rangeList	the new ranges

Reimplemented from OsiSolverInterface.

7.15.3.17 virtual void OsiGlpkSolverInterface::setColSolution (const double * colsol) [virtual]

Set the primal solution column values.

colsol[numcols()] is an array of values of the problem column variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of colsol() until changed by another call to setColsol() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.15.3.18 virtual void OsiGlpkSolverInterface::setRowPrice (const double * rowprice) [virtual]

Set dual solution vector.

rowprice[numrows()] is an array of values of the problem row dual variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of rowprice() until changed by another call to setRowprice() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.15.3.19 virtual void OsiGlpkSolverInterface::addCol (const CoinPackedVectorBase & vec, const double collb, const double collb, const double obj) [virtual]

Add a column (primal variable) to the problem.

Implements OsiSolverInterface.

7.15.3.20 virtual void OsiGlpkSolverInterface::addCols (const int *numcols*, const CoinPackedVectorBase *const * cols, const double * collb, const double * colub, const double * obj) [virtual]

Add a set of columns (primal variables) to the problem.

The default implementation simply makes repeated calls to addCol().

Reimplemented from OsiSolverInterface.

7.15.3.21 virtual void OsiGlpkSolverInterface::deleteCols (const int num, const int * collndices) [virtual]

Remove a set of columns (primal variables) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted variables are

nonbasic.

Implements OsiSolverInterface.

7.15.3.22 virtual void OsiGlpkSolverInterface::addRow (const CoinPackedVectorBase & vec, const double rowlb, const double rowlb) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.15.3.23 virtual void OsiGlpkSolverInterface::addRow (const CoinPackedVectorBase & vec, const char rowsen, const double rowrns, const double rowrng) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.15.3.24 virtual void OsiGlpkSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * *rows*, const double * *rowlb*, const double * *rowub*) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.15.3.25 virtual void OsiGlpkSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * rows, const char * rowsen, const double * rowrhs, const double * rowrng) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.15.3.26 virtual void OsiGlpkSolverInterface::deleteRows (const int num, const int * rowIndices) [virtual]

Delete a set of rows (constraints) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted rows are loose. Implements OsiSolverInterface.

7.15.3.27 virtual void OsiGlpkSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowlb, const double * rowlb) [virtual]

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- rowub: all rows have upper bound infinity
- rowlb: all rows have lower bound -infinity
- obj: all variables have 0 objective coefficient

Implements OsiSolverInterface.

7.15.3.28 virtual void OsiGlpkSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& rowlb, double *& rowlb) [virtual]

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

7.15.3.29 virtual void OsiGlpkSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * colub, const double * rowrns, const double * rowrns, const double * rowrns)

[virtual]

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets). If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- obj: all variables have 0 objective coefficient
- rowsen: all rows are >=
- rowrhs: all right hand sides are 0
- rowrng: 0 for the ranged rows

Implements OsiSolverInterface.

7.15.3.30 virtual void OsiGlpkSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& collb, double *& rowrns, double *& rowrn

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

7.15.3.31 virtual void OsiGlpkSolverInterface::loadProblem (const int numcols, const int numrows, const int * start, const int * index, const double * value, const double * collb, const double * collb, const double * obj, const double * rowlb, const double * rowub) [virtual]

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

7.15.3.33 virtual void OsiGlpkSolverInterface::writeMps (const char * filename, const char * extension = "mps", double objSense = 0.0) const [virtual]

Write the problem into an mps file of the given filename.

If objSense is non zero then -1.0 forces the code to write a maximization objective and +1.0 to write a minimization one. If 0.0 then solver can do what it wants

Implements OsiSolverInterface.

7.15.3.34 void OsiGlpkSolverInterface::setRowName(int ndx, std::string name) [virtual]

Set a row name.

Quietly does nothing if the name discipline (#OsiNameDiscipline) is auto. Quietly fails if the row index is invalid.

Reimplemented from OsiSolverInterface.

7.15.3.35 void OsiGlpkSolverInterface::setColName (int ndx, std::string name) [virtual]

Set a column name.

Quietly does nothing if the name discipline (#OsiNameDiscipline) is auto. Quietly fails if the column index is invalid.

Reimplemented from OsiSolverInterface.

7.15.3.36 static void OsiGlpkSolverInterface::incrementInstanceCounter() [inline], [static]

GLPK has a context which must be freed after all GLPK LPs (or MIPs) are freed.

It is automatically created when the first LP is created. This method:

Increments by 1 the number of uses of the GLPK environment.

Definition at line 674 of file OsiGlpkSolverInterface.hpp.

7.15.3.37 static void OsiGlpkSolverInterface::decrementInstanceCounter() [static]

GLPK has a context which must be freed after all GLPK LPs (or MIPs) are freed.

This method:

- Decrements by 1 the number of uses of the GLPK environment.
- Deletes the GLPK environment when the number of uses is change to 0 from 1.

7.15.3.38 virtual void OsiGlpkSolverInterface::applyColCut (const OsiColCut & cc) [protected], [virtual]

Apply a column cut (bound adjustment).

Return true if cut was applied.

Implements OsiSolverInterface.

7.15.4 Friends And Related Function Documentation

7.15.4.1 void OsiGlpkSolverInterfaceUnitTest (const std::string & mpsDir, const std::string & netlibDir) [friend]

A function that tests the methods in the OsiGlpkSolverInterface class.

The documentation for this class was generated from the following file:


· OsiGlpkSolverInterface.hpp

7.16 OsiGrbSolverInterface Class Reference


Gurobi Solver Interface.

#include <OsiGrbSolverInterface.hpp>

Inheritance diagram for OsiGrbSolverInterface:



Collaboration diagram for OsiGrbSolverInterface:



Public Member Functions

virtual void setObjSense (double s)

Set objective function sense (1 for min (default), -1 for max,)

• virtual void setColSolution (const double *colsol)

Set the primal solution column values.

virtual void setRowPrice (const double *rowprice)

Set dual solution vector.

const char * getCtype () const

return a vector of variable types (continous, binary, integer)

virtual

OsiSolverInterface::ApplyCutsReturnCode applyCuts (const OsiCuts &cs, double effectivenessLb=0.0)

Apply a collection of cuts.

Solve methods

virtual void initialSolve ()

Solve initial LP relaxation.

• virtual void resolve ()

Resolve an LP relaxation after problem modification.

virtual void branchAndBound ()

Invoke solver's built-in enumeration algorithm.

Parameter set/get methods

The set methods return true if the parameter was set to the given value, false otherwise.

There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the volume algorithm), the parameter is not yet implemented for the solver or simply the value of the parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.

The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.

bool setIntParam (OsiIntParam key, int value)

Set an integer parameter.

bool setDblParam (OsiDblParam key, double value)

Set a double parameter.

bool setStrParam (OsiStrParam key, const std::string &value)

Set a string parameter.

bool setHintParam (OsiHintParam key, bool yesNo=true, OsiHintStrength strength=OsiHintTry, void *=NULL)
 Set a hint parameter.

bool getIntParam (OsiIntParam key, int &value) const

Get an integer parameter.

bool getDblParam (OsiDblParam key, double &value) const

Get a double parameter.

• bool getStrParam (OsiStrParam key, std::string &value) const

Get a string parameter.

bool getHintParam (OsiHintParam key, bool &yesNo, OsiHintStrength &strength, void *&otherInformation)
 const

Get a hint parameter (all information)

• bool getHintParam (OsiHintParam key, bool &yesNo, OsiHintStrength &strength) const

Get a hint parameter (sense and strength only)

• bool getHintParam (OsiHintParam key, bool &yesNo) const

Get a hint parameter (sense only)

- void setMipStart (bool value)
- bool getMipStart () const

Methods returning info on how the solution process terminated

· virtual bool isAbandoned () const

Are there a numerical difficulties?

virtual bool isProvenOptimal () const

Is optimality proven?

virtual bool isProvenPrimalInfeasible () const

Is primal infeasiblity proven?

· virtual bool isProvenDualInfeasible () const

Is dual infeasiblity proven?

· virtual bool isPrimalObjectiveLimitReached () const

Is the given primal objective limit reached?

· virtual bool isDualObjectiveLimitReached () const

Is the given dual objective limit reached?

virtual bool isIterationLimitReached () const

Iteration limit reached?

WarmStart related methods

CoinWarmStart * getEmptyWarmStart () const

Get an empty warm start object.

virtual CoinWarmStart * getWarmStart () const

Get warmstarting information.

virtual bool setWarmStart (const CoinWarmStart *warmstart)

Set warmstarting information.

Hotstart related methods (primarily used in strong branching).

 tr>

The user can create a hotstart (a snapshot) of the optimization process then reoptimize over and over again always starting from there.

NOTE: between hotstarted optimizations only bound changes are allowed.

• virtual void markHotStart ()

Create a hotstart point of the optimization process.

virtual void solveFromHotStart ()

Optimize starting from the hotstart.

virtual void unmarkHotStart ()

Delete the snapshot.

Methods related to querying the input data

virtual int getNumCols () const

Get number of columns.

virtual int getNumRows () const

Get number of rows.

• virtual int getNumElements () const

Get number of nonzero elements.

virtual const double * getColLower () const

Get pointer to array[getNumCols()] of column lower bounds.

• virtual const double * getColUpper () const

Get pointer to array[getNumCols()] of column upper bounds.

virtual const char * getRowSense () const

Get pointer to array[getNumRows()] of row constraint senses.

virtual const double * getRightHandSide () const

Get pointer to array[getNumRows()] of rows right-hand sides.

virtual const double * getRowRange () const

Get pointer to array[getNumRows()] of row ranges.

virtual const double * getRowLower () const

Get pointer to array[getNumRows()] of row lower bounds.

virtual const double * getRowUpper () const

Get pointer to array[getNumRows()] of row upper bounds.

virtual const double * getObjCoefficients () const

Get pointer to array[getNumCols()] of objective function coefficients.

· virtual double getObjSense () const

Get objective function sense (1 for min (default), -1 for max)

· virtual bool isContinuous (int colNumber) const

Return true if column is continuous.

virtual const CoinPackedMatrix * getMatrixByRow () const

Get pointer to row-wise copy of matrix.

virtual const CoinPackedMatrix * getMatrixByCol () const

Get pointer to column-wise copy of matrix.

virtual double getInfinity () const

Get solver's value for infinity.

Methods related to querying the solution

virtual const double * getColSolution () const

Get pointer to array[getNumCols()] of primal solution vector.

virtual const double * getRowPrice () const

Get pointer to array[getNumRows()] of dual prices.

virtual const double * getReducedCost () const

Get a pointer to array[getNumCols()] of reduced costs.

virtual const double * getRowActivity () const

Get pointer to array[getNumRows()] of row activity levels (constraint matrix times the solution vector.

• virtual double getObjValue () const

Get objective function value.

virtual int getIterationCount () const

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

virtual std::vector< double * > getDualRays (int maxNumRays, bool fullRay=false) const
 Get as many dual rays as the solver can provide.

virtual std::vector< double * > getPrimalRays (int maxNumRays) const

Get as many primal rays as the solver can provide.

Changing bounds on variables and constraints

virtual void setObjCoeff (int elementIndex, double elementValue)

Set an objective function coefficient.

virtual void setObjCoeffSet (const int *indexFirst, const int *indexLast, const double *coeffList)

Set a a set of objective function coefficients.

virtual void setColLower (int elementIndex, double elementValue)

Set a single column lower bound

Use -COIN DBL MAX for -infinity.

• virtual void setColUpper (int elementIndex, double elementValue)

Set a single column upper bound

Use COIN_DBL_MAX for infinity.

• virtual void setColBounds (int elementIndex, double lower, double upper)

Set a single column lower and upper bound

The default implementation just invokes setColLower() and setColUpper()

virtual void setColSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of columns simultaneously

The default implementation just invokes <code>setCollower()</code> and <code>setColupper()</code> over and over again.

virtual void setRowLower (int elementIndex, double elementValue)

Set a single row lower bound

Use -COIN_DBL_MAX for -infinity.

virtual void setRowUpper (int elementIndex, double elementValue)

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

virtual void setRowBounds (int elementIndex, double lower, double upper)

Set a single row lower and upper bound

The default implementation just invokes setRowLower() and setRowUpper()

virtual void setRowType (int index, char sense, double rightHandSide, double range)

Set the type of a single row

virtual void setRowSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

 virtual void setRowSetTypes (const int *indexFirst, const int *indexLast, const char *senseList, const double *rhsList, const double *rangeList)

Set the type of a number of rows simultaneously

The default implementation just invokes <code>setRowType()</code> and over again.

Integrality related changing methods

virtual void setContinuous (int index)

Set the index-th variable to be a continuous variable.

virtual void setInteger (int index)

Set the index-th variable to be an integer variable.

virtual void setContinuous (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be continuous variables.

virtual void setInteger (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be integer variables.

Naming methods

virtual void setRowName (int ndx, std::string name)

Set a row name.

virtual void setColName (int ndx, std::string name)

Set a column name.

Methods to expand a problem. < br>

Note that if a column is added then by default it will correspond to a continuous variable.

virtual void addCol (const CoinPackedVectorBase &vec, const double collb, const double colub, const double obj)

Add a column (primal variable) to the problem.

virtual void addCols (const int numcols, const CoinPackedVectorBase *const *cols, const double *collb, const double *collb, const double *obj)

Add a set of columns (primal variables) to the problem.

virtual void deleteCols (const int num, const int *colIndices)

Remove a set of columns (primal variables) from the problem.

virtual void addRow (const CoinPackedVectorBase &vec, const double rowlb, const double rowlb)

Add a row (constraint) to the problem.

 virtual void addRow (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng)

Add a row (constraint) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const double *rowlb, const double *rowlb)

Add a set of rows (constraints) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const char *rowsen, const double *rowrhs, const double *rowrng)

Add a set of rows (constraints) to the problem.

virtual void deleteRows (const int num, const int *rowIndices)

Delete a set of rows (constraints) from the problem.

Methods to input a problem

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowlb, const double *rowlb)

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, double *&rowlb, double *&rowlb)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *collb, const double *rowrng)

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

 virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, char *&rowsen, double *&rowrhs, double *&rowrng)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowlb, const double *rowlb, const double *rowlb)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

 virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *colub, const double *obj, const char *rowsen, const double *rowrhs, const double *rowrng)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

• virtual int readMps (const char *filename, const char *extension="mps")

Read an mps file from the given filename.

• virtual void writeMps (const char *filename, const char *extension="mps", double objSense=0.0) const Write the problem into an mps file of the given filename.

Constructors and destructor

OsiGrbSolverInterface (bool use_local_env=false)

Default Constructor.

• OsiGrbSolverInterface (GRBenv *localgrbenv)

Constructor that takes a gurobi environment and assumes membership.

virtual OsiSolverInterface * clone (bool copyData=true) const

Clone

OsiGrbSolverInterface (const OsiGrbSolverInterface &)

Copy constructor.

• OsiGrbSolverInterface & operator= (const OsiGrbSolverInterface &rhs)

Assignment operator.

virtual ∼OsiGrbSolverInterface ()

Destructor.

virtual void reset ()

Resets as if default constructor.

OsiSimplexInterface methods

Gurobi adds a slack with coeff +1 in "<=" and "=" constraints, with coeff -1 in ">=", slack being non negative.

We switch in order to get a "Clp tableau" where all the slacks have coefficient +1 in the original tableau.

If a slack for ">=" is non basic, invB is not changed; column of the slack in the optimal tableau is flipped.

If a slack for ">=" is basic, corresp. row of invB is flipped; whole row of the optimal tableau is flipped; then whole column for the slack in opt tableau is flipped.

Ranged rows are not supported. It might work, but no garantee is given.

virtual int canDoSimplexInterface () const

Returns 1 if can just do getBlnv etc 2 if has all OsiSimplex methods and 0 if it has none.

virtual void enableSimplexInterface (int doingPrimal)

Useless function, defined only for compatibility with OsiSimplexInterface.

• virtual void disableSimplexInterface ()

Useless function, defined only for compatibility with OsiSimplexInterface.

• virtual void enableFactorization () const

Useless function, defined only for compatibility with OsiSimplexInterface.

virtual void disableFactorization () const

Useless function, defined only for compatibility with OsiSimplexInterface.

virtual bool basisIsAvailable () const

Returns true if a basis is available.

virtual void getBasisStatus (int *cstat, int *rstat) const

Returns a basis status of the structural/artificial variables At present as warm start i.e 0: free, 1: basic, 2: upper, 3: lower.

void switchToLP ()

Get indices of the pivot variable in each row

(order of indices corresponds to the order of elements in a vector retured by getBInvACol() and getBInvCol()).

• void switchToMIP ()

switches Gurobi to prob type MIP

Static Public Member Functions

Static instance counter methods

static void incrementInstanceCounter ()

Gurobi has a context which must be created prior to all other Gurobi calls.

static void decrementInstanceCounter ()

Gurobi has a context which should be deleted after Gurobi calls.

static void setEnvironment (GRBenv *globalenv)

sets the global gurobi environment to a user given one

static unsigned int getNumInstances ()

Return the number of instances of instantiated objects using Gurobi services.

Protected Member Functions

Protected methods

virtual void applyRowCut (const OsiRowCut &rc)

Apply a row cut. Return true if cut was applied.

virtual void applyColCut (const OsiColCut &cc)

Apply a column cut (bound adjustment).

Friends

void OsiGrbSolverInterfaceUnitTest (const std::string &mpsDir, const std::string &netlibDir)

A function that tests the methods in the OsiGrbSolverInterface class.

Gurobi specific public interfaces

enum keepCachedFlag {
 KEEPCACHED_NONE = 0, KEEPCACHED_COLUMN = 1, KEEPCACHED_ROW = 2, KEEPCACHED_MATRIX
 = 4,
 KEEPCACHED_RESULTS = 8, KEEPCACHED_PROBLEM = KEEPCACHED_COLUMN | KEEPCACHED_ROW | KEEPCACHED_MATRIX, KEEPCACHED_ALL = KEEPCACHED_PROBLEM | KEEPCACHED_RESULTS,
 FREECACHED_COLUMN = KEEPCACHED_PROBLEM & ~KEEPCACHED_COLUMN,

FREECACHED_COLUMN = KEEPCACHED_PROBLEM & ~KEEPCACHED_COLUMN,
FREECACHED_ROW = KEEPCACHED_PROBLEM & ~KEEPCACHED_ROW, FREECACHED_MATRIX = KEEPCACHED_PROBLEM & ~KEEPCACHED_MATRIX, FREECACHED_RESULTS = KEEPCACHED_ALL &
~KEEPCACHED_RESULTS }

Get pointer to Gurobi model and free all specified cached data entries (combined with logical or-operator '|'):

- GRBmodel * getLpPtr (int keepCached=KEEPCACHED_NONE)
- GRBenv * getEnvironmentPtr () const

Method to access Gurobi environment pointer.

· bool isDemoLicense () const

Return whether the current Gurobi environment runs in demo mode.

Additional Inherited Members

7.16.1 Detailed Description

Gurobi Solver Interface.

Instantiation of OsiGrbSolverInterface for Gurobi

Definition at line 29 of file OsiGrbSolverInterface.hpp.

7.16.2 Member Enumeration Documentation

7.16.2.1 enum OsiGrbSolverInterface::keepCachedFlag

Get pointer to Gurobi model and free all specified cached data entries (combined with logical or-operator '|'):

Enumerator:

KEEPCACHED_NONE discard all cached data (default)

KEEPCACHED COLUMN column information: objective values, lower and upper bounds, variable types

KEEPCACHED_ROW row information: right hand sides, ranges and senses, lower and upper bounds for row

KEEPCACHED_MATRIX problem matrix: matrix ordered by column and by row

KEEPCACHED RESULTS LP solution: primal and dual solution, reduced costs, row activities.

KEEPCACHED_PROBLEM only discard cached LP solution

KEEPCACHED_ALL keep all cached data (similar to getMutableLpPtr())

FREECACHED_COLUMN free only cached column and LP solution information

FREECACHED_ROW free only cached row and LP solution information

FREECACHED_MATRIX free only cached matrix and LP solution information **FREECACHED_RESULTS** free only cached LP solution information

Definition at line 546 of file OsiGrbSolverInterface.hpp.

7.16.3 Member Function Documentation

7.16.3.1 bool OsiGrbSolverInterface::setHintParam (OsiHintParam key, bool yesNo = true, OsiHintStrength strength = OsiHintTry, void * = NULL) [virtual]

Set a hint parameter.

The otherInformation parameter can be used to pass in an arbitrary block of information which is interpreted by the OSI and the underlying solver. Users are cautioned that this hook is solver-specific.

Implementors: The default implementation completely ignores otherInformation and always throws an exception for OsiForceDo. This is almost certainly not the behaviour you want; you really should override this method.

Reimplemented from OsiSolverInterface.

7.16.3.2 bool OsiGrbSolverInterface::getHintParam (OsiHintParam key, bool & yesNo, OsiHintStrength & strength, void *& otherInformation) const [virtual]

Get a hint parameter (all information)

Return all available information for the hint: sense, strength, and any extra information associated with the hint.

Implementors: The default implementation will always set otherInformation to NULL. This is almost certainly not the behaviour you want; you really should override this method.

Reimplemented from OsiSolverInterface.

7.16.3.3 bool OsiGrbSolverInterface::getHintParam (OsiHintParam key, bool & yesNo, OsiHintStrength & strength) const [virtual]

Get a hint parameter (sense and strength only)

Return only the sense and strength of the hint.

Reimplemented from OsiSolverInterface.

7.16.3.4 bool OsiGrbSolverInterface::getHintParam (OsiHintParam key, bool & yesNo) const [virtual]

Get a hint parameter (sense only)

Return only the sense (true/false) of the hint.

Reimplemented from OsiSolverInterface.

7.16.3.5 CoinWarmStart* OsiGrbSolverInterface::getEmptyWarmStart() const [virtual]

Get an empty warm start object.

This routine returns an empty **CoinWarmStartBasis** object. Its purpose is to provide a way to give a client a warm start basis object of the appropriate type, which can resized and modified as desired.

Implements OsiSolverInterface.

7.16.3.6 virtual bool OsiGrbSolverInterface::setWarmStart (const CoinWarmStart * warmstart) [virtual]

Set warmstarting information.

Return true/false depending on whether the warmstart information was accepted or not.

Implements OsiSolverInterface.

```
7.16.3.7 virtual const char* OsiGrbSolverInterface::getRowSense() const [virtual]
```

Get pointer to array[getNumRows()] of row constraint senses.

- 'L': <= constraint
- 'E': = constraint
- 'G': >= constraint
- · 'R': ranged constraint
- · 'N': free constraint

Implements OsiSolverInterface.

```
7.16.3.8 virtual const double* OsiGrbSolverInterface::getRightHandSide( ) const [virtual]
```

Get pointer to array[getNumRows()] of rows right-hand sides.

- if rowsense()[i] == 'L' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'G' then rhs()[i] == rowlower()[i]
- if rowsense()[i] == 'R' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'N' then rhs()[i] == 0.0

Implements OsiSolverInterface.

```
7.16.3.9 virtual const double* OsiGrbSolverInterface::getRowRange() const [virtual]
```

Get pointer to array[getNumRows()] of row ranges.

- if rowsense()[i] == 'R' then rowrange()[i] == rowupper()[i] rowlower()[i]
- if rowsense()[i] != 'R' then rowrange()[i] is 0.0

Implements OsiSolverInterface.

```
7.16.3.10 virtual int OsiGrbSolverInterface::getIterationCount() const [virtual]
```

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

Implements OsiSolverInterface.

```
7.16.3.11 virtual std::vector<double*> OsiGrbSolverInterface::getDualRays( int maxNumRays, bool fullRay = false) const [virtual]
```

Get as many dual rays as the solver can provide.

(In case of proven primal infeasibility there should be at least one.)

The first getNumRows() ray components will always be associated with the row duals (as returned by getRowPrice()). If fullRay is true, the final getNumCols() entries will correspond to the ray components associated with the nonbasic variables. If the full ray is requested and the method cannot provide it, it will throw an exception.

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumRows() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

7.16.3.12 virtual std::vector<double*> OsiGrbSolverInterface::getPrimalRays (int maxNumRays) const [virtual]

Get as many primal rays as the solver can provide.

(In case of proven dual infeasibility there should be at least one.)

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumCols() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

7.16.3.13 virtual void OsiGrbSolverInterface::setColLower (int elementIndex, double elementValue) [virtual]

Set a single column lower bound

Use -COIN DBL MAX for -infinity.

Implements OsiSolverInterface.

7.16.3.14 virtual void OsiGrbSolverInterface::setColUpper (int elementIndex, double elementValue) [virtual]

Set a single column upper bound

Use COIN DBL MAX for infinity.

Implements OsiSolverInterface.

7.16.3.15 virtual void OsiGrbSolverInterface::setColSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of columns simultaneously

The default implementation just invokes setCollower() and setColupper() over and over again.

Parameters

	contains the indices of the constraints whose either bound changes
<code>[indexfirst,index-</code>	
Last]	
boundList	the new lower/upper bound pairs for the variables

Reimplemented from OsiSolverInterface.

7.16.3.16 virtual void OsiGrbSolverInterface::setRowLower(int elementIndex, double elementValue) [virtual]

Set a single row lower bound

Use -COIN_DBL_MAX for -infinity.

Implements OsiSolverInterface.

7.16.3.17 virtual void OsiGrbSolverInterface::setRowUpper(int elementIndex, double elementValue) [virtual]

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.16.3.18 virtual void OsiGrbSolverInterface::setRowSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

Parameters

	contains the indices of the constraints whose either bound changes
<code>[indexfirst,</code>	index-
Last]	
boundList	the new lower/upper bound pairs for the constraints

Reimplemented from OsiSolverInterface.

7.16.3.19 virtual void OsiGrbSolverInterface::setRowSetTypes (const int * indexFirst, const int * indexLast, const char * senseList, const double * rhsList, const double * rangeList) [virtual]

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType () and over and over again.

Parameters

	contains the indices of the constraints whose type changes
<code>[indexfirst,</code>	index-
Last]	
senseList	the new senses
rhsList	the new right hand sides
rangeList	the new ranges

Reimplemented from OsiSolverInterface.

7.16.3.20 virtual void OsiGrbSolverInterface::setColSolution (const double * colsol) [virtual]

Set the primal solution column values.

colsol[numcols()] is an array of values of the problem column variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of colsol() until changed by another call to setColsol() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.16.3.21 virtual void OsiGrbSolverInterface::setRowPrice (const double * rowprice) [virtual]

Set dual solution vector.

rowprice[numrows()] is an array of values of the problem row dual variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of rowprice() until changed by another call to setRowprice() or by a call to any solver routine. Whether the solver makes use of the solution in any way is

solver-dependent.

Implements OsiSolverInterface.

7.16.3.22 virtual void OsiGrbSolverInterface::addCol (const CoinPackedVectorBase & vec, const double collb, const double collb, const double obj) [virtual]

Add a column (primal variable) to the problem.

Implements OsiSolverInterface.

7.16.3.23 virtual void OsiGrbSolverInterface::addCols (const int *numcols*, const CoinPackedVectorBase *const * cols, const double * collb, const double * collb, const double * obj) [virtual]

Add a set of columns (primal variables) to the problem.

The default implementation simply makes repeated calls to addCol().

Reimplemented from OsiSolverInterface.

7.16.3.24 virtual void OsiGrbSolverInterface::deleteCols (const int num, const int * collndices) [virtual]

Remove a set of columns (primal variables) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted variables are nonbasic.

Implements OsiSolverInterface.

7.16.3.25 virtual void OsiGrbSolverInterface::addRow (const CoinPackedVectorBase & vec, const double rowlb, const double rowub) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.16.3.26 virtual void OsiGrbSolverInterface::addRow (const CoinPackedVectorBase & *vec*, const char *rowsen*, const double *rowrns*, const double *rowrng*) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.16.3.27 virtual void OsiGrbSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * *rows*, const double * *rowlb*, const double * *rowub*) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.16.3.28 virtual void OsiGrbSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * rows, const char * rowsen, const double * rowrhs, const double * rowrng) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.16.3.29 virtual void OsiGrbSolverInterface::deleteRows (const int num, const int * rowIndices) [virtual]

Delete a set of rows (constraints) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted rows are loose. Implements OsiSolverInterface.

7.16.3.30 virtual void OsiGrbSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowlb, const double * rowlb) [virtual]

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds). If a pointer is 0 then the following values are the default:

- · colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- rowub: all rows have upper bound infinity
- rowlb: all rows have lower bound -infinity
- obj: all variables have 0 objective coefficient

Implements OsiSolverInterface.

```
7.16.3.31 virtual void OsiGrbSolverInterface::assignProblem ( CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowlb, double *& rowlb ) [virtual]
```

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

```
7.16.3.32 virtual void OsiGrbSolverInterface::loadProblem ( const CoinPackedMatrix & matrix, const double * collb, const double * colub, const double * rowrns, const double * rowrns, const double * rowrns )

[virtual]
```

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets). If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- obj: all variables have 0 objective coefficient
- rowsen: all rows are >=
- rowrhs: all right hand sides are 0
- rowrng: 0 for the ranged rows

Implements OsiSolverInterface.

7.16.3.33 virtual void OsiGrbSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowrng, double *& rowrng) [virtual]

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

7.16.3.34 virtual void OsiGrbSolverInterface::loadProblem (const int *numcols*, const int *numrows*, const int * *start*, const int * *index*, const double * *value*, const double * *collb*, const double * *colub*, const double * *obj*, const double * *rowub*) [virtual]

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

7.16.3.36 virtual void OsiGrbSolverInterface::writeMps (const char * filename, const char * extension = "mps", double objSense = 0.0) const [virtual]

Write the problem into an mps file of the given filename.

If objSense is non zero then -1.0 forces the code to write a maximization objective and +1.0 to write a minimization one. If 0.0 then solver can do what it wants

Implements OsiSolverInterface.

7.16.3.37 static void OsiGrbSolverInterface::incrementInstanceCounter() [static]

Gurobi has a context which must be created prior to all other Gurobi calls.

This method:

- Increments by 1 the number of uses of the Gurobi environment.
- Creates the Gurobi context when the number of uses is change to 1 from 0.

7.16.3.38 static void OsiGrbSolverInterface::decrementInstanceCounter() [static]

Gurobi has a context which should be deleted after Gurobi calls.

This method:

- Decrements by 1 the number of uses of the Gurobi environment.
- Deletes the Gurobi context when the number of uses is change to 0 from 1.

```
7.16.3.39 void OsiGrbSolverInterface::switchToLP ( )
```

Get indices of the pivot variable in each row

(order of indices corresponds to the order of elements in a vector retured by getBInvACol() and getBInvCol()). switches Gurobi to prob type LP

7.16.3.40 virtual OsiSolverInterface::ApplyCutsReturnCode OsiGrbSolverInterface::applyCuts (const OsiCuts & cs, double effectivenessLb = 0.0) [virtual]

Apply a collection of cuts.

Only cuts which have an effectiveness >= effectivenessLb are applied.

- ReturnCode.getNumineffective() number of cuts which were not applied because they had an effectiveness
 effectivenessLb
- ReturnCode.getNuminconsistent() number of invalid cuts
- ReturnCode.getNuminconsistentWrtIntegerModel() number of cuts that are invalid with respect to this integer
 model
- ReturnCode.getNuminfeasible() number of cuts that would make this integer model infeasible
- ReturnCode.getNumApplied() number of integer cuts which were applied to the integer model
- cs.size() == getNumineffective() + getNuminconsistent() + getNuminconsistentWrtIntegerModel() + getNuminfeasible() + getNumApplied()

Reimplemented from OsiSolverInterface.

7.16.3.41 virtual void OsiGrbSolverInterface::applyColCut (const OsiColCut & cc) [protected], [virtual]

Apply a column cut (bound adjustment).

Return true if cut was applied.

Implements OsiSolverInterface.

7.16.4 Friends And Related Function Documentation

7.16.4.1 void OsiGrbSolverInterfaceUnitTest (const std::string & mpsDir, const std::string & netlibDir) [friend]

A function that tests the methods in the OsiGrbSolverInterface class.

The documentation for this class was generated from the following file:


OsiGrbSolverInterface.hpp

7.17 OsiHotInfo Class Reference

This class contains the result of strong branching on a variable When created it stores enough information for strong branching.

#include <OsiChooseVariable.hpp>

Collaboration diagram for OsiHotInfo:



Public Member Functions

• OsiHotInfo ()

Default Constructor.

OsiHotInfo (OsiSolverInterface *solver, const OsiBranchingInformation *info, const OsiObject *const *objects, int whichObject)

Constructor from useful information.

• OsiHotInfo (const OsiHotInfo &)

Copy constructor.

• OsiHotInfo & operator= (const OsiHotInfo &rhs)

Assignment operator.

virtual OsiHotInfo * clone () const

Clone.

virtual ∼OsiHotInfo ()

Destructor.

• int updateInformation (const OsiSolverInterface *solver, const OsiBranchingInformation *info, OsiChooseVariable *choose)

Fill in useful information after strong branch.

· double originalObjectiveValue () const

Original objective value.

· double upChange () const

Up change - invalid if n-way.

• double downChange () const

Down change - invalid if n-way.

void setUpChange (double value)

Set up change - invalid if n-way.

• void setDownChange (double value)

Set down change - invalid if n-way.

• double change (int k) const

Change on way k.

• int upIterationCount () const

Up iteration count - invalid if n-way.

int downIterationCount () const

Down iteration count - invalid if n-way.

int iterationCount (int k) const

Iteration count on way k.

• int upStatus () const

Up status - invalid if n-way.

· int downStatus () const

Down status - invalid if n-way.

void setUpStatus (int value)

Set up status - invalid if n-way.

• void setDownStatus (int value)

Set down status - invalid if n-way.

· int status (int k) const

Status on way k.

OsiBranchingObject * branchingObject () const

Branching object.

Protected Attributes

double originalObjectiveValue_

Original objective value.

• double * changes_

Objective changes.

int * iterationCounts

Iteration counts.

int * statuses_

Status -1 - not done 0 - feasible and finished 1 - infeasible 2 - not finished.

OsiBranchingObject * branchingObject_

Branching object.

· int whichObject_

Which object on list.

7.17.1 Detailed Description

This class contains the result of strong branching on a variable When created it stores enough information for strong branching.

Definition at line 432 of file OsiChooseVariable.hpp.

7.17.2 Member Function Documentation

7.17.2.1 int OsiHotInfo::updateInformation (const OsiSolverInterface * solver, const OsiBranchingInformation * info, OsiChooseVariable * choose)

Fill in useful information after strong branch.

Return status

The documentation for this class was generated from the following file:


· OsiChooseVariable.hpp

7.18 OsiIntegerBranchingObject Class Reference


Simple branching object for an integer variable.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiIntegerBranchingObject:



Collaboration diagram for OsiIntegerBranchingObject:



Public Member Functions

• OsiIntegerBranchingObject ()

Default constructor.

OsiIntegerBranchingObject (OsiSolverInterface *solver, const OsiSimpleInteger *originalObject, int way, double value)

Create a standard floor/ceiling branch object.

OsiIntegerBranchingObject (OsiSolverInterface *solver, const OsiSimpleInteger *originalObject, int way, double value, double downUpperBound, double upLowerBound)

Create a standard floor/ceiling branch object.

OsiIntegerBranchingObject (const OsiIntegerBranchingObject &)

Copy constructor.

OsiIntegerBranchingObject & operator= (const OsiIntegerBranchingObject &rhs)

Assignment operator.

virtual OsiBranchingObject * clone () const

Clone

virtual ~OsiIntegerBranchingObject ()

Destructor.

virtual double branch (OsiSolverInterface *solver)

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

virtual void print (const OsiSolverInterface *solver=NULL)

Print something about branch - only if log level high.

Protected Attributes

```
    double down [2]
```

Lower [0] and upper [1] bounds for the down arm (way_ = -1)

• double up [2]

Lower [0] and upper [1] bounds for the up arm (way_ = 1)

7.18.1 Detailed Description

Simple branching object for an integer variable.

This object can specify a two-way branch on an integer variable. For each arm of the branch, the upper and lower bounds on the variable can be independently specified. 0 -> down, 1-> up.

Definition at line 607 of file OsiBranchingObject.hpp.

7.18.2 Constructor & Destructor Documentation

7.18.2.1 OsilntegerBranchingObject::OsilntegerBranchingObject (OsiSolverInterface * solver, const OsiSimpleInteger * originalObject, int way, double value)

Create a standard floor/ceiling branch object.

Specifies a simple two-way branch. Let value = x*. One arm of the branch will be $lb \le x \le loor(x*)$, the other $ceil(x*) \le x \le ub$. Specify way = -1 to set the object state to perform the down arm first, way = 1 for the up arm.

7.18.2.2 OsiIntegerBranchingObject::OsiIntegerBranchingObject (OsiSolverInterface * solver, const OsiSimpleInteger * originalObject, int way, double value, double downUpperBound, double upLowerBound)

Create a standard floor/ceiling branch object.

Specifies a simple two-way branch in a more flexible way. One arm of the branch will be $lb \le x \le downUpperBound$, the other upLowerBound $t \le x \le downUpperBound$, the other upLowerBound $t \le x \le downUpperBound$, the other upLowerBound $t \le x \le downUpperBound$, the other upLowerBound $t \le x \le downUpperBound$, the other upLowerBound $t \le x \le downUpperBound$, the other upLowerBound $t \le x \le downUpperBound$, the other upLowerBound $t \le x \le downUpperBound$, and the other upLowerBound $t \le x \le downUpperBound$, the other upLowerBound $t \le x \le downUpperBound$, and the other upLowerBound $t \le x \le downUpperBound$, and the other upLowerBound $t \le x \le downUpperBound$, and the other upLowerBound $t \le x \le downUpperBound$, and the other upLowerBound $t \le x \le downUpperBound$, and the other upLowerBound $t \le x \le downUpperBound$.

7.18.3 Member Function Documentation

```
7.18.3.1 virtual double OsilntegerBranchingObject::branch (OsiSolverInterface * solver) [virtual]
```

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

state. Returns change in guessed objective on next branch

Implements OsiTwoWayBranchingObject.

The documentation for this class was generated from the following file:


OsiBranchingObject.hpp

7.19 OsiLotsize Class Reference


Lotsize class.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiLotsize:



Collaboration diagram for OsiLotsize:



Public Member Functions

- virtual OsiObject * clone () const Clone.
- virtual double infeasibility (const OsiBranchingInformation *info, int &whichWay) const Infeasibility - large is 0.5.
- virtual double feasibleRegion (OsiSolverInterface *solver, const OsiBranchingInformation *info) const Set bounds to contain the current solution.

virtual OsiBranchingObject * createBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way) const

Creates a branching object.

void setColumnNumber (int value)

Set solver column number.

virtual int columnNumber () const

Column number if single column object -1 otherwise, so returns >= 0 Used by heuristics.

virtual void resetBounds (const OsiSolverInterface *solver)

Reset original upper and lower bound values from the solver.

bool findRange (double value, double integerTolerance) const

Finds range of interest so value is feasible in range range_ or infeasible between hi[range_] and lo[range_+1].

• virtual void floorCeiling (double &floorLotsize, double &ceilingLotsize, double value, double tolerance) const

Returns floor and ceiling.

· double originalLowerBound () const

Original bounds.

int rangeType () const

Type - 1 points, 2 ranges.

int numberRanges () const

Number of points.

double * bound () const

Ranges.

virtual void resetSequenceEtc (int numberColumns, const int *originalColumns)

Change column numbers after preprocessing.

virtual double upEstimate () const

Return "up" estimate (default 1.0e-5)

virtual double downEstimate () const

Return "down" estimate (default 1.0e-5)

virtual bool canHandleShadowPrices () const
 Return true if knows how to deal with Pseudo Shadow Prices.

• virtual bool canDoHeuristics () const

Return true if object can take part in normal heuristics.

Additional Inherited Members

7.19.1 Detailed Description

Lotsize class.

Definition at line 827 of file OsiBranchingObject.hpp.

7.19.2 Member Function Documentation

```
7.19.2.1 virtual double OsiLotsize::feasibleRegion (OsiSolverInterface * solver, const OsiBranchingInformation * info ) const [virtual]
```

Set bounds to contain the current solution.

More precisely, for the variable associated with this object, take the value given in the current solution, force it within the current bounds if required, then set the bounds to fix the variable at the integer nearest the solution value. Returns amount it had to move variable.

Implements OsiObject.

7.19.2.2 virtual OsiBranchingObject* OsiLotsize::createBranch (OsiSolverInterface * solver, const OsiBranchingInformation * info, int way) const [virtual]

Creates a branching object.

The preferred direction is set by way, 0 for down, 1 for up.

Reimplemented from OsiObject.

7.19.2.3 virtual void OsiLotsize::resetBounds (const OsiSolverInterface * solver) [virtual]

Reset original upper and lower bound values from the solver.

Handy for updating bounds held in this object after bounds held in the solver have been tightened.

Reimplemented from OsiObject.

7.19.2.4 bool OsiLotsize::findRange (double value, double integerTolerance) const

Finds range of interest so value is feasible in range range_ or infeasible between hi[range_] and lo[range_+1].

Returns true if feasible.

The documentation for this class was generated from the following file:


OsiBranchingObject.hpp

7.20 OsiLotsizeBranchingObject Class Reference


Lotsize branching object.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiLotsizeBranchingObject:



Collaboration diagram for OsiLotsizeBranchingObject:



Public Member Functions

• OsiLotsizeBranchingObject ()

Default constructor.

 $\bullet \ \ OsiLotsize Branching Object \ (OsiSolverInterface *solver, const\ OsiLotsize *original Object, int way, double \ value)$

Create a lotsize floor/ceiling branch object.

OsiLotsizeBranchingObject (const OsiLotsizeBranchingObject &)

Copy constructor.

• OsiLotsizeBranchingObject & operator= (const OsiLotsizeBranchingObject &rhs)

Assignment operator.

• virtual OsiBranchingObject * clone () const

Clone.

virtual ∼OsiLotsizeBranchingObject ()

Destructor.

virtual double branch (OsiSolverInterface *solver)

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

virtual void print (const OsiSolverInterface *solver=NULL)

Print something about branch - only if log level high.

Protected Attributes

• double down_ [2]

Lower [0] and upper [1] bounds for the down arm (way_ = -1)

double up_[2]

Lower [0] and upper [1] bounds for the up arm (way = 1)

7.20.1 Detailed Description

Lotsize branching object.

This object can specify a two-way branch on an integer variable. For each arm of the branch, the upper and lower bounds on the variable can be independently specified.

Variable holds the index of the integer variable in the integer Variable array of the model.

Definition at line 957 of file OsiBranchingObject.hpp.

7.20.2 Constructor & Destructor Documentation

7.20.2.1 OsiLotsizeBranchingObject::OsiLotsizeBranchingObject (OsiSolverInterface * solver, const OsiLotsize * originalObject, int way, double value)

Create a lotsize floor/ceiling branch object.

Specifies a simple two-way branch. Let value = x*. One arm of the branch will be is $lb \le x \le valid$ range below(x*), the other valid range above(x*) $\le x \le ub$. Specify way = -1 to set the object state to perform the down arm first, way = 1 for the up arm.

7.20.3 Member Function Documentation

7.20.3.1 virtual double OsiLotsizeBranchingObject::branch (OsiSolverInterface * solver) [virtual]

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm

state. Returns change in guessed objective on next branch


Implements OsiTwoWayBranchingObject.

The documentation for this class was generated from the following file:


OsiBranchingObject.hpp

7.21 OsiMskSolverInterface Class Reference

Inheritance diagram for OsiMskSolverInterface:



Collaboration diagram for OsiMskSolverInterface:



Public Member Functions

• virtual void setObjSense (double s)

Set objective function sense (1 for min (default), -1 for max,)

virtual void setColSolution (const double *colsol)

Set the primal solution column values.

• virtual void setRowPrice (const double *rowprice)

Set dual solution vector.

const char * getCtype () const

return a vector of variable types (continous, binary, integer)

Solve methods

• virtual void initialSolve ()

Solve initial LP relaxation.

• virtual void resolve ()

Resolve an LP relaxation after problem modification.

virtual void branchAndBound ()

Invoke solver's built-in enumeration algorithm.

Parameter set/get methods

The set methods return true if the parameter was set to the given value, false otherwise.

There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the volume algorithm), the parameter is not yet implemented for the solver or simply the value of the parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.

The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.

bool setIntParam (OsiIntParam key, int value)

Set an integer parameter.

• bool setDblParam (OsiDblParam key, double value)

Set a double parameter.

bool setStrParam (OsiStrParam key, const std::string &value)

Set a string parameter.

bool getIntParam (OsiIntParam key, int &value) const

Get an integer parameter.

bool getDblParam (OsiDblParam key, double &value) const

Get a double parameter.

bool getStrParam (OsiStrParam key, std::string &value) const

Get a string parameter.

Methods returning info on how the solution process terminated

· virtual bool isAbandoned () const

Are there a numerical difficulties?

virtual bool isProvenOptimal () const

Is optimality proven?

virtual bool isProvenPrimalInfeasible () const

Is primal infeasiblity proven?

• virtual bool isProvenDualInfeasible () const

Is dual infeasiblity proven?

· virtual bool isPrimalObjectiveLimitReached () const

Is the given primal objective limit reached?

virtual bool isDualObjectiveLimitReached () const

Is the given dual objective limit reached?

· virtual bool isIterationLimitReached () const

Iteration limit reached?

• virtual bool isLicenseError () const

Has there been a license problem?

• int getRescode () const

Get rescode return of last Mosek optimizer call.

WarmStart related methods

CoinWarmStart * getEmptyWarmStart () const

Get an empty warm start object.

virtual CoinWarmStart * getWarmStart () const

Get warmstarting information.

virtual bool setWarmStart (const CoinWarmStart *warmstart)

Set warmstarting information.

Hotstart related methods (primarily used in strong branching).

 tr>

The user can create a hotstart (a snapshot) of the optimization process then reoptimize over and over again always starting from there.

NOTE: between hotstarted optimizations only bound changes are allowed.

virtual void markHotStart ()

Create a hotstart point of the optimization process.

virtual void solveFromHotStart ()

Optimize starting from the hotstart.

virtual void unmarkHotStart ()

Delete the snapshot.

Methods related to querying the input data

virtual int getNumCols () const

Get number of columns.

virtual int getNumRows () const

Get number of rows.

virtual int getNumElements () const

Get number of nonzero elements.

virtual const double * getColLower () const

Get pointer to array[getNumCols()] of column lower bounds.

virtual const double * getColUpper () const

Get pointer to array[getNumCols()] of column upper bounds.

virtual const char * getRowSense () const

Get pointer to array[getNumRows()] of row constraint senses.

virtual const double * getRightHandSide () const

Get pointer to array[getNumRows()] of rows right-hand sides.

virtual const double * getRowRange () const

Get pointer to array[getNumRows()] of row ranges.

virtual const double * getRowLower () const

Get pointer to array[getNumRows()] of row lower bounds.

virtual const double * getRowUpper () const

Get pointer to array[getNumRows()] of row upper bounds.

virtual const double * getObjCoefficients () const

Get pointer to array[getNumCols()] of objective function coefficients.

virtual double getObjSense () const

Get objective function sense (1 for min (default), -1 for max)

· virtual bool isContinuous (int colNumber) const

Return true if column is continuous.

virtual const CoinPackedMatrix * getMatrixByRow () const

Get pointer to row-wise copy of matrix.

virtual const CoinPackedMatrix * getMatrixByCol () const

Get pointer to column-wise copy of matrix.

virtual double getInfinity () const

Get solver's value for infinity.

Methods related to querying the solution

virtual const double * getColSolution () const

Get pointer to array[getNumCols()] of primal solution vector.

virtual const double * getRowPrice () const

Get pointer to array[getNumRows()] of dual prices.

virtual const double * getReducedCost () const

Get a pointer to array[getNumCols()] of reduced costs.

virtual const double * getRowActivity () const

Get pointer to array[getNumRows()] of row activity levels (constraint matrix times the solution vector.

virtual double getObjValue () const

Get objective function value.

virtual int getIterationCount () const

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

virtual std::vector< double * > getDualRays (int maxNumRays, bool fullRay=false) const

Get as many dual rays as the solver can provide.

virtual std::vector< double * > getPrimalRays (int maxNumRays) const

Get as many primal rays as the solver can provide.

Changing bounds on variables and constraints

virtual void setObjCoeff (int elementIndex, double elementValue)

Set an objective function coefficient.

virtual void setObjCoeffSet (const int *indexFirst, const int *indexLast, const double *coeffList)

Set a a set of objective function coefficients.

virtual void setColLower (int elementIndex, double elementValue)

Set a single column lower bound

Use -COIN_DBL_MAX for -infinity.

virtual void setColUpper (int elementIndex, double elementValue)

Set a single column upper bound

Use COIN_DBL_MAX for infinity.

virtual void setColBounds (int elementIndex, double lower, double upper)

Set a single column lower and upper bound

The default implementation just invokes setColLower() and setColUpper()

virtual void setColSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of columns simultaneously

The default implementation just invokes setCollower() and setColupper() over and over again.

virtual void setRowLower (int elementIndex, double elementValue)

Set a single row lower bound

Use -COIN_DBL_MAX for -infinity.

virtual void setRowUpper (int elementIndex, double elementValue)

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

virtual void setRowBounds (int elementIndex, double lower, double upper)

Set a single row lower and upper bound

The default implementation just invokes <code>setRowLower()</code> and <code>setRowUpper()</code>

• virtual void setRowType (int index, char sense, double rightHandSide, double range)

Set the type of a single row

virtual void setRowSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of rows simultaneously

The default implementation just invokes <code>setRowLower()</code> and <code>setRowUpper()</code> over and over again.

 virtual void setRowSetTypes (const int *indexFirst, const int *indexLast, const char *senseList, const double *rhsList, const double *rangeList)

Set the type of a number of rows simultaneously

The default implementation just invokes <code>setRowType()</code> and over again.

Integrality related changing methods

virtual void setContinuous (int index)

Set the index-th variable to be a continuous variable.

virtual void setInteger (int index)

Set the index-th variable to be an integer variable.

virtual void setContinuous (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be continuous variables.

virtual void setInteger (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be integer variables.

Methods to expand a problem.

Note that if a column is added then by default it will correspond to a continuous variable.

virtual void addCol (const CoinPackedVectorBase &vec, const double collb, const double colub, const double obi)

Add a column (primal variable) to the problem.

virtual void addCols (const int numcols, const CoinPackedVectorBase *const *cols, const double *collb, const double *collb, const double *obj)

Add a set of columns (primal variables) to the problem.

virtual void deleteCols (const int num, const int *colIndices)

Remove a set of columns (primal variables) from the problem.

virtual void addRow (const CoinPackedVectorBase &vec, const double rowlb, const double rowlb)

Add a row (constraint) to the problem.

 virtual void addRow (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng)

Add a row (constraint) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const double *rowlb, const double *rowub)

Add a set of rows (constraints) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const char *rowsen, const double *rowrhs, const double *rowrng)

Add a set of rows (constraints) to the problem.

virtual void deleteRows (const int num, const int *rowIndices)

Delete a set of rows (constraints) from the problem.

Methods to input a problem

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowlb, const double *rowlb

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&colub, double *&rowlb, double *&rowlb)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowrng)

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

 virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, char *&rowsen, double *&rowrhs, double *&rowrng)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowlb, const double *rowlb, const double *rowlb

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

 virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *colub, const double *obj, const char *rowsen, const double *rowrhs, const double *rowrng)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

virtual int readMps (const char *filename, const char *extension="mps")

Read an mps file from the given filename.

• virtual void writeMps (const char *filename, const char *extension="mps", double objSense=0.0) const Write the problem into an mps file of the given filename.

Message handling

void passInMessageHandler (CoinMessageHandler *handler)

Pass in a message handler It is the client's responsibility to destroy a message handler installed by this routine; it will not be destroyed when the solver interface is destroyed.

Constructors and destructor

OsiMskSolverInterface (MSKenv t mskenv=NULL)

Default Constructor optional argument mskenv can be used to reach in an initialized user environment OsiMsk assumes membership of mskenv, so it will be freed when the last instanciation of OsiMsk is deleted.

virtual OsiSolverInterface * clone (bool copyData=true) const

Clone.

OsiMskSolverInterface (const OsiMskSolverInterface &)

Copy constructor.

OsiMskSolverInterface & operator= (const OsiMskSolverInterface &rhs)

Assignment operator.

virtual ∼OsiMskSolverInterface ()

Destructor.

Static Public Member Functions

Static instance counter methods

static void incrementInstanceCounter ()

MOSEK has a context which must be created prior to all other MOSEK calls.

static void decrementInstanceCounter ()

MOSEK has a context which should be deleted after MOSEK calls.

static unsigned int getNumInstances ()

Return the number of instances of instantiated objects using MOSEK services.

Public Attributes

Private member data

MSKtask_t task_

MOSEK model represented by this class instance.

int * hotStartCStat

Hotstart information.

- int hotStartCStatSize
- int * hotStartRStat
- int hotStartRStatSize
- int hotStartMaxIteration_

Cached information derived from the MOSEK model

double * obj

Pointer to objective vector.

double * collower

Pointer to dense vector of variable lower bounds.

double * colupper

Pointer to dense vector of variable lower bounds.

• char * rowsense

Pointer to dense vector of row sense indicators.

double * rhs

Pointer to dense vector of row right-hand side values.

double * rowrange

Pointer to dense vector of slack upper bounds for range constraints (undefined for non-range rows)

double * rowlower

Pointer to dense vector of row lower bounds.

double * rowupper

Pointer to dense vector of row upper bounds.

double * colsol

Pointer to primal solution vector.

double * rowsol

Pointer to dual solution vector.

double * redcost

Pointer to reduced cost vector.

double * rowact

Pointer to row activity (slack) vector.

CoinPackedMatrix * matrixByRow

Pointer to row-wise copy of problem matrix coefficients.

CoinPackedMatrix * matrixByCol_

Pointer to row-wise copy of problem matrix coefficients.

Additional information needed for storing MIP problems

char * coltype

Pointer to dense vector of variable types (continous, binary, integer)

· int coltypesize_

Size of allocated memory for coltype_.

· bool probtypemip_

Stores whether MOSEK' prob type is currently set to MIP.

Protected Member Functions

Protected methods

virtual void applyRowCut (const OsiRowCut &rc)

Apply a row cut. Return true if cut was applied.

virtual void applyColCut (const OsiColCut &cc)

Apply a column cut (bound adjustment).

Friends

void OsiMskSolverInterfaceUnitTest (const std::string &mpsDir, const std::string &netlibDir)

A function that tests the methods in the OsiMskSolverInterface class.

MOSEK specific public interfaces

enum keepCachedFlag {
 KEEPCACHED_NONE = 0, KEEPCACHED_COLUMN = 1, KEEPCACHED_ROW = 2, KEEPCACHED_MATRIX
 = 4,
 KEEPCACHED_RESULTS = 8, KEEPCACHED_PROBLEM = KEEPCACHED_COLUMN | KEEPCACHED_ROW | KEEPCACHED_MATRIX, KEEPCACHED_ALL = KEEPCACHED_PROBLEM | KEEPCACHED_RESULTS,
 FREECACHED_COLUMN = KEEPCACHED_PROBLEM & ~KEEPCACHED_COLUMN,
 FREECACHED_ROW = KEEPCACHED_PROBLEM & ~KEEPCACHED_ROW, FREECACHED_MATRIX = K-

EEPCACHED PROBLEM & ~KEEPCACHED MATRIX, FREECACHED RESULTS = KEEPCACHED ALL &

Get pointer to MOSEK model and free all specified cached data entries (combined with logical or-operator '\'):

- MSKtask t getLpPtr (int keepCached=KEEPCACHED NONE)
- MSKenv t getEnvironmentPtr ()

~KEEPCACHED_RESULTS }

Method to access MOSEK environment pointer.

Private methods

MSKtask_t getMutableLpPtr () const

Get task Pointer for const methods.

void gutsOfCopy (const OsiMskSolverInterface &source)

The real work of a copy constructor (used by copy and assignment)

· void gutsOfConstructor ()

The real work of the constructor.

void gutsOfDestructor ()

The real work of the destructor.

void freeCachedColRim ()

free cached column rim vectors

void freeCachedRowRim ()

free cached row rim vectors

void freeCachedResults ()

free cached result vectors

void freeCachedMatrix ()

free cached matrices

void freeCachedData (int keepCached=KEEPCACHED_NONE)

free all cached data (except specified entries, see getLpPtr())

void freeAllMemory ()

free all allocated memory

Additional Inherited Members

7.21.1 Detailed Description

Definition at line 23 of file OsiMskSolverInterface.hpp.

7.21.2 Member Enumeration Documentation

7.21.2.1 enum OsiMskSolverInterface::keepCachedFlag

Get pointer to MOSEK model and free all specified cached data entries (combined with logical or-operator '|'):

Enumerator:

KEEPCACHED_NONE discard all cached data (default)

KEEPCACHED_COLUMN column information: objective values, lower and upper bounds, variable types

KEEPCACHED_ROW row information: right hand sides, ranges and senses, lower and upper bounds for row

KEEPCACHED MATRIX problem matrix: matrix ordered by column and by row

KEEPCACHED_RESULTS LP solution: primal and dual solution, reduced costs, row activities.

KEEPCACHED_PROBLEM only discard cached LP solution

KEEPCACHED_ALL keep all cached data (similar to getMutableLpPtr())

FREECACHED_COLUMN free only cached column and LP solution information

FREECACHED_ROW free only cached row and LP solution information

FREECACHED_MATRIX free only cached matrix and LP solution information

FREECACHED_RESULTS free only cached LP solution information

Definition at line 598 of file OsiMskSolverInterface.hpp.

7.21.3 Member Function Documentation

7.21.3.1 CoinWarmStart* OsiMskSolverInterface::getEmptyWarmStart()const [virtual]

Get an empty warm start object.

This routine returns an empty **CoinWarmStartBasis** object. Its purpose is to provide a way to give a client a warm start basis object of the appropriate type, which can resized and modified as desired.

Implements OsiSolverInterface.

```
7.21.3.2 virtual bool OsiMskSolverInterface::setWarmStart ( const CoinWarmStart * warmstart ) [virtual]
```

Set warmstarting information.

Return true/false depending on whether the warmstart information was accepted or not.

Implements OsiSolverInterface.

```
7.21.3.3 virtual const char* OsiMskSolverInterface::getRowSense() const [virtual]
```

Get pointer to array[getNumRows()] of row constraint senses.

- 'L': <= constraint
- 'E': = constraint
- 'G': >= constraint
- · 'R': ranged constraint
- · 'N': free constraint

Implements OsiSolverInterface.

7.21.3.4 virtual const double* OsiMskSolverInterface::getRightHandSide() const [virtual]

Get pointer to array[getNumRows()] of rows right-hand sides.

- if rowsense()[i] == 'L' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'G' then rhs()[i] == rowlower()[i]
- if rowsense()[i] == 'R' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'N' then rhs()[i] == 0.0

Implements OsiSolverInterface.

```
7.21.3.5 virtual const double* OsiMskSolverInterface::getRowRange( ) const [virtual]
```

Get pointer to array[getNumRows()] of row ranges.

- if rowsense()[i] == 'R' then rowrange()[i] == rowupper()[i] rowlower()[i]
- if rowsense()[i] != 'R' then rowrange()[i] is 0.0

Implements OsiSolverInterface.

```
7.21.3.6 virtual int OsiMskSolverInterface::getIterationCount() const [virtual]
```

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

Implements OsiSolverInterface.

```
7.21.3.7 virtual std::vector<double*> OsiMskSolverInterface::getDualRays ( int maxNumRays, bool fullRay = false ) const [virtual]
```

Get as many dual rays as the solver can provide.

(In case of proven primal infeasibility there should be at least one.)

The first getNumRows() ray components will always be associated with the row duals (as returned by getRowPrice()). If fullRay is true, the final getNumCols() entries will correspond to the ray components associated with the nonbasic variables. If the full ray is requested and the method cannot provide it, it will throw an exception.

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumRows() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

```
7.21.3.8 virtual std::vector<double*> OsiMskSolverInterface::getPrimalRays ( int maxNumRays ) const [virtual]
```

Get as many primal rays as the solver can provide.

(In case of proven dual infeasibility there should be at least one.)

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumCols() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

7.21.3.9 virtual void OsiMskSolverInterface::setColLower (int elementIndex, double elementValue) [virtual]

Set a single column lower bound

Use -COIN DBL MAX for -infinity.

Implements OsiSolverInterface.

7.21.3.10 virtual void OsiMskSolverInterface::setColUpper (int elementIndex, double elementValue) [virtual]

Set a single column upper bound

Use COIN DBL MAX for infinity.

Implements OsiSolverInterface.

7.21.3.11 virtual void OsiMskSolverInterface::setColSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of columns simultaneously

The default implementation just invokes setCollower() and setColupper() over and over again.

Parameters

	contains the indices of the constraints whose either bound changes
<code>[indexfire</code>	t,index-
Last]	
boundLis	the new lower/upper bound pairs for the variables

Reimplemented from OsiSolverInterface.

7.21.3.12 virtual void OsiMskSolverInterface::setRowLower (int elementIndex, double elementValue) [virtual]

Set a single row lower bound

Use -COIN DBL MAX for -infinity.

Implements OsiSolverInterface.

7.21.3.13 virtual void OsiMskSolverInterface::setRowUpper(int elementIndex, double elementValue) [virtual]

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.21.3.14 virtual void OsiMskSolverInterface::setRowSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

Parameters

		contains the indices of the constraints whose either bound changes
	<code>[indexfirst,</code>	index-
	Last]	
Ī	boundList	the new lower/upper bound pairs for the constraints

Reimplemented from OsiSolverInterface.

```
7.21.3.15 virtual void OsiMskSolverInterface::setRowSetTypes ( const int * indexFirst, const int * indexLast, const char * senseList, const double * rhsList, const double * rangeList ) [virtual]
```

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType () and over and over again.

Parameters

	contains the indices of the constraints whose type changes
<code>[indexfirst,</code>	index-
Last]	
senseList	the new senses
rhsList	the new right hand sides
rangeList	the new ranges

Reimplemented from OsiSolverInterface.

```
7.21.3.16 virtual void OsiMskSolverInterface::setColSolution ( const double * colsol ) [virtual]
```

Set the primal solution column values.

colsol[numcols()] is an array of values of the problem column variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of colsol() until changed by another call to setColsol() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

```
7.21.3.17 virtual void OsiMskSolverInterface::setRowPrice ( const double * rowprice ) [virtual]
```

Set dual solution vector.

rowprice[numrows()] is an array of values of the problem row dual variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of rowprice() until changed by another call to setRowprice() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.21.3.18 virtual void OsiMskSolverInterface::addCol (const CoinPackedVectorBase & vec, const double collb, const double collb, const double obj) [virtual]

Add a column (primal variable) to the problem.

Implements OsiSolverInterface.

7.21.3.19 virtual void OsiMskSolverInterface::addCols (const int *numcols*, const CoinPackedVectorBase *const * cols, const double * collb, const double

Add a set of columns (primal variables) to the problem.

The default implementation simply makes repeated calls to addCol().

Reimplemented from OsiSolverInterface.

7.21.3.20 virtual void OsiMskSolverInterface::deleteCols (const int num, const int * colIndices) [virtual]

Remove a set of columns (primal variables) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted variables are nonbasic.

Implements OsiSolverInterface.

7.21.3.21 virtual void OsiMskSolverInterface::addRow (const CoinPackedVectorBase & *vec*, const double *rowlb*, const double *rowub*) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.21.3.22 virtual void OsiMskSolverInterface::addRow (const CoinPackedVectorBase & *vec*, const char *rowsen*, const double *rowrhs*, const double *rowrng*) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.21.3.23 virtual void OsiMskSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * rows, const double * rowlb, const double * rowub) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.21.3.24 virtual void OsiMskSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * rows, const char * rowsen, const double * rowrhs, const double * rowrng) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.21.3.25 virtual void OsiMskSolverInterface::deleteRows (const int num, const int * rowIndices) [virtual]

Delete a set of rows (constraints) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted rows are loose. Implements OsiSolverInterface.

7.21.3.26 virtual void OsiMskSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowlb, const double * rowlb, const double * rowlb) [virtual]

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0

- · rowub: all rows have upper bound infinity
- · rowlb: all rows have lower bound -infinity
- obj: all variables have 0 objective coefficient

Implements OsiSolverInterface.

7.21.3.27 virtual void OsiMskSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowlb, double *& rowlb) [virtual]

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

```
7.21.3.28 virtual void OsiMskSolverInterface::loadProblem ( const CoinPackedMatrix & matrix, const double * collb, const double * colub, const double * colub, const double * rowrns, const double * rowrns, const double * rowrns )

[virtual]
```

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets). If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- obj: all variables have 0 objective coefficient
- rowsen: all rows are >=
- rowrhs: all right hand sides are 0
- rowrng: 0 for the ranged rows

Implements OsiSolverInterface.

7.21.3.29 virtual void OsiMskSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowrhs, double *& rowrng) [virtual]

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

```
7.21.3.30 virtual void OsiMskSolverInterface::loadProblem ( const int numcols, const int numrows, const int * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const double * rowlb, const double * rowub ) [virtual]
```

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

7.21.3.31 virtual void OsiMskSolverInterface::loadProblem (const int *numcols*, const int *numrows*, const int * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const char * rowsen, const double * rowrhs, const double * rowrng) [virtual]

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

7.21.3.32 virtual void OsiMskSolverInterface::writeMps (const char * filename, const char * extension = "mps", double objSense = 0.0) const [virtual]

Write the problem into an mps file of the given filename.

If objSense is non zero then -1.0 forces the code to write a maximization objective and +1.0 to write a minimization one. If 0.0 then solver can do what it wants

Implements OsiSolverInterface.

7.21.3.33 static void OsiMskSolverInterface::incrementInstanceCounter() [static]

MOSEK has a context which must be created prior to all other MOSEK calls.

This method:

- Increments by 1 the number of uses of the MOSEK environment.
- Creates the MOSEK context when the number of uses is change to 1 from 0.

7.21.3.34 static void OsiMskSolverInterface::decrementInstanceCounter() [static]

MOSEK has a context which should be deleted after MOSEK calls.

This method:

- Decrements by 1 the number of uses of the MOSEK environment.
- Deletes the MOSEK context when the number of uses is change to 0 from 1.

7.21.3.35 virtual void OsiMskSolverInterface::applyColCut (const OsiColCut & cc) [protected], [virtual]

Apply a column cut (bound adjustment).

Return true if cut was applied.

Implements OsiSolverInterface.

The documentation for this class was generated from the following file:


OsiMskSolverInterface.hpp

7.22 OsiObject Class Reference

Abstract base class for 'objects'.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiObject:



Public Member Functions

• OsiObject ()

Default Constructor.

• OsiObject (const OsiObject &)

Copy constructor.

• OsiObject & operator= (const OsiObject &rhs)

Assignment operator.

• virtual OsiObject * clone () const =0

Clone.

virtual ∼OsiObject ()

Destructor.

• double infeasibility (const OsiSolverInterface *solver, int &whichWay) const

Infeasibility of the object.

virtual double feasibleRegion (OsiSolverInterface *solver) const

For the variable(s) referenced by the object, look at the current solution and set bounds to match the solution.

• virtual double feasibleRegion (OsiSolverInterface *solver, const OsiBranchingInformation *info) const =0

For the variable(s) referenced by the object, look at the current solution and set bounds to match the solution.

- virtual OsiBranchingObject * createBranch (OsiSolverInterface *, const OsiBranchingInformation *, int) const Create a branching object and indicate which way to branch first.
- virtual bool canDoHeuristics () const

Return true if object can take part in normal heuristics.

• virtual bool canMoveToNearest () const

Return true if object can take part in move to nearest heuristic.

• virtual int columnNumber () const

Column number if single column object -1 otherwise, Used by heuristics.

· int priority () const

Return Priority - note 1 is highest priority.

void setPriority (int priority)

Set priority.

virtual bool boundBranch () const

Return true if branch should only bound variables.

virtual bool canHandleShadowPrices () const

Return true if knows how to deal with Pseudo Shadow Prices.

• int numberWays () const

Return maximum number of ways branch may have.

· void setNumberWays (int numberWays)

Set maximum number of ways branch may have.

void setWhichWay (int way)

Return preferred way to branch.

• int whichWay () const

Return current preferred way to branch.

· virtual int preferredWay () const

Get pre-emptive preferred way of branching - -1 off, 0 down, 1 up (for 2-way)

· double infeasibility () const

Return infeasibility.

• virtual double upEstimate () const

Return "up" estimate (default 1.0e-5)

· virtual double downEstimate () const

Return "down" estimate (default 1.0e-5)

virtual void resetBounds (const OsiSolverInterface *)

Reset variable bounds to their original values.

virtual void resetSequenceEtc (int, const int *)

Change column numbers after preprocessing.

virtual void updateBefore (const OsiObject *)

Updates stuff like pseudocosts before threads.

virtual void updateAfter (const OsiObject *, const OsiObject *)

Updates stuff like pseudocosts after threads finished.

Protected Attributes

double infeasibility

data

short whichWay

Computed preferred way to branch.

short numberWays_

Maximum number of ways on branch.

int priority_

Priority.

7.22.1 Detailed Description

Abstract base class for 'objects'.

The branching model used in Osi is based on the idea of an *object*. In the abstract, an object is something that has a feasible region, can be evaluated for infeasibility, can be branched on (*i.e.*, there's some constructive action to be taken to move toward feasibility), and allows comparison of the effect of branching.

This class (OsiObject) is the base class for an object. To round out the branching model, the class OsiBranchingObject describes how to perform a branch, and the class OsiBranchDecision describes how to compare two OsiBranching-Objects.

To create a new type of object you need to provide three methods: infeasibility(), feasibleRegion(), and createBranch(), described below.

This base class is primarily virtual to allow for any form of structure. Any form of discontinuity is allowed.

As there is an overhead in getting information from solvers and because other useful information is available there is also an OsiBranchingInformation class which can contain pointers to information. If used it must at minimum contain pointers to current value of objective, maximum allowed objective and pointers to arrays for bounds and solution and direction of optimization. Also integer and primal tolerance.

Classes which inherit might have other information such as depth, number of solutions, pseudo-shadow prices etc etc. May be easier just to throw in here - as I keep doing

Definition at line 56 of file OsiBranchingObject.hpp.

7.22.2 Member Function Documentation

7.22.2.1 double OsiObject::infeasibility (const OsiSolverInterface * solver, int & whichWay) const

Infeasibility of the object.

This is some measure of the infeasibility of the object. 0.0 indicates that the object is satisfied.

The preferred branching direction is returned in which Way, where for normal two-way branching 0 is down, 1 is up

This is used to prepare for strong branching but should also think of case when no strong branching

The object may also compute an estimate of cost of going "up" or "down". This will probably be based on pseudo-cost ideas

This should also set mutable infeasibility and which Way This is for instant re-use for speed

Default for this just calls infeasibility with OsiBranchingInformation NOTE - Convention says that an infeasibility of COI-N_DBL_MAX means object has worked out it can't be satisfied!

```
7.22.2.2 virtual double OsiObject::feasibleRegion ( OsiSolverInterface * solver ) const [virtual]
```

For the variable(s) referenced by the object, look at the current solution and set bounds to match the solution.

Returns measure of how much it had to move solution to make feasible

```
7.22.2.3 virtual double OsiObject::feasibleRegion ( OsiSolverInterface * solver, const OsiBranchingInformation * info ) const [pure virtual]
```

For the variable(s) referenced by the object, look at the current solution and set bounds to match the solution.

Returns measure of how much it had to move solution to make feasible Faster version

Implemented in OsiLotsize, OsiSOS, and OsiSimpleInteger.

7.22.2.4 virtual OsiBranchingObject* OsiObject::createBranch (OsiSolverInterface * , const OsiBranchingInformation * , int) const [inline], [virtual]

Create a branching object and indicate which way to branch first.

The branching object has to know how to create branches (fix variables, etc.)

Reimplemented in OsiLotsize, OsiSOS, and OsiSimpleInteger.

Definition at line 119 of file OsiBranchingObject.hpp.

7.22.2.5 void OsiObject::setWhichWay (int way) [inline]

Return preferred way to branch.

If two then way=0 means down and 1 means up, otherwise way points to preferred branch

Definition at line 158 of file OsiBranchingObject.hpp.

7.22.2.6 int OsiObject::whichWay () const [inline]

Return current preferred way to branch.

If two then way=0 means down and 1 means up, otherwise way points to preferred branch

Definition at line 164 of file OsiBranchingObject.hpp.

7.22.2.7 virtual void OsiObject::resetBounds (const OsiSolverInterface *) [inline], [virtual]

Reset variable bounds to their original values.

Bounds may be tightened, so it may be good to be able to reset them to their original values.

Reimplemented in OsiLotsize, and OsiSimpleInteger.

Definition at line 180 of file OsiBranchingObject.hpp.

7.22.3 Member Data Documentation

7.22.3.1 double OsiObject::infeasibility [mutable], [protected]

data

Computed infeasibility

Definition at line 193 of file OsiBranchingObject.hpp.

The documentation for this class was generated from the following file:


OsiBranchingObject.hpp

7.23 OsiObject2 Class Reference


Define a class to add a bit of complexity to OsiObject This assumes 2 way branching.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiObject2:



Collaboration diagram for OsiObject2:



Public Member Functions

• OsiObject2 ()

Default Constructor.

• OsiObject2 (const OsiObject2 &)

Copy constructor.

• OsiObject2 & operator= (const OsiObject2 &rhs)

Assignment operator.

virtual ∼OsiObject2 ()

Destructor.

• void setPreferredWay (int value)

Set preferred way of branching - -1 off, 0 down, 1 up (for 2-way)

· virtual int preferredWay () const

Get preferred way of branching - -1 off, 0 down, 1 up (for 2-way)

Protected Attributes

int preferredWay_

Preferred way of branching - -1 off, 0 down, 1 up (for 2-way)

double otherInfeasibility

"Infeasibility" on other way

7.23.1 Detailed Description

Define a class to add a bit of complexity to OsiObject This assumes 2 way branching.

Definition at line 206 of file OsiBranchingObject.hpp.

The documentation for this class was generated from the following file:

OsiBranchingObject.hpp

7.24 OsiPresolve Class Reference

OSI interface to COIN problem simplification capabilities.

```
#include <OsiPresolve.hpp>
```

Public Member Functions

• OsiPresolve ()

Default constructor (empty object)

virtual ∼OsiPresolve ()

Virtual destructor.

 virtual OsiSolverInterface * presolvedModel (OsiSolverInterface & origModel, double feasibilityTolerance=0.0, bool keepIntegers=true, int numberPasses=5, const char *prohibited=NULL, bool doStatus=true, const char *row-Prohibited=NULL)

Create a new OsiSolverInterface loaded with the presolved problem.

virtual void postsolve (bool updateStatus=true)

Restate the solution to the presolved problem in terms of the original problem and load it into the original model.

OsiSolverInterface * model () const

Return a pointer to the presolved model.

OsiSolverInterface * originalModel () const

Return a pointer to the original model.

void setOriginalModel (OsiSolverInterface *model)

Set the pointer to the original model.

const int * originalColumns () const

Return a pointer to the original columns.

const int * originalRows () const

Return a pointer to the original rows.

int getNumRows () const

Return number of rows in original model.

int getNumCols () const

Return number of columns in original model.

void setNonLinearValue (double value)

"Magic" number.

void setPresolveActions (int action)

Fine control over presolve actions.

Protected Member Functions

virtual const CoinPresolveAction * presolve (CoinPresolveMatrix *prob)

Apply presolve transformations to the problem.

virtual void postsolve (CoinPostsolveMatrix &prob)

Reverse presolve transformations to recover the solution to the original problem.

· void gutsOfDestroy ()

Destroys queued postsolve actions.

7.24.1 Detailed Description

OSI interface to COIN problem simplification capabilities.

COIN provides a number of classes which implement problem simplification algorithms (**CoinPresolveAction**, **Coin-PrePostsolveMatrix**, and derived classes). The model of operation is as follows:

- · Create a copy of the original problem.
- Subject the copy to a series of transformations (the *presolve* methods) to produce a presolved model. Each transformation is also expected to provide a method to reverse the transformation (the *postsolve* method). The postsolve methods are collected in a linked list; the postsolve method for the final presolve transformation is at the head of the list.
- · Hand the presolved problem to the solver for optimization.
- Apply the collected postsolve methods to the presolved problem and solution, restating the solution in terms of the original problem.

The COIN presolve algorithms are unaware of OSI. The OsiPresolve class takes care of the interface. Given an Osi-SolverInterface origModel, it will take care of creating a clone properly loaded with the presolved problem and ready for optimization. After optimization, it will apply postsolve transformations and load the result back into origModel.

Assuming a problem has been loaded into an OsiSolverInterface origModel, a bare-bones application looks like this:

Definition at line 62 of file OsiPresolve.hpp.

7.24.2 Member Function Documentation

7.24.2.1 virtual OsiSolverInterface* OsiPresolve::presolvedModel (OsiSolverInterface & origModel, double feasibilityTolerance = 0.0, bool keepIntegers = true, int numberPasses = 5, const char * prohibited = NULL, bool doStatus = true, const char * rowProhibited = NULL) [virtual]

Create a new OsiSolverInterface loaded with the presolved problem.

This method implements the first two steps described in the class documentation. It clones <code>origModel</code> and applies presolve transformations, storing the resulting list of postsolve transformations. It returns a pointer to a new <code>OsiSolver-Interface</code> loaded with the presolved problem, or NULL if the problem is infeasible or unbounded. If <code>keepIntegers</code> is true then bounds may be tightened in the original. Bounds will be moved by up to <code>feasibilityTolerance</code> to try and stay feasible. When <code>doStatus</code> is true, the current solution will be transformed to match the presolved model.

This should be paired with postsolve(). It is up to the client to destroy the returned OsiSolverInterface, *after* calling postsolve().

This method is virtual. Override this method if you need to customize the steps of creating a model to apply presolve transformations.

In some sense, a wrapper for presolve(CoinPresolveMatrix*).

```
7.24.2.2 virtual void OsiPresolve::postsolve ( bool updateStatus = true ) [virtual]
```

Restate the solution to the presolved problem in terms of the original problem and load it into the original model.

postsolve() restates the solution in terms of the original problem and updates the original OsiSolverInterface supplied to presolvedModel(). If the problem has not been solved to optimality, there are no guarantees. If you are using an algorithm like simplex that has a concept of a basic solution, then set updateStatus

The advantage of going back to the original problem is that it will be exactly as it was, i.e., 0.0 will not become 1.0e-19.

Note that if you modified the original problem after presolving, then you must "undo" these modifications before calling postsolve().

In some sense, a wrapper for postsolve(CoinPostsolveMatrix&).

```
7.24.2.3 OsiSolverInterface * OsiPresolve::model ( ) const
```

Return a pointer to the presolved model.

```
7.24.2.4 void OsiPresolve::setNonLinearValue ( double value ) [inline]
```

"Magic" number.

If this is non-zero then any elements with this value may change and so presolve is very limited in what can be done to the row and column. This is for non-linear problems.

Definition at line 144 of file OsiPresolve.hpp.

```
7.24.2.5 void OsiPresolve::setPresolveActions (int action) [inline]
```

Fine control over presolve actions.

Set/clear the following bits to allow or suppress actions:

- 0x01 allow duplicate column processing on integer columns and dual stuff on integers
- 0x02 switch off actions which can change +1 to something else (doubleton, tripleton, implied free)
- 0x04 allow transfer of costs from singletons and between integer variables (when advantageous)
- 0x08 do not allow x+y+z=1 transform

- 0x10 allow actions that don't easily unroll
- · 0x20 allow dubious gub element reduction

GUB element reduction is only partially implemented in CoinPresolve (see **gubrow_action**) and willl cause an abort at postsolve. It's not clear what's meant by 'dual stuff on integers'. – Ih, 110605 –

Definition at line 166 of file OsiPresolve.hpp.

```
7.24.2.6 virtual const CoinPresolveAction* OsiPresolve::presolve( CoinPresolveMatrix * prob ) [protected], [virtual]
```

Apply presolve transformations to the problem.

Handles the core activity of applying presolve transformations.

If you want to apply the individual presolve routines differently, or perhaps add your own to the mix, define a derived class and override this method

```
7.24.2.7 virtual void OsiPresolve::postsolve (CoinPostsolveMatrix & prob) [protected], [virtual]
```

Reverse presolve transformations to recover the solution to the original problem.

Handles the core activity of applying postsolve transformations.

Postsolving is pretty generic; just apply the transformations in reverse order. You will probably only be interested in overriding this method if you want to add code to test for consistency while debugging new presolve techniques.

```
7.24.2.8 void OsiPresolve::gutsOfDestroy() [protected]
```

Destroys queued postsolve actions.

E.g., when presolve() determines the problem is infeasible, so that it will not be necessary to actually solve the presolved problem and convert the result back to the original problem.

The documentation for this class was generated from the following file:

OsiPresolve.hpp

7.25 OsiPseudoCosts Class Reference

This class is the placeholder for the pseudocosts used by OsiChooseStrong.

```
#include <OsiChooseVariable.hpp>
```

Public Member Functions

int numberBeforeTrusted () const

Number of times before trusted.

void setNumberBeforeTrusted (int value)

Set number of times before trusted.

• void initialize (int n)

Initialize the pseudocosts with n entries.

int numberObjects () const

Give the number of objects for which pseudo costs are stored.

virtual void updateInformation (const OsiBranchingInformation *info, int branch, OsiHotInfo *hotInfo)

Given a candidate fill in useful information e.g. estimates.

 virtual void updateInformation (int whichObject, int branch, double changeInObjective, double changeInValue, int status)

Given a branch fill in useful information e.g. estimates.

Accessor methods to pseudo costs data

- double * upTotalChange ()
- · const double * upTotalChange () const
- double * downTotalChange ()
- const double * downTotalChange () const
- int * upNumber ()
- const int * upNumber () const
- int * downNumber ()
- const int * downNumber () const

Protected Attributes

double * upTotalChange_

Total of all changes up.

• double * downTotalChange_

Total of all changes down.

int * upNumber_

Number of times up.

int * downNumber_

Number of times down.

int numberObjects

Number of objects (could be found from solver)

• int numberBeforeTrusted_

Number before we trust.

7.25.1 Detailed Description

This class is the placeholder for the pseudocosts used by OsiChooseStrong.

It can also be used by any other pseudocost based strong branching algorithm.

Definition at line 240 of file OsiChooseVariable.hpp.

The documentation for this class was generated from the following file:


OsiChooseVariable.hpp

7.26 OsiRowCut Class Reference


Row Cut Class.

#include <OsiRowCut.hpp>

Inheritance diagram for OsiRowCut:



Collaboration diagram for OsiRowCut:



Public Member Functions

• void sortIncrIndex ()

Allow access row sorting function.

Row bounds

- OsiRowCut_inline double lb () const Get lower bound.
- $\bullet \ \, {\sf OsiRowCut_inline} \ \, {\sf void} \ \, {\sf setLb} \ \, ({\sf double} \ \, {\sf lb})$

Set lower bound.

 OsiRowCut_inline double ub () const Get upper bound. OsiRowCut_inline void setUb (double ub)
 Set upper bound.

Row rhs, sense, range

• char sense () const

Get sense ('E', 'G', 'L', 'N', 'R')

· double rhs () const

Get right-hand side.

double range () const

Get range (ub - lb for 'R' rows, 0 otherwise)

Row elements

OsiRowCut_inline void setRow (int size, const int *colIndices, const double *elements, bool testForDuplicate-Index=COIN_DEFAULT_VALUE_FOR_DUPLICATE)

Set row elements.

OsiRowCut inline void setRow (const CoinPackedVector &v)

Set row elements from a packed vector.

· OsiRowCut inline const

CoinPackedVector & row () const

Get row elements.

OsiRowCut_inline CoinPackedVector & mutableRow ()

Get row elements for changing.

Comparison operators

 OsiRowCut_inline bool operator== (const OsiRowCut &rhs) const equal - true if lower bound, upper bound, row elements, and OsiCut are equal.

 OsiRowCut_inline bool operator!= (const OsiRowCut &rhs) const not equal

Sanity checks on cut

OsiRowCut_inline bool consistent () const

Returns true if the cut is consistent.

OsiRowCut inline bool consistent (const OsiSolverInterface &im) const

Returns true if cut is consistent with respect to the solver interface's model.

OsiRowCut_inline bool infeasible (const OsiSolverInterface &im) const

Returns true if the row cut itself is infeasible and cannot be satisfied.

virtual double violated (const double *solution) const

Returns infeasibility of the cut with respect to solution passed in i.e.

Arithmetic operators. Apply CoinPackedVector methods to the vector

void operator+= (double value)

add value to every vector entry

• void operator-= (double value)

subtract value from every vector entry

• void operator*= (double value)

multiply every vector entry by value

void operator/= (double value)

divide every vector entry by value

Constructors and destructors

OsiRowCut & operator= (const OsiRowCut &rhs)

Assignment operator.

OsiRowCut (const OsiRowCut &)

Copy constructor.

virtual OsiRowCut * clone () const

Clone.

• OsiRowCut ()

Default Constructor.

- OsiRowCut (double cutlb, double cutub, int capacity, int size, int *&colIndices, double *&elements)
 - Ownership Constructor.
- virtual ~OsiRowCut ()

Destructor.

Debug stuff

· virtual void print () const

Print cuts in collection.

Friends

• void OsiRowCutUnitTest (const OsiSolverInterface *baseSiP, const std::string &mpsDir)

A function that tests the methods in the OsiRowCut class.

Additional Inherited Members

7.26.1 Detailed Description

Row Cut Class.

A row cut has:

- · a lower bound
- · an upper bound
- · a vector of row elements

Definition at line 29 of file OsiRowCut.hpp.

7.26.2 Constructor & Destructor Documentation

7.26.2.1 OsiRowCut::OsiRowCut (double cutlb, double cutub, int capacity, int size, int *& collndices, double *& elements)

Ownership Constructor.

This constructor assumes ownership of the vectors passed as parameters for indices and elements. colIndices and elements will be NULL on return.

7.26.3 Member Function Documentation

7.26.3.1 OsiRowCut_inline bool OsiRowCut::consistent() const [virtual]

Returns true if the cut is consistent.

This checks to ensure that:

- The row element vector does not have duplicate indices
- The row element vector indices are >= 0

Implements OsiCut.

7.26.3.2 OsiRowCut_inline bool OsiRowCut::consistent (const OsiSolverInterface & im) const [virtual]

Returns true if cut is consistent with respect to the solver interface's model.

This checks to ensure that

The row element vector indices are < the number of columns in the model

Implements OsiCut.

7.26.3.3 OsiRowCut_inline bool OsiRowCut::infeasible (const OsiSolverInterface & im) const [virtual]

Returns true if the row cut itself is infeasible and cannot be satisfied.

This checks whether

• the lower bound is strictly greater than the upper bound.

Implements OsiCut.

7.26.3.4 virtual double OsiRowCut::violated (const double * solution) const [virtual]

Returns infeasibility of the cut with respect to solution passed in i.e.

is positive if cuts off that solution. solution is getNumCols() long..

Implements OsiCut.

7.26.4 Friends And Related Function Documentation

7.26.4.1 void OsiRowCutUnitTest (const OsiSolverInterface * baseSiP, const std::string & mpsDir) [friend]

A function that tests the methods in the OsiRowCut class.

The documentation for this class was generated from the following file:


· OsiRowCut.hpp

7.27 OsiRowCut2 Class Reference


Row Cut Class which refers back to row which created it.

#include <OsiRowCut.hpp>

Inheritance diagram for OsiRowCut2:



Collaboration diagram for OsiRowCut2:



Public Member Functions

Which row

• int whichRow () const

Get row.

void setWhichRow (int row)

Set row.

Constructors and destructors

OsiRowCut2 & operator= (const OsiRowCut2 &rhs)

Assignment operator.

OsiRowCut2 (const OsiRowCut2 &)

Copy constructor.

virtual OsiRowCut * clone () const

Clone.

OsiRowCut2 (int row=-1)

Default Constructor.

virtual ~OsiRowCut2 ()

Destructor.

Additional Inherited Members

7.27.1 Detailed Description

Row Cut Class which refers back to row which created it.

It may be useful to strengthen a row rather than add a cut. To do this we need to know which row is strengthened. This trivial extension to OsiRowCut does that.

Definition at line 290 of file OsiRowCut.hpp.

The documentation for this class was generated from the following file:

OsiRowCut.hpp

7.28 OsiRowCutDebugger Class Reference

Validate cuts against a known solution.

```
#include <OsiRowCutDebugger.hpp>
```

Public Member Functions

Validate Row Cuts

Check that the specified cuts do not cut off the known solution.

- virtual int validateCuts (const OsiCuts &cs, int first, int last) const
 Check that the set of cuts does not cut off the solution known to the debugger.
- virtual bool invalidCut (const OsiRowCut &rowcut) const

Check that the cut does not cut off the solution known to the debugger.

bool onOptimalPath (const OsiSolverInterface &si) const

Returns true if the solution held in the solver is compatible with the known solution.

Activate the Debugger

The debugger is considered to be active when it holds a known solution.

- bool activate (const OsiSolverInterface &si, const char *model)
 - Activate a debugger using the name of a problem.
- bool activate (const OsiSolverInterface &si, const double *solution, bool keepContinuous=false)

Activate a debugger using a full solution array.

· bool active () const

Returns true if the debugger is active.

Query or Manipulate the Known Solution

const double * optimalSolution () const

Return the known solution.

int numberColumns () const

Return the number of columns in the known solution.

double optimalValue () const

Return the value of the objective for the known solution.

void redoSolution (int numberColumns, const int *originalColumns)

Edit the known solution to reflect column changes.

int printOptimalSolution (const OsiSolverInterface &si) const

Print optimal solution (returns -1 bad debug, 0 on optimal, 1 not)

Constructors and Destructors

OsiRowCutDebugger ()

Default constructor - no checking.

OsiRowCutDebugger (const OsiSolverInterface &si, const char *model)

Constructor with name of model.

- OsiRowCutDebugger (const OsiSolverInterface &si, const double *solution, bool enforceOptimality=false) Constructor with full solution.
- OsiRowCutDebugger (const OsiRowCutDebugger &)

Copy constructor.

OsiRowCutDebugger & operator= (const OsiRowCutDebugger &rhs)

Assignment operator.

virtual ~OsiRowCutDebugger ()

Destructor.

Friends

void OsiRowCutDebuggerUnitTest (const OsiSolverInterface *siP, const std::string &mpsDir)

A function that tests the methods in the OsiRowCutDebugger class.

7.28.1 Detailed Description

Validate cuts against a known solution.

OsiRowCutDebugger provides a facility for validating cuts against a known solution for a problem. The debugger knows an optimal solution for many of the miplib3 problems. Check the source for activate(const OsiSolverInterface&,const char*) in OsiRowCutDebugger.cpp for the full set of known problems.

A full solution vector can be supplied as a parameter with (activate(const OsiSolverInterface&,const double*,bool)). Only the integer values need to be valid. The default behaviour is to solve an lp relaxation with the integer variables fixed to the specified values and use the optimal solution to fill in the continuous variables in the solution. The debugger can be instructed to preserve the continuous variables (useful when debugging solvers where the linear relaxation doesn't capture all the constraints).

Note that the solution must match the problem held in the solver interface. If you want to use the row cut debugger on a problem after applying presolve transformations, your solution must match the presolved problem. (But see redo-Solution().)

Definition at line 42 of file OsiRowCutDebugger.hpp.

7.28.2 Constructor & Destructor Documentation

7.28.2.1 OsiRowCutDebugger::OsiRowCutDebugger (const OsiSolverInterface & si, const char * model)

Constructor with name of model.

See activate(const OsiSolverInterface&,const char*).

7.28.2.2 OsiRowCutDebugger::OsiRowCutDebugger (const OsiSolverInterface & si, const double * solution, bool enforceOptimality = false)

Constructor with full solution.

See activate(const OsiSolverInterface&,const double*,bool).

7.28.3 Member Function Documentation

7.28.3.1 virtual int OsiRowCutDebugger::validateCuts (const OsiCuts & cs, int first, int last) const [virtual]

Check that the set of cuts does not cut off the solution known to the debugger.

Check if any generated cuts cut off the solution known to the debugger! If so then print offending cuts. Return the number of invalid cuts.

7.28.3.2 virtual bool OsiRowCutDebugger::invalidCut (const OsiRowCut & rowcut) const [virtual]

Check that the cut does not cut off the solution known to the debugger.

Return true if cut is invalid

7.28.3.3 bool OsiRowCutDebugger::onOptimalPath (const OsiSolverInterface & si) const

Returns true if the solution held in the solver is compatible with the known solution.

More specifically, returns true if the known solution satisfies the column bounds held in the solver.

7.28.3.4 bool OsiRowCutDebugger::activate (const OsiSolverInterface & si, const char * model)

Activate a debugger using the name of a problem.

The debugger knows an optimal solution for most of miplib3. Check the source code for the full list. Returns true if the debugger is successfully activated.

7.28.3.5 bool OsiRowCutDebugger::activate (const OsiSolverInterface & si, const double * solution, bool keepContinuous = false)

Activate a debugger using a full solution array.

The solution must have one entry for every variable, but only the entries for integer values are used. By default the debugger will solve an Ip relaxation with the integer variables fixed and fill in values for the continuous variables from this solution. If the debugger should preserve the given values for the continuous variables, set keepContinuous to true.

Returns true if debugger activates successfully.

7.28.3.6 void OsiRowCutDebugger::redoSolution (int numberColumns, const int * originalColumns)

Edit the known solution to reflect column changes.

Given a translation array originalColumns[numberColumns] which can translate current column indices to original

column indices, this method will edit the solution held in the debugger so that it matches the current set of columns.

Useful when the original problem is preprocessed prior to cut generation. The debugger does keep a record of the changes.

7.28.4 Friends And Related Function Documentation

7.28.4.1 void OsiRowCutDebuggerUnitTest (const OsiSolverInterface * siP, const std::string & mpsDir) [friend]

A function that tests the methods in the OsiRowCutDebugger class.

The documentation for this class was generated from the following file:


OsiRowCutDebugger.hpp

7.29 OsiSimpleInteger Class Reference


Define a single integer class.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiSimpleInteger:



Collaboration diagram for OsiSimpleInteger:



Public Member Functions

OsiSimpleInteger ()

Default Constructor.

OsiSimpleInteger (const OsiSolverInterface *solver, int iColumn)

Useful constructor - passed solver index.

• OsiSimpleInteger (int iColumn, double lower, double upper)

Useful constructor - passed solver index and original bounds.

OsiSimpleInteger (const OsiSimpleInteger &)

Copy constructor.

virtual OsiObject * clone () const

Clone

OsiSimpleInteger & operator= (const OsiSimpleInteger &rhs)

Assignment operator.

virtual ∼OsiSimpleInteger ()

Destructor.

• virtual double infeasibility (const OsiBranchingInformation *info, int &whichWay) const

Infeasibility - large is 0.5.

• virtual double feasibleRegion (OsiSolverInterface *solver, const OsiBranchingInformation *info) const Set bounds to fix the variable at the current (integer) value.

• virtual OsiBranchingObject * createBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way) const

Creates a branching object.

void setColumnNumber (int value)

Set solver column number.

virtual int columnNumber () const

Column number if single column object -1 otherwise, so returns >= 0 Used by heuristics.

· double originalLowerBound () const

Original bounds.

virtual void resetBounds (const OsiSolverInterface *solver)

Reset variable bounds to their original values.

virtual void resetSequenceEtc (int numberColumns, const int *originalColumns)

Change column numbers after preprocessing.

virtual double upEstimate () const

Return "up" estimate (default 1.0e-5)

virtual double downEstimate () const

Return "down" estimate (default 1.0e-5)

· virtual bool canHandleShadowPrices () const

Return true if knows how to deal with Pseudo Shadow Prices.

Protected Attributes

· double originalLower_

data Original lower bound

· double originalUpper_

Original upper bound.

int columnNumber

Column number in solver.

7.29.1 Detailed Description

Define a single integer class.

Definition at line 511 of file OsiBranchingObject.hpp.

7.29.2 Member Function Documentation

```
7.29.2.1 virtual double OsiSimpleInteger::feasibleRegion ( OsiSolverInterface * solver, const OsiBranchingInformation * info ) const [virtual]
```

Set bounds to fix the variable at the current (integer) value.

Given an integer value, set the lower and upper bounds to fix the variable. Returns amount it had to move variable.

Implements OsiObject.

```
7.29.2.2 virtual OsiBranchingObject* OsiSimpleInteger::createBranch ( OsiSolverInterface * solver, const OsiBranchingInformation * info, int way ) const [virtual]
```

Creates a branching object.

The preferred direction is set by way, 0 for down, 1 for up.

Reimplemented from OsiObject.

7.29.2.3 virtual void OsiSimpleInteger::resetBounds (const OsiSolverInterface * solver) [virtual]

Reset variable bounds to their original values.

Bounds may be tightened, so it may be good to be able to reset them to their original values.

Reimplemented from OsiObject.

The documentation for this class was generated from the following file:

OsiBranchingObject.hpp

7.30 OsiSolverBranch Class Reference

Solver Branch Class.

#include <OsiSolverBranch.hpp>

Public Member Functions

Add and Get methods

void addBranch (int iColumn, double value)

Add a simple branch (i.e. first sets ub of floor(value), second lb of ceil(value))

 void addBranch (int way, int numberTighterLower, const int *whichLower, const double *newLower, int number-TighterUpper, const int *whichUpper, const double *newUpper)

Add bounds - way =-1 is first , +1 is second.

void addBranch (int way, int numberColumns, const double *oldLower, const double *newLower, const double *newUpper)

Add bounds - way =-1 is first , +1 is second.

void applyBounds (OsiSolverInterface &solver, int way) const

Apply bounds.

• bool feasibleOneWay (const OsiSolverInterface &solver) const

Returns true if current solution satsifies one side of branch.

• const int * starts () const

Starts.

const int * which () const

Which variables.

• const double * bounds () const

Bounds.

Constructors and destructors

• OsiSolverBranch ()

Default Constructor.

OsiSolverBranch (const OsiSolverBranch &rhs)

Copy constructor.

OsiSolverBranch & operator= (const OsiSolverBranch &rhs)

Assignment operator.

∼OsiSolverBranch ()

Destructor.

7.30.1 Detailed Description

Solver Branch Class.

This provides information on a branch as a set of tighter bounds on both ways

Definition at line 18 of file OsiSolverBranch.hpp.

The documentation for this class was generated from the following file:


OsiSolverBranch.hpp

7.31 OsiSolverInterface Class Reference

Abstract Base Class for describing an interface to a solver.

#include <OsiSolverInterface.hpp>

Inheritance diagram for OsiSolverInterface:



Collaboration diagram for OsiSolverInterface:



Classes

· class ApplyCutsReturnCode

Internal class for obtaining status from the applyCuts method.

Public Types

typedef std::vector < std::string > OsiNameVec
 Data type for name vectors.

Public Member Functions

Solve methods

• virtual void initialSolve ()=0

Solve initial LP relaxation.

virtual void resolve ()=0

Resolve an LP relaxation after problem modification.

virtual void branchAndBound ()=0

Invoke solver's built-in enumeration algorithm.

Parameter set/get methods

The set methods return true if the parameter was set to the given value, false otherwise.

When a set method returns false, the original value (if any) should be unchanged. There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the volume algorithm), the parameter is not yet implemented for the solver or simply the value of the parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.

The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.

Note

There is a default implementation of the set/get methods, namely to store/retrieve the given value using an array in the base class. A specific solver implementation can use this feature, for example, to store parameters that should be used later on. Implementors of a solver interface should overload these functions to provide the proper interface to and accurately reflect the capabilities of a specific solver.

The format for hints is slightly different in that a boolean specifies the sense of the hint and an enum specifies the strength of the hint. Hints should be initialised when a solver is instantiated. (See OsiSolverParameters.hpp for defined hint parameters and strength.) When specifying the sense of the hint, a value of true means to work with the hint, false to work against it. For example,

• setHintParam(OsiDoScale,true,OsiHintTry)

is a mild suggestion to the solver to scale the constraint system.

• setHintParam(OsiDoScale, false,OsiForceDo)

tells the solver to disable scaling, or throw an exception if it cannot comply.

As another example, a solver interface could use the value and strength of the <code>OsiDoReducePrint</code> hint to adjust the amount of information printed by the interface and/or solver. The extent to which a solver obeys hints is left to the solver. The value and strength returned by <code>getHintParam</code> will match the most recent call to <code>setHintParam</code>, and will not necessarily reflect the solver's ability to comply with the hint. If the hint strength is <code>OsiForceDo</code>, the solver is required to throw an exception if it cannot perform the specified action.

Note

As with the other set/get methods, there is a default implementation which maintains arrays in the base class for hint sense and strength. The default implementation does not store the otherInformation pointer, and always throws an exception for strength OsiForceDo. Implementors of a solver interface should override these functions to provide the proper interface to and accurately reflect the capabilities of a specific solver.

· virtual bool setIntParam (OsiIntParam key, int value)

Set an integer parameter.

virtual bool setDblParam (OsiDblParam key, double value)

Set a double parameter.

virtual bool setStrParam (OsiStrParam key, const std::string &value)

Set a string parameter.

 virtual bool setHintParam (OsiHintParam key, bool yesNo=true, OsiHintStrength strength=OsiHintTry, void *=N-ULL)

Set a hint parameter.

virtual bool getIntParam (OsiIntParam key, int &value) const

Get an integer parameter.

virtual bool getDblParam (OsiDblParam key, double &value) const

Get a double parameter.

virtual bool getStrParam (OsiStrParam key, std::string &value) const

Get a string parameter.

 virtual bool getHintParam (OsiHintParam key, bool &yesNo, OsiHintStrength &strength, void *&other-Information) const

Get a hint parameter (all information)

virtual bool getHintParam (OsiHintParam key, bool &yesNo, OsiHintStrength &strength) const

Get a hint parameter (sense and strength only)

virtual bool getHintParam (OsiHintParam key, bool &yesNo) const

Get a hint parameter (sense only)

void copyParameters (OsiSolverInterface &rhs)

Copy all parameters in this section from one solver to another.

double getIntegerTolerance () const

Return the integrality tolerance of the underlying solver.

Methods returning info on how the solution process terminated

virtual bool isAbandoned () const =0

Are there numerical difficulties?

virtual bool isProvenOptimal () const =0

Is optimality proven?

virtual bool isProvenPrimalInfeasible () const =0

Is primal infeasibility proven?

virtual bool isProvenDualInfeasible () const =0

Is dual infeasibility proven?

virtual bool isPrimalObjectiveLimitReached () const

Is the given primal objective limit reached?

virtual bool isDualObjectiveLimitReached () const

Is the given dual objective limit reached?

virtual bool isIterationLimitReached () const =0

Iteration limit reached?

Warm start methods

Note that the warm start methods return a generic CoinWarmStart object.

The precise characteristics of this object are solver-dependent. Clients who wish to maintain a maximum degree of solver independence should take care to avoid unnecessary assumptions about the properties of a warm start object.

virtual CoinWarmStart * getEmptyWarmStart () const =0

Get an empty warm start object.

virtual CoinWarmStart * getWarmStart () const =0

Get warm start information.

virtual CoinWarmStart * getPointerToWarmStart (bool &mustDelete)

Get warm start information.

virtual bool setWarmStart (const CoinWarmStart *warmstart)=0

Set warm start information.

Hot start methods

Primarily used in strong branching.

The user can create a hot start object — a snapshot of the optimization process — then reoptimize over and over again, starting from the same point.

Note

- · Between hot started optimizations only bound changes are allowed.
- The copy constructor and assignment operator should NOT copy any hot start information.
- The default implementation simply extracts a warm start object in markHotStart, resets to the warm start object in solveFromHotStart, and deletes the warm start object in unmarkHotStart. Actual solver implementations are encouraged to do better.
- virtual void markHotStart ()

Create a hot start snapshot of the optimization process.

virtual void solveFromHotStart ()

Optimize starting from the hot start snapshot.

• virtual void unmarkHotStart ()

Delete the hot start snapshot.

Problem query methods

Querying a problem that has no data associated with it will result in zeros for the number of rows and columns, and NULL pointers from the methods that return vectors.

Const pointers returned from any data-query method are valid as long as the data is unchanged and the solver is not called.

virtual int getNumCols () const =0

Get the number of columns.

virtual int getNumRows () const =0

Get the number of rows.

virtual int getNumElements () const =0

Get the number of nonzero elements.

• virtual int getNumIntegers () const

Get the number of integer variables.

virtual const double * getColLower () const =0

Get a pointer to an array[getNumCols()] of column lower bounds.

virtual const double * getColUpper () const =0

Get a pointer to an array[getNumCols()] of column upper bounds.

virtual const char * getRowSense () const =0

Get a pointer to an array[getNumRows()] of row constraint senses.

• virtual const double * getRightHandSide () const =0

Get a pointer to an array[getNumRows()] of row right-hand sides.

virtual const double * getRowRange () const =0

Get a pointer to an array[getNumRows()] of row ranges.

virtual const double * getRowLower () const =0

Get a pointer to an array[getNumRows()] of row lower bounds.

virtual const double * getRowUpper () const =0

Get a pointer to an array[getNumRows()] of row upper bounds.

virtual const double * getObjCoefficients () const =0

Get a pointer to an array[getNumCols()] of objective function coefficients.

virtual double getObjSense () const =0

Get the objective function sense.

virtual bool isContinuous (int collndex) const =0

Return true if the variable is continuous.

virtual bool isBinary (int collndex) const

Return true if the variable is binary.

virtual bool isInteger (int colIndex) const

Return true if the variable is integer.

virtual bool isIntegerNonBinary (int colIndex) const

Return true if the variable is general integer.

virtual bool isFreeBinary (int colIndex) const

Return true if the variable is binary and not fixed.

const char * columnType (bool refresh=false) const

Return an array[getNumCols()] of column types.

virtual const char * getColType (bool refresh=false) const

Return an array[getNumCols()] of column types.

virtual const CoinPackedMatrix * getMatrixByRow () const =0

Get a pointer to a row-wise copy of the matrix.

virtual const CoinPackedMatrix * getMatrixByCol () const =0

Get a pointer to a column-wise copy of the matrix.

virtual CoinPackedMatrix * getMutableMatrixByRow () const

Get a pointer to a mutable row-wise copy of the matrix.

virtual CoinPackedMatrix * getMutableMatrixByCol () const

Get a pointer to a mutable column-wise copy of the matrix.

• virtual double getInfinity () const =0

Get the solver's value for infinity.

Solution query methods

virtual const double * getColSolution () const =0

Get a pointer to an array[getNumCols()] of primal variable values.

virtual const double * getStrictColSolution ()

Get a pointer to an array[getNumCols()] of primal variable values guaranteed to be between the column lower and upper bounds.

virtual const double * getRowPrice () const =0

Get pointer to array[getNumRows()] of dual variable values.

virtual const double * getReducedCost () const =0

Get a pointer to an array[getNumCols()] of reduced costs.

virtual const double * getRowActivity () const =0

Get a pointer to array[getNumRows()] of row activity levels.

• virtual double getObjValue () const =0

Get the objective function value.

virtual int getIterationCount () const =0

Get the number of iterations it took to solve the problem (whatever 'iteration' means to the solver).

virtual std::vector< double * > getDualRays (int maxNumRays, bool fullRay=false) const =0

Get as many dual rays as the solver can provide.

virtual std::vector< double * > getPrimalRays (int maxNumRays) const =0

Get as many primal rays as the solver can provide.

virtual OsiVectorInt getFractionalIndices (const double etol=1.e-05) const

Get vector of indices of primal variables which are integer variables but have fractional values in the current solution.

Methods to modify the objective, bounds, and solution

For functions which take a set of indices as parameters (setObjCoeffSet(), setColSetBounds(), set-RowSetBounds(), setRowSetTypes()), the parameters follow the C++ STL iterator convention: index-First points to the first index in the set, and indexLast points to a position one past the last index in the set.

virtual void setObjCoeff (int elementIndex, double elementValue)=0

Set an objective function coefficient.

virtual void setObjCoeffSet (const int *indexFirst, const int *indexLast, const double *coeffList)

Set a set of objective function coefficients.

virtual void setObjective (const double *array)

Set the objective coefficients for all columns.

virtual void setObjSense (double s)=0

Set the objective function sense.

virtual void setColLower (int elementIndex, double elementValue)=0

Set a single column lower bound.

virtual void setColLower (const double *array)

Set the lower bounds for all columns.

virtual void setColUpper (int elementIndex, double elementValue)=0

Set a single column upper bound.

virtual void setColUpper (const double *array)

Set the upper bounds for all columns.

virtual void setColBounds (int elementIndex, double lower, double upper)

Set a single column lower and upper bound.

virtual void setColSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the upper and lower bounds of a set of columns.

virtual void setRowLower (int elementIndex, double elementValue)=0

Set a single row lower bound.

virtual void setRowUpper (int elementIndex, double elementValue)=0

Set a single row upper bound.

• virtual void setRowBounds (int elementIndex, double lower, double upper)

Set a single row lower and upper bound.

virtual void setRowSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a set of rows.

• virtual void setRowType (int index, char sense, double rightHandSide, double range)=0

Set the type of a single row.

 virtual void setRowSetTypes (const int *indexFirst, const int *indexLast, const char *senseList, const double *rhsList, const double *rangeList)

Set the type of a set of rows.

• virtual void setColSolution (const double *colsol)=0

Set the primal solution variable values.

virtual void setRowPrice (const double *rowprice)=0

Set dual solution variable values.

virtual int reducedCostFix (double gap, bool justInteger=true)

Fix variables at bound based on reduced cost.

Methods to set variable type

virtual void setContinuous (int index)=0

Set the index-th variable to be a continuous variable.

virtual void setInteger (int index)=0

Set the index-th variable to be an integer variable.

virtual void setContinuous (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be continuous variables.

virtual void setInteger (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be integer variables.

Methods for row and column names

Osi defines three name management disciplines: 'auto names' (0), 'lazy names' (1), and 'full names' (2).

See the description of #OsiNameDiscipline for details. Changing the name discipline (via setIntParam()) will not automatically add or remove name information, but setting the discipline to auto will make existing information inaccessible until the discipline is reset to lazy or full.

By definition, a row index of getNumRows() (i.e., one larger than the largest valid row index) refers to the objective function.

OSI users and implementors: While the OSI base class can define an interface and provide rudimentary support, use of names really depends on support by the OsiXXX class to ensure that names are managed correctly. If an OsiXXX class does not support names, it should return false for calls to getIntParam() or setIntParam() that reference OsiNameDiscipline.

• virtual std::string dfltRowColName (char rc, int ndx, unsigned digits=7) const

Generate a standard name of the form Rnnnnnnn or Cnnnnnnn.

virtual std::string getObjName (unsigned maxLen=std::numeric_limits< unsigned >::max()) const

Return the name of the objective function.

virtual void setObjName (std::string name)

Set the name of the objective function.

virtual std::string getRowName (int rowIndex, unsigned maxLen=std::numeric_limits< unsigned >::max())

Return the name of the row.

virtual const OsiNameVec & getRowNames ()

Return a pointer to a vector of row names.

virtual void setRowName (int ndx, std::string name)

Set a row name

virtual void setRowNames (OsiNameVec &srcNames, int srcStart, int len, int tgtStart)

Set multiple row names.

virtual void deleteRowNames (int tgtStart, int len)

Delete len row names starting at index tgtStart.

virtual std::string getColName (int colIndex, unsigned maxLen=std::numeric_limits< unsigned >::max())
const

Return the name of the column.

virtual const OsiNameVec & getColNames ()

Return a pointer to a vector of column names.

virtual void setColName (int ndx, std::string name)

Set a column name.

virtual void setColNames (OsiNameVec &srcNames, int srcStart, int len, int tgtStart)

Set multiple column names.

virtual void deleteColNames (int tgtStart, int len)

Delete len column names starting at index tgtStart.

void setRowColNames (const CoinMpsIO &mps)

Set row and column names from a CoinMpsIO object.

void setRowColNames (CoinModel &mod)

Set row and column names from a CoinModel object.

void setRowColNames (CoinLpIO &mod)

Set row and column names from a CoinLplO object.

Methods to modify the constraint system.

Note that new columns are added as continuous variables.

virtual void addCol (const CoinPackedVectorBase &vec, const double collb, const double colub, const double obj)=0

Add a column (primal variable) to the problem.

virtual void addCol (const CoinPackedVectorBase &vec, const double collb, const double colub, const double obj, std::string name)

Add a named column (primal variable) to the problem.

 virtual void addCol (int numberElements, const int *rows, const double *elements, const double collb, const double colub, const double obj)

Add a column (primal variable) to the problem.

 virtual void addCol (int numberElements, const int *rows, const double *elements, const double collb, const double colub, const double obj, std::string name)

Add a named column (primal variable) to the problem.

virtual void addCols (const int numcols, const CoinPackedVectorBase *const *cols, const double *collb, const double *collb

Add a set of columns (primal variables) to the problem.

virtual void addCols (const int numcols, const int *columnStarts, const int *rows, const double *elements, const double *collb, const double *c

Add a set of columns (primal variables) to the problem.

void addCols (const CoinBuild &buildObject)

Add columns using a CoinBuild object.

int addCols (CoinModel &modelObject)

Add columns from a model object.

virtual void deleteCols (const int num, const int *colIndices)=0

Remove a set of columns (primal variables) from the problem.

virtual void addRow (const CoinPackedVectorBase &vec, const double rowlb, const double rowlb)=0
 Add a row (constraint) to the problem.

virtual void addRow (const CoinPackedVectorBase &vec, const double rowlb, const double rowlb, std::string name)

Add a named row (constraint) to the problem.

 virtual void addRow (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng)=0

Add a row (constraint) to the problem.

 virtual void addRow (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng, std::string name)

Add a named row (constraint) to the problem.

virtual void addRow (int numberElements, const int *columns, const double *element, const double rowlb, const double rowlb)

Add a row (constraint) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const double *rowlb, const double *rowub)

Add a set of rows (constraints) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const char *rowsen, const double *rowrns, const double *rowrns)

Add a set of rows (constraints) to the problem.

 virtual void addRows (const int numrows, const int *rowStarts, const int *columns, const double *element, const double *rowlb, const double *rowlb)

Add a set of rows (constraints) to the problem.

void addRows (const CoinBuild &buildObject)

Add rows using a CoinBuild object.

int addRows (CoinModel &modelObject)

Add rows from a CoinModel object.

virtual void deleteRows (const int num, const int *rowIndices)=0

Delete a set of rows (constraints) from the problem.

virtual void replaceMatrixOptional (const CoinPackedMatrix &)

Replace the constraint matrix.

virtual void replaceMatrix (const CoinPackedMatrix &)

Replace the constraint matrix.

virtual void saveBaseModel ()

Save a copy of the base model.

virtual void restoreBaseModel (int numberRows)

Reduce the constraint system to the specified number of constraints.

virtual ApplyCutsReturnCode applyCuts (const OsiCuts &cs, double effectivenessLb=0.0)

Apply a collection of cuts.

virtual void applyRowCuts (int numberCuts, const OsiRowCut *cuts)

Apply a collection of row cuts which are all effective.

virtual void applyRowCuts (int numberCuts, const OsiRowCut **cuts)

Apply a collection of row cuts which are all effective.

void deleteBranchingInfo (int numberDeleted, const int *which)

Deletes branching information before columns deleted.

Methods for problem input and output

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *collb, const double *rowub)=0

Load in a problem by copying the arguments.

virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&colub, double *&colub, double *&rowub)=0

Load in a problem by assuming ownership of the arguments.

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, c

Load in a problem by copying the arguments.

 virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, char *&rowsen, double *&rowrhs, double *&rowrng)=0

Load in a problem by assuming ownership of the arguments.

• virtual void loadProblem (const int numcols, const int numrows, const CoinBigIndex *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowlb, const double *rowlb)=0

Load in a problem by copying the arguments.

• virtual void loadProblem (const int numcols, const int numrows, const CoinBigIndex *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowrhs, const double *rowrng)=0

Load in a problem by copying the arguments.

virtual int loadFromCoinModel (CoinModel &modelObject, bool keepSolution=false)

Load a model from a CoinModel object.

virtual int readMps (const char *filename, const char *extension="mps")

Read a problem in MPS format from the given filename.

virtual int readMps (const char *filename, const char *extension, int &numberSets, CoinSet **&sets)

Read a problem in MPS format from the given full filename.

• virtual int readGMPL (const char *filename, const char *dataname=NULL)

Read a problem in GMPL format from the given filenames.

- virtual void writeMps (const char *filename, const char *extension="mps", double objSense=0.0) const =0

 Write the problem in MPS format to the specified file.
- int writeMpsNative (const char *filename, const char **rowNames, const char **columnNames, int format-Type=0, int numberAcross=2, double objSense=0.0, int numberSOS=0, const **CoinSet** *setInfo=NULL) const Write the problem in MPS format to the specified file with more control over the output.

• virtual void writeLp (const char *filename, const char *extension="lp", double epsilon=1e-5, int number-Across=10, int decimals=5, double objSense=0.0, bool useRowNames=true) const

Write the problem into an Lp file of the given filename with the specified extension.

 virtual void writeLp (FILE *fp, double epsilon=1e-5, int numberAcross=10, int decimals=5, double objSense=0.-0, bool useRowNames=true) const

Write the problem into the file pointed to by the parameter fp.

int writeLpNative (const char *filename, char const *const *const rowNames, char const *const *const column-Names, const double epsilon=1.0e-5, const int numberAcross=10, const int decimals=5, const double obj-Sense=0.0, const bool useRowNames=true) const

Write the problem into an Lp file.

int writeLpNative (FILE *fp, char const *const *const rowNames, char const *const *const columnNames, const double epsilon=1.0e-5, const int numberAcross=10, const int decimals=5, const double objSense=0.0, const bool useRowNames=true) const

Write the problem into the file pointed to by the parameter fp.

virtual int readLp (const char *filename, const double epsilon=1e-5)

Read file in LP format from file with name filename.

int readLp (FILE *fp, const double epsilon=1e-5)

Read file in LP format from the file pointed to by fp.

Miscellaneous

int differentModel (OsiSolverInterface & other, bool ignoreNames=true)

Check two models against each other.

Setting/Accessing application data

void setApplicationData (void *appData)

Set application data.

void setAuxiliaryInfo (OsiAuxInfo *auxiliaryInfo)

Create a clone of an Auxiliary Information object.

void * getApplicationData () const

Get application data.

OsiAuxInfo * getAuxiliaryInfo () const

Get pointer to auxiliary info object.

Message handling

See the COIN library documentation for additional information about COIN message facilities.

virtual void passInMessageHandler (CoinMessageHandler *handler)

Pass in a message handler.

void newLanguage (CoinMessages::Language language)

Set language.

- void setLanguage (CoinMessages::Language language)
- CoinMessageHandler * messageHandler () const

Return a pointer to the current message handler.

CoinMessages messages ()

Return the current set of messages.

CoinMessages * messagesPointer ()

Return a pointer to the current set of messages.

· bool defaultHandler () const

Return true if default handler.

Methods for dealing with discontinuities other than integers.

Osi should be able to know about SOS and other types.

This is an optional section where such information can be stored.

void findIntegers (bool justCount)

Identify integer variables and create corresponding objects.

virtual int findIntegersAndSOS (bool justCount)

Identify integer variables and SOS and create corresponding objects.

int numberObjects () const

Get the number of objects.

void setNumberObjects (int number)

Set the number of objects.

OsiObject ** objects () const

Get the array of objects.

const OsiObject * object (int which) const

Get the specified object.

• OsiObject * modifiableObject (int which) const

Get the specified object.

void deleteObjects ()

Delete all object information.

void addObjects (int numberObjects, OsiObject **objects)

Add in object information.

• double forceFeasible ()

Use current solution to set bounds so current integer feasible solution will stay feasible.

Methods related to testing generated cuts

See the documentation for OsiRowCutDebugger for additional details.

virtual void activateRowCutDebugger (const char *modelName)

Activate the row cut debugger.

virtual void activateRowCutDebugger (const double *solution, bool enforceOptimality=true)

Activate the row cut debugger using a full solution array.

const OsiRowCutDebugger * getRowCutDebugger () const

Get the row cut debugger provided the solution known to the debugger is within the feasible region held in the solver.

OsiRowCutDebugger * getRowCutDebuggerAlways () const

Get the row cut debugger object.

OsiSimplexInterface

Simplex Interface

Methods for an advanced interface to a simplex solver. The interface comprises two groups of methods. Group 1 contains methods for tableau access. Group 2 contains methods for dictating individual simplex pivots.

virtual int canDoSimplexInterface () const

Return the simplex implementation level.

OsiSimplex Group 1

Tableau access methods.

This group of methods provides access to rows and columns of the basis inverse and to rows and columns of the tableau.

· virtual void enableFactorization () const

Prepare the solver for the use of tableau access methods.

· virtual void disableFactorization () const

Undo the effects of enableFactorization.

virtual bool basisIsAvailable () const

Check if an optimal basis is available.

bool optimalBasisIsAvailable () const

Synonym for basisIsAvailable.

virtual void getBasisStatus (int *cstat, int *rstat) const

Retrieve status information for column and row variables.

virtual int setBasisStatus (const int *cstat, const int *rstat)

Set the status of column and row variables and update the basis factorization and solution.

• virtual void getReducedGradient (double *columnReducedCosts, double *duals, const double *c) const

Calculate duals and reduced costs for the given objective coefficients.

virtual void getBInvARow (int row, double *z, double *slack=NULL) const

Get a row of the tableau.

virtual void getBlnvRow (int row, double *z) const

Get a row of the basis inverse.

virtual void getBInvACol (int col, double *vec) const

Get a column of the tableau.

• virtual void getBlnvCol (int col, double *vec) const

Get a column of the basis inverse.

virtual void getBasics (int *index) const

Get indices of basic variables.

OsiSimplex Group 2

Pivoting methods

This group of methods provides for control of individual pivots by a simplex solver.

virtual void enableSimplexInterface (bool doingPrimal)

Enables normal operation of subsequent functions.

virtual void disableSimplexInterface ()

Undo whatever setting changes the above method had to make.

virtual int pivot (int colln, int colOut, int outStatus)

Perform a pivot by substituting a colln for colOut in the basis.

- virtual int primalPivotResult (int colln, int sign, int &colOut, int &outStatus, double &t, CoinPackedVector *dx)
 Obtain a result of the primal pivot Outputs: colOut leaving column, outStatus its status, t step size, and, if dx!=NULL, *dx primal ray direction.
- virtual int dualPivotResult (int &colln, int &sign, int colOut, int outStatus, double &t, CoinPackedVector *dx)
 Obtain a result of the dual pivot (similar to the previous method) Differences: entering variable and a sign of its change are now the outputs, the leaving variable and its statuts the inputs If dx!=NULL, then *dx contains dual ray Return code: same.

Constructors and destructors

OsiSolverInterface ()

Default Constructor.

virtual OsiSolverInterface * clone (bool copyData=true) const =0

Clone.

OsiSolverInterface (const OsiSolverInterface &)

Copy constructor.

OsiSolverInterface & operator= (const OsiSolverInterface &rhs)

Assignment operator.

virtual ∼OsiSolverInterface ()

Destructor.

virtual void reset ()

Reset the solver interface.

Protected Member Functions

Protected methods

virtual void applyRowCut (const OsiRowCut &rc)=0

Apply a row cut (append to the constraint matrix).

virtual void applyColCut (const OsiColCut &cc)=0

Apply a column cut (adjust the bounds of one or more variables).

 void convertBoundToSense (const double lower, const double upper, char &sense, double &right, double &range) const

A quick inlined function to convert from the lb/ub style of constraint definition to the sense/rhs/range style.

 void convertSenseToBound (const char sense, const double right, const double range, double &lower, double &upper) const

A quick inlined function to convert from the sense/rhs/range style of constraint definition to the lb/ub style.

· template<class T >

T forceIntoRange (const T value, const T lower, const T upper) const

A quick inlined function to force a value to be between a minimum and a maximum value.

void setInitialData ()

Set OsiSolverInterface object state for default constructor.

Protected Attributes

Protected member data

OsiRowCutDebugger * rowCutDebugger_

Pointer to row cut debugger object.

CoinMessageHandler * handler_

Message handler.

· bool defaultHandler_

Flag to say if the currrent handler is the default handler.

CoinMessages messages

Messages.

int numberIntegers_

Number of integers.

· int numberObjects_

Total number of objects.

OsiObject ** object

Integer and ... information (integer info normally at beginning)

char * columnType_

Column type 0 - continuous 1 - binary (may get fixed later) 2 - general integer (may get fixed later)

Friends

 void OsiSolverInterfaceCommonUnitTest (const OsiSolverInterface *emptySi, const std::string &mpsDir, const std::string &netlibDir)

A function that tests the methods in the OsiSolverInterface class.

 void OsiSolverInterfaceMpsUnitTest (const std::vector< OsiSolverInterface * > &vecSiP, const std::string &mps-Dir)

A function that tests that a lot of problems given in MPS files (mostly the NETLIB problems) solve properly with all the specified solvers.

7.31.1 Detailed Description

Abstract Base Class for describing an interface to a solver.

Many OsiSolverInterface query methods return a const pointer to the requested read-only data. If the model data is changed or the solver is called, these pointers may no longer be valid and should be refreshed by invoking the member function to obtain an updated copy of the pointer. For example:

```
OsiSolverInterface solverInterfacePtr;
const double * ruBnds = solverInterfacePtr->getRowUpper();
solverInterfacePtr->applyCuts(someSetOfCuts);
// ruBnds is no longer a valid pointer and must be refreshed
ruBnds = solverInterfacePtr->getRowUpper();
```

Querying a problem that has no data associated with it will result in zeros for the number of rows and columns, and NULL pointers from the methods that return vectors.

Definition at line 62 of file OsiSolverInterface.hpp.

7.31.2 Member Typedef Documentation

7.31.2.1 typedef std::vector<std::string> OsiSolverInterface::OsiNameVec

Data type for name vectors.

Definition at line 888 of file OsiSolverInterface.hpp.

7.31.3 Member Function Documentation

```
7.31.3.1 virtual void OsiSolverInterface::resolve() [pure virtual]
```

Resolve an LP relaxation after problem modification.

Note the 're-' in 'resolve'. initialSolve() should be used to solve the problem for the first time.

Implemented in OsiSpxSolverInterface, OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiGrbSolverInterface, OsiGrb

```
7.31.3.2 virtual bool OsiSolverInterface::setHintParam ( OsiHintParam key, bool yesNo = true, OsiHintStrength strength = OsiHintTry, void * = NULL ) [inline], [virtual]
```

Set a hint parameter.

The otherInformation parameter can be used to pass in an arbitrary block of information which is interpreted by the OSI and the underlying solver. Users are cautioned that this hook is solver-specific.

Implementors: The default implementation completely ignores otherInformation and always throws an exception for OsiForceDo. This is almost certainly not the behaviour you want; you really should override this method.

Reimplemented in OsiGlpkSolverInterface, and OsiGrbSolverInterface.

Definition at line 294 of file OsiSolverInterface.hpp.

7.31.3.3 virtual bool OsiSolverInterface::getHintParam (OsiHintParam key, bool & yesNo, OsiHintStrength & strength, void *& otherInformation) const [inline], [virtual]

Get a hint parameter (all information)

Return all available information for the hint: sense, strength, and any extra information associated with the hint.

Implementors: The default implementation will always set otherInformation to NULL. This is almost certainly not the behaviour you want; you really should override this method.

Reimplemented in OsiGrbSolverInterface.

Definition at line 333 of file OsiSolverInterface.hpp.

7.31.3.4 virtual bool OsiSolverInterface::getHintParam (OsiHintParam key, bool & yesNo, OsiHintStrength & strength) const [inline], [virtual]

Get a hint parameter (sense and strength only)

Return only the sense and strength of the hint.

Reimplemented in OsiGrbSolverInterface.

Definition at line 347 of file OsiSolverInterface.hpp.

7.31.3.5 virtual bool OsiSolverInterface::getHintParam (OsiHintParam key, bool & yesNo) const [inline], [virtual]

Get a hint parameter (sense only)

Return only the sense (true/false) of the hint.

Reimplemented in OsiGrbSolverInterface.

Definition at line 359 of file OsiSolverInterface.hpp.

7.31.3.6 void OsiSolverInterface::copyParameters (OsiSolverInterface & rhs)

Copy all parameters in this section from one solver to another.

Note that the current implementation also copies the appData block, message handler, and rowCutDebugger. Arguably these should have independent copy methods.

7.31.3.7 double OsiSolverInterface::getIntegerTolerance() const [inline]

Return the integrality tolerance of the underlying solver.

We should be able to get an integrality tolerance, but until that time just use the primal tolerance

Definition at line 386 of file OsiSolverInterface.hpp.

7.31.3.8 virtual CoinWarmStart* OsiSolverInterface::getEmptyWarmStart() const [pure virtual]

Get an empty warm start object.

This routine returns an empty warm start object. Its purpose is to provide a way for a client to acquire a warm start object of the appropriate type for the solver, which can then be resized and modified as desired.

Implemented in OsiGlpkSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, and OsiXprSolverInterface.

7.31.3.9 virtual CoinWarmStart* OsiSolverInterface::getWarmStart() const [pure virtual]

Get warm start information.

Return warm start information for the current state of the solver interface. If there is no valid warm start information, an empty warm start object wil be returned.

Implemented in OsiGrbSolverInterface, OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiSpx

7.31.3.10 virtual CoinWarmStart* OsiSolverInterface::getPointerToWarmStart(bool & mustDelete) [virtual]

Get warm start information.

Return warm start information for the current state of the solver interface. If there is no valid warm start information, an empty warm start object will be returned. This does not necessarily create an object - may just point to one. must Delete set true if user should delete returned object.

7.31.3.11 virtual bool OsiSolverInterface::setWarmStart (const CoinWarmStart * warmstart) [pure virtual]

Set warm start information.

Return true or false depending on whether the warm start information was accepted or not. By definition, a call to setWarmStart with a null parameter should cause the solver interface to refresh its warm start information from the underlying solver.

Implemented in OsiGrbSolverInterface, OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiSpx

7.31.3.12 virtual const char* OsiSolverInterface::getRowSense() const [pure virtual]

Get a pointer to an array[getNumRows()] of row constraint senses.

- 'L': <= constraint
- 'E': = constraint
- 'G': >= constraint
- · 'R': ranged constraint
- · 'N': free constraint

Implemented in OsiGrbSolverInterface, OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, and OsiXprSolverInterface.

```
7.31.3.13 virtual const double* OsiSolverInterface::getRightHandSide( ) const [pure virtual]
```

Get a pointer to an array[getNumRows()] of row right-hand sides.

- if getRowSense()[i] == 'L' then getRightHandSide()[i] == getRowUpper()[i]
- if getRowSense()[i] == 'G' then getRightHandSide()[i] == getRowLower()[i]
- if getRowSense()[i] == 'R' then getRightHandSide()[i] == getRowUpper()[i]
- if getRowSense()[i] == 'N' then getRightHandSide()[i] == 0.0

Implemented in OsiGrbSolverInterface, OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, and OsiXprSolverInterface.

```
7.31.3.14 virtual const double* OsiSolverInterface::getRowRange( ) const [pure virtual]
```

Get a pointer to an array[getNumRows()] of row ranges.

- if getRowSense()[i] == 'R' then getRowRange()[i] == getRowUpper()[i] getRowLower()[i]
- if getRowSense()[i] != 'R' then getRowRange()[i] is 0.0

Implemented in OsiGrbSolverInterface, OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, and OsiXprSolverInterface.

7.31.3.15 virtual double OsiSolverInterface::getObjSense() const [pure virtual]

Get the objective function sense.

- 1 for minimisation (default)
- -1 for maximisation

Implemented in OsiGrbSolverInterface, OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, and OsiXprSolverInterface.

7.31.3.16 virtual bool OsiSolverInterface::isInteger (int colIndex) const [virtual]

Return true if the variable is integer.

This method returns true if the variable is binary or general integer.

7.31.3.17 const char* OsiSolverInterface::columnType (bool refresh = false) const [inline]

Return an array[getNumCols()] of column types.

Deprecated See getColType

Definition at line 593 of file OsiSolverInterface.hpp.

7.31.3.18 virtual const char* OsiSolverInterface::getColType (bool refresh = false) const [virtual]

Return an array[getNumCols()] of column types.

- 0 continuous
- 1 binary
- · 2 general integer

If refresh is true, the classification of integer variables as binary or general integer will be reevaluated. If the current bounds are [0,1], or if the variable is fixed at 0 or 1, it will be classified as binary, otherwise it will be classified as general integer.

7.31.3.19 virtual CoinPackedMatrix* OsiSolverInterface::getMutableMatrixByRow()const [inline], [virtual]

Get a pointer to a mutable row-wise copy of the matrix.

Returns NULL if the request is not meaningful (i.e., the OSI will not recognise any modifications to the matrix).

Definition at line 620 of file OsiSolverInterface.hpp.

7.31.3.20 virtual CoinPackedMatrix* OsiSolverInterface::getMutableMatrixByCol() const [inline], [virtual]

Get a pointer to a mutable column-wise copy of the matrix.

Returns NULL if the request is not meaningful (i.e., the OSI will not recognise any modifications to the matrix).

Definition at line 627 of file OsiSolverInterface.hpp.

7.31.3.21 virtual const double* OsiSolverInterface::getRowActivity() const [pure virtual]

Get a pointer to array[getNumRows()] of row activity levels.

The row activity for a row is the left-hand side evaluated at the current solution.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiSpx

7.31.3.22 virtual std::vector<double*> OsiSolverInterface::getDualRays (int maxNumRays, bool fullRay = false) const [pure virtual]

Get as many dual rays as the solver can provide.

In case of proven primal infeasibility there should (with high probability) be at least one.

The first getNumRows() ray components will always be associated with the row duals (as returned by getRowPrice()). If fullRay is true, the final getNumCols() entries will correspond to the ray components associated with the nonbasic variables. If the full ray is requested and the method cannot provide it, it will throw an exception.

Note

Implementors of solver interfaces note that the double pointers in the vector should point to arrays of length get-NumRows() (fullRay = false) or (getNumRows()+getNumCols()) (fullRay = true) and they should be allocated with new[].

Clients of solver interfaces note that it is the client's responsibility to free the double pointers in the vector using delete[]. Clients are reminded that a problem can be dual and primal infeasible.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiGrb

7.31.3.23 virtual std::vector<double*> OsiSolverInterface::getPrimalRays(int maxNumRays) const [pure virtual]

Get as many primal rays as the solver can provide.

In case of proven dual infeasibility there should (with high probability) be at least one.

Note

Implementors of solver interfaces note that the double pointers in the vector should point to arrays of length get-NumCols() and they should be allocated with new[].

Clients of solver interfaces note that it is the client's responsibility to free the double pointers in the vector using delete[]. Clients are reminded that a problem can be dual and primal infeasible.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, and OsiXprSolverInterface.

7.31.3.24 virtual OsiVectorInt OsiSolverInterface::getFractionalIndices (const double etol = 1.e-05) const [virtual]

Get vector of indices of primal variables which are integer variables but have fractional values in the current solution.

7.31.3.25 virtual void OsiSolverInterface::setObjective (const double * array) [virtual]

Set the objective coefficients for all columns.

array [getNumCols()] is an array of values for the objective. This defaults to a series of set operations and is here for speed.

7.31.3.26 virtual void OsiSolverInterface::setObjSense (double s) [pure virtual]

Set the objective function sense.

Use 1 for minimisation (default), -1 for maximisation.

Note

Implementors note that objective function sense is a parameter of the OSI, not a property of the problem. Objective sense can be set prior to problem load and should not be affected by loading a new problem.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiGrb

7.31.3.27 virtual void OsiSolverInterface::setColLower (int elementIndex, double elementValue) [pure virtual]

Set a single column lower bound.

Use -getInfinity() for -infinity.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiGrb

7.31.3.28 virtual void OsiSolverInterface::setColLower (const double * array) [virtual]

Set the lower bounds for all columns.

array [getNumCols()] is an array of values for the lower bounds. This defaults to a series of set operations and is here for speed.

7.31.3.29 virtual void OsiSolverInterface::setColUpper (int elementIndex, double elementValue) [pure virtual]

Set a single column upper bound.

Use getInfinity() for infinity.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiGrb

7.31.3.30 virtual void OsiSolverInterface::setColUpper (const double * array) [virtual]

Set the upper bounds for all columns.

array [getNumCols()] is an array of values for the upper bounds. This defaults to a series of set operations and is here for speed.

7.31.3.31 virtual void OsiSolverInterface::setColBounds (int *elementIndex*, double *lower*, double *upper*) [inline], [virtual]

Set a single column lower and upper bound.

The default implementation just invokes setColLower() and setColUpper()

Reimplemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGpxSolverInterface, OsiG

Definition at line 778 of file OsiSolverInterface.hpp.

7.31.3.32 virtual void OsiSolverInterface::setColSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the upper and lower bounds of a set of columns.

The default implementation just invokes setColBounds() over and over again. For each column, boundList must contain both a lower and upper bound, in that order.

Reimplemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, and OsiXprSolverInterface.

7.31.3.33 virtual void OsiSolverInterface::setRowLower(int elementIndex, double elementValue) [pure virtual]

Set a single row lower bound.

Use -getInfinity() for -infinity.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiGrb

7.31.3.34 virtual void OsiSolverInterface::setRowUpper (int elementIndex, double elementValue) [pure virtual]

Set a single row upper bound.

Use getInfinity() for infinity.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiGrb

7.31.3.35 virtual void OsiSolverInterface::setRowBounds (int elementIndex, double lower, double upper) [inline], [virtual]

Set a single row lower and upper bound.

The default implementation just invokes setRowLower() and setRowUpper()

Reimplemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGpsSolverInterface, OsiG

Definition at line 805 of file OsiSolverInterface.hpp.

7.31.3.36 virtual void OsiSolverInterface::setRowSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a set of rows.

The default implementation just invokes setRowBounds() over and over again. For each row, boundList must contain both a lower and upper bound, in that order.

Reimplemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, and OsiXprSolverInterface.

7.31.3.37 virtual void OsiSolverInterface::setRowSetTypes (const int * indexFirst, const int * indexLast, const char * senseList, const double * rhsList, const double * rangeList) [virtual]

Set the type of a set of rows.

The default implementation just invokes setRowType() over and over again.

Reimplemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, and OsiXprSolverInterface.

7.31.3.38 virtual void OsiSolverInterface::setColSolution (const double * colsol) [pure virtual]

Set the primal solution variable values.

colsol[getNumCols()] is an array of values for the primal variables. These values are copied to memory owned by the solver interface object or the solver. They will be returned as the result of getColSolution() until changed by another call to setColSolution() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiSpx

7.31.3.39 virtual void OsiSolverInterface::setRowPrice (const double * rowprice) [pure virtual]

Set dual solution variable values.

rowprice[getNumRows()] is an array of values for the dual variables. These values are copied to memory owned by the solver interface object or the solver. They will be returned as the result of getRowPrice() until changed by another call to setRowPrice() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiGrb

7.31.3.40 virtual int OsiSolverInterface::reducedCostFix (double gap, bool justInteger = true) [virtual]

Fix variables at bound based on reduced cost.

For variables currently at bound, fix the variable at bound if the reduced cost exceeds the gap. Return the number of variables fixed.

If justInteger is set to false, the routine will also fix continuous variables, but the test still assumes a delta of 1.0.

7.31.3.41 virtual std::string OsiSolverInterface::dfltRowColName (char rc, int ndx, unsigned digits = 7) const [virtual]

Generate a standard name of the form Rnnnnnnn or Cnnnnnnn.

Set rc to 'r' for a row name, 'c' for a column name. The 'nnnnnnn' part is generated from ndx and will contain 7 digits by default, padded with zeros if necessary. As a special case, ndx = getNumRows() is interpreted as a request for the name of the objective function. OBJECTIVE is returned, truncated to digits+1 characters to match the row and column names.

```
7.31.3.42 virtual std::string OsiSolverInterface::getRowName ( int rowIndex, unsigned maxLen = std::numeric_limits< unsigned >::max() ) const [virtual]
```

Return the name of the row.

The routine will *always* return some name, regardless of the name discipline or the level of support by an OsiXXX derived class. Use maxLen to limit the length.

```
7.31.3.43 virtual const OsiNameVec& OsiSolverInterface::getRowNames() [virtual]
```

Return a pointer to a vector of row names.

If the name discipline (#OsiNameDiscipline) is auto, the return value will be a vector of length zero. If the name discipline is lazy, the vector will contain only names supplied by the client and will be no larger than needed to hold those names; entries not supplied will be null strings. In particular, the objective name is *not* included in the vector for lazy names. If the name discipline is full, the vector will have getNumRows() names, either supplied or generated, plus one additional entry for the objective name.

```
7.31.3.44 virtual void OsiSolverInterface::setRowName (int ndx, std::string name) [virtual]
```

Set a row name.

Quietly does nothing if the name discipline (#OsiNameDiscipline) is auto. Quietly fails if the row index is invalid.

Reimplemented in OsiGlpkSolverInterface, and OsiGrbSolverInterface.

```
7.31.3.45 virtual void OsiSolverInterface::setRowNames ( OsiNameVec & srcNames, int srcStart, int len, int tgtStart )

[virtual]
```

Set multiple row names.

The run of len entries starting at srcNames[srcStart] are installed as row names starting at row index tgtStart. The base class implementation makes repeated calls to setRowName.

7.31.3.46 virtual void OsiSolverInterface::deleteRowNames (int tgtStart, int len) [virtual]

Delete len row names starting at index tgtStart.

The specified row names are removed and the remaining row names are copied down to close the gap.

```
7.31.3.47 virtual std::string OsiSolverInterface::getColName ( int colIndex, unsigned maxLen = std::numeric_limits< unsigned >::max() ) const [virtual]
```

Return the name of the column.

The routine will *always* return some name, regardless of the name discipline or the level of support by an OsiXXX derived class. Use maxLen to limit the length.

```
7.31.3.48 virtual const OsiNameVec& OsiSolverInterface::getColNames() [virtual]
```

Return a pointer to a vector of column names.

If the name discipline (#OsiNameDiscipline) is auto, the return value will be a vector of length zero. If the name discipline is lazy, the vector will contain only names supplied by the client and will be no larger than needed to hold those names; entries not supplied will be null strings. If the name discipline is full, the vector will have getNumCols() names, either supplied or generated.

```
7.31.3.49 virtual void OsiSolverInterface::setColName ( int ndx, std::string name ) [virtual]
```

Set a column name.

Quietly does nothing if the name discipline (#OsiNameDiscipline) is auto. Quietly fails if the column index is invalid.

Reimplemented in OsiGlpkSolverInterface, and OsiGrbSolverInterface.

```
7.31.3.50 virtual void OsiSolverInterface::setColNames ( OsiNameVec & srcNames, int srcStart, int len, int tgtStart )

[virtual]
```

Set multiple column names.

The run of len entries starting at srcNames[srcStart] are installed as column names starting at column index tgtStart. The base class implementation makes repeated calls to setColName.

```
7.31.3.51 virtual void OsiSolverInterface::deleteColNames (int tgtStart, int len ) [virtual]
```

Delete len column names starting at index tgtStart.

The specified column names are removed and the remaining column names are copied down to close the gap.

```
7.31.3.52 void OsiSolverInterface::setRowColNames ( const CoinMpsIO & mps )
```

Set row and column names from a CoinMpsIO object.

Also sets the name of the objective function. If the name discipline is auto, you get what you asked for. This routine does not use setRowName or setColName.

```
7.31.3.53 void OsiSolverInterface::setRowColNames ( CoinModel & mod )
```

Set row and column names from a **CoinModel** object.

If the name discipline is auto, you get what you asked for. This routine does not use setRowName or setColName.

7.31.3.54 void OsiSolverInterface::setRowColNames (CoinLpIO & mod)

Set row and column names from a CoinLplO object.

Also sets the name of the objective function. If the name discipline is auto, you get what you asked for. This routine does not use setRowName or setColName.

7.31.3.55 virtual void OsiSolverInterface::addCol (const CoinPackedVectorBase & vec, const double collb, const double collb, const double obj) [pure virtual]

Add a column (primal variable) to the problem.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, OsiGrb

7.31.3.56 virtual void OsiSolverInterface::addCol (const CoinPackedVectorBase & vec, const double collb, const double collb, std::string name) [virtual]

Add a named column (primal variable) to the problem.

The default implementation adds the column, then changes the name. This can surely be made more efficient within an OsiXXX class.

7.31.3.57 virtual void OsiSolverInterface::addCol (int *numberElements*, const int * rows, const double * elements, const double collb, const double obj) [virtual]

Add a column (primal variable) to the problem.

7.31.3.58 virtual void OsiSolverInterface::addCol (int *numberElements*, const int * *rows*, const double * *elements*, const double collb, const double obj, std::string name) [virtual]

Add a named column (primal variable) to the problem.

The default implementation adds the column, then changes the name. This can surely be made more efficient within an OsiXXX class.

7.31.3.59 virtual void OsiSolverInterface::addCols (const int *numcols*, const CoinPackedVectorBase *const * cols, const double * collb, const double * collb, const double * obj) [virtual]

Add a set of columns (primal variables) to the problem.

The default implementation simply makes repeated calls to addCol().

Reimplemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, and OsiXprSolverInterface.

7.31.3.60 virtual void OsiSolverInterface::addCols (const int *numcols*, const int * *columnStarts*, const int * *rows*, const double * *elements*, const double * *collb*, const double * *colub*, const double * *obj*) [virtual]

Add a set of columns (primal variables) to the problem.

The default implementation simply makes repeated calls to addCol().

7.31.3.61 int OsiSolverInterface::addCols (CoinModel & modelObject)

Add columns from a model object.

returns -1 if object in bad state (i.e. has row information) otherwise number of errors modelObject non const as can be regularized as part of build

7.31.3.62 virtual void OsiSolverInterface::deleteCols (const int num, const int * collndices) [pure virtual]

Remove a set of columns (primal variables) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted variables are nonbasic.

Implemented in OsiGlpkSolverInterface, OsiSpxSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiGpxSolverInterface, OsiGpx

7.31.3.63 virtual void OsiSolverInterface::addRow (const CoinPackedVectorBase & vec, const double rowlb, const double rowub) [pure virtual]

Add a row (constraint) to the problem.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, and OsiXprSolverInterface.

7.31.3.64 virtual void OsiSolverInterface::addRow (const CoinPackedVectorBase & vec, const double rowlb, const double rowub, std::string name) [virtual]

Add a named row (constraint) to the problem.

The default implementation adds the row, then changes the name. This can surely be made more efficient within an OsiXXX class.

7.31.3.65 virtual void OsiSolverInterface::addRow(const CoinPackedVectorBase & vec, const char rowsen, const double rowrng) [pure virtual]

Add a row (constraint) to the problem.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, and OsiXprSolverInterface.

7.31.3.66 virtual void OsiSolverInterface::addRow (const CoinPackedVectorBase & *vec*, const char *rowsen*, const double *rowrns*, const double *rowrng*, std::string *name*) [virtual]

Add a named row (constraint) to the problem.

The default implementation adds the row, then changes the name. This can surely be made more efficient within an OsiXXX class.

7.31.3.67 virtual void OsiSolverInterface::addRow (int numberElements, const int * columns, const double * element, const double rowlb, const double rowlb) [virtual]

Add a row (constraint) to the problem.

Converts to addRow(CoinPackedVectorBase&,const double,const double).

7.31.3.68 virtual void OsiSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * rows, const double * rowlb, const double * rowub) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

 $Reimplemented \ in \ OsiGlpkSolverInterface, \ OsiGpxSolverInterface, \ OsiMskSolverInterface, \ OsiGrbSolverInterface, \ and \ OsiXprSolverInterface.$

7.31.3.69 virtual void OsiSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * rows, const char * rowsen. const double * rowrhs. const double * rowrng) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiGrbSolverInterface, and OsiXprSolverInterface.

7.31.3.70 virtual void OsiSolverInterface::addRows (const int *numrows*, const int * *rowStarts*, const int * *columns*, const double * *element*, const double * *rowlb*, const double * *rowub*) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

7.31.3.71 int OsiSolverInterface::addRows (CoinModel & modelObject)

Add rows from a **CoinModel** object.

Returns -1 if the object is in the wrong state (i.e., has column-major information), otherwise the number of errors.

The modelObject is not const as it can be regularized as part of the build.

7.31.3.72 virtual void OsiSolverInterface::deleteRows (const int num, const int * rowIndices) [pure virtual]

Delete a set of rows (constraints) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted rows are loose.

Implemented in OsiGlpkSolverInterface, OsiSpxSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiGpsSolverInterface, OsiGps

7.31.3.73 virtual void OsiSolverInterface::replaceMatrixOptional (const CoinPackedMatrix &) [inline], [virtual]

Replace the constraint matrix.

I (JJF) am getting annoyed because I can't just replace a matrix. The default behavior of this is do nothing so only use where that would not matter, e.g. strengthening a matrix for MIP.

Definition at line 1228 of file OsiSolverInterface.hpp.

7.31.3.74 virtual void OsiSolverInterface::replaceMatrix (const CoinPackedMatrix &) [inline], [virtual]

Replace the constraint matrix.

And if it does matter (not used at present)

Definition at line 1234 of file OsiSolverInterface.hpp.

7.31.3.75 virtual void OsiSolverInterface::saveBaseModel() [inline], [virtual]

Save a copy of the base model.

If solver wants it can save a copy of "base" (continuous) model here.

Definition at line 1240 of file OsiSolverInterface.hpp.

7.31.3.76 virtual void OsiSolverInterface::restoreBaseModel(int numberRows) [virtual]

Reduce the constraint system to the specified number of constraints.

If solver wants it can restore a copy of "base" (continuous) model here.

Note

The name is somewhat misleading. Implementors should consider the opportunity to optimise behaviour in the common case where numberRows is exactly the number of original constraints. Do not, however, neglect the possibility that numberRows does not equal the number of original constraints.

7.31.3.77 virtual ApplyCutsReturnCode OsiSolverInterface::applyCuts (const OsiCuts & cs, double effectivenessLb = 0.0)
[virtual]

Apply a collection of cuts.

Only cuts which have an effectiveness >= effectivenessLb are applied.

- ReturnCode.getNumineffective() number of cuts which were not applied because they had an effectiveness
 effectivenessLb
- ReturnCode.getNuminconsistent() number of invalid cuts
- ReturnCode.getNuminconsistentWrtIntegerModel() number of cuts that are invalid with respect to this integer
 model
- ReturnCode.getNuminfeasible() number of cuts that would make this integer model infeasible
- ReturnCode.getNumApplied() number of integer cuts which were applied to the integer model
- cs.size() == getNumineffective() + getNuminconsistent() + getNuminconsistentWrtIntegerModel() + getNuminfeasible() + getNumApplied()

Reimplemented in OsiGrbSolverInterface.

7.31.3.78 virtual void OsiSolverInterface::applyRowCuts (int numberCuts, const OsiRowCut * cuts) [virtual]

Apply a collection of row cuts which are all effective.

applyCuts seems to do one at a time which seems inefficient. Would be even more efficient to pass an array of pointers.

7.31.3.79 virtual void OsiSolverInterface::applyRowCuts (int numberCuts, const OsiRowCut ** cuts) [virtual]

Apply a collection of row cuts which are all effective.

This is passed in as an array of pointers.

7.31.3.80 virtual void OsiSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowlb, const double * rowlb) [pure virtual]

Load in a problem by copying the arguments.

The constraints on the rows are given by lower and upper bounds.

If a pointer is 0 then the following values are the default:

- · colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- · rowub: all rows have upper bound infinity

- rowlb: all rows have lower bound -infinity
- obj: all variables have 0 objective coefficient

Note that the default values for rowub and rowlb produce the constraint -infty \leq = ax \leq = infty. This is probably not what you want.

Implemented in OsiGlpkSolverInterface, OsiSpxSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiMsk

7.31.3.81 virtual void OsiSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowlb, doub

Load in a problem by assuming ownership of the arguments.

The constraints on the rows are given by lower and upper bounds.

For default argument values see the matching loadProblem method.

Warning

The arguments passed to this method will be freed using the C++ delete and delete[] functions.

Implemented in OsiGlpkSolverInterface, OsiSpxSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiXprSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiMskSolverInterface, OsiCpxSolverInterface, OsiCpx

7.31.3.82 virtual void OsiSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowrns, const double * rowrns) [pure virtual]

Load in a problem by copying the arguments.

The constraints on the rows are given by sense/rhs/range triplets.

If a pointer is 0 then the following values are the default:

- · colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- obj: all variables have 0 objective coefficient
- rowsen: all rows are >=
- rowrhs: all right hand sides are 0
- rowrng: 0 for the ranged rows

Note that the default values for rowsen, rowrhs, and rowrng produce the constraint ax \geq = 0.

Implemented in OsiGlpkSolverInterface, OsiSpxSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiCpxSolverInterface, OsiCpx

7.31.3.83 virtual void OsiSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowrng, double *& rowrng) [pure virtual]

Load in a problem by assuming ownership of the arguments.

The constraints on the rows are given by sense/rhs/range triplets.

For default argument values see the matching loadProblem method.

Warning

The arguments passed to this method will be freed using the C++ delete and delete[] functions.

Implemented in OsiGlpkSolverInterface, OsiSpxSolverInterface, OsiCpxSolverInterface, OsiMskSolverInterface, OsiXprSolverInterface, and OsiGrbSolverInterface.

7.31.3.84 virtual void OsiSolverInterface::loadProblem (const int *numcols*, const int *numrows*, const CoinBigIndex * *start*, const int * *index*, const double * *value*, const double * *collb*, const double * *colub*, const double * *rowlb*, const double * *rowlb*) [pure virtual]

Load in a problem by copying the arguments.

The constraint matrix is is specified with standard column-major column starts / row indices / coefficients vectors. The constraints on the rows are given by lower and upper bounds.

The matrix vectors must be gap-free. Note that start must have numcols+1 entries so that the length of the last column can be calculated as start [numcols]-start[numcols-1].

See the previous loadProblem method using rowlb and rowub for default argument values.

7.31.3.85 virtual void OsiSolverInterface::loadProblem (const int *numcols*, const int *numrows*, const CoinBigIndex * *start*, const int * *index*, const double * *value*, const double * *collb*, const double * *colub*, const double * *obj*, const char * *rowsen*, const double * *rowrhs*, const double * *rowrng*) [pure virtual]

Load in a problem by copying the arguments.

The constraint matrix is is specified with standard column-major column starts / row indices / coefficients vectors. The constraints on the rows are given by sense/rhs/range triplets.

The matrix vectors must be gap-free. Note that start must have numcols+1 entries so that the length of the last column can be calculated as start [numcols]-start [numcols-1].

See the previous loadProblem method using sense/rhs/range for default argument values.

7.31.3.86 virtual int OsiSolverInterface::loadFromCoinModel (CoinModel & modelObject, bool keepSolution = false)
[virtual]

Load a model from a CoinModel object.

Return the number of errors encountered.

The modelObject parameter cannot be const as it may be changed as part of process. If keepSolution is true will try and keep warmStart.

7.31.3.87 virtual int OsiSolverInterface::readMps (const char * filename, const char * extension = "mps") [virtual]

Read a problem in MPS format from the given filename.

The default implementation uses **CoinMpsIO::readMps()** to read the MPS file and returns the number of errors encountered.

Reimplemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiS

```
7.31.3.88 virtual int OsiSolverInterface::readMps ( const char * filename, const char * extension, int & numberSets, CoinSet **& sets ) [virtual]
```

Read a problem in MPS format from the given full filename.

This uses **CoinMpsIO::readMps()** to read the MPS file and returns the number of errors encountered. It also may return an array of set information

```
7.31.3.89 virtual int OsiSolverInterface::readGMPL ( const char * filename, const char * dataname = NULL ) [virtual]
```

Read a problem in GMPL format from the given filenames.

The default implementation uses **CoinMpsIO::readGMPL()**. This capability is available only if the third-party package Glpk is installed.

```
7.31.3.90 virtual void OsiSolverInterface::writeMps ( const char * filename, const char * extension = "mps", double objSense = 0.0) const [pure virtual]
```

Write the problem in MPS format to the specified file.

If objSense is non-zero, a value of -1.0 causes the problem to be written with a maximization objective; +1.0 forces a minimization objective. If objSense is zero, the choice is left to the implementation.

Implemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiMskSolverInterface, OsiSpxSolverInterface, OsiSpx

```
7.31.3.91 int OsiSolverInterface::writeMpsNative ( const char * filename, const char ** rowNames, const char ** columnNames, int formatType = 0, int numberAcross = 2, double objSense = 0.0, int numberSOS = 0, const CoinSet * setInfo = NULL ) const
```

Write the problem in MPS format to the specified file with more control over the output.

Row and column names may be null. formatType is

- 0 normal
- 1 extra accuracy
- · 2 IEEE hex

Returns non-zero on I/O error

```
7.31.3.92 virtual void OsiSolverInterface::writeLp ( const char * filename, const char * extension = "lp", double epsilon = 1e-5, int numberAcross = 10, int decimals = 5, double objSense = 0.0, bool useRowNames = true ) const [virtual]
```

Write the problem into an Lp file of the given filename with the specified extension.

Coefficients with value less than epsilon away from an integer value are written as integers. Write at most numberAcross monomials on a line. Write non integer numbers with decimals digits after the decimal point.

The written problem is always a minimization problem. If the current problem is a maximization problem, the intended objective function for the written problem is the current objective function multiplied by -1. If the current problem is a minimization problem, the intended objective function for the written problem is the current objective function. If objSense < 0, the intended objective function is multiplied by -1 before writing the problem. It is left unchanged otherwise.

Write objective function name and constraint names if useRowNames is true. This version calls writeLpNative().

7.31.3.93 virtual void OsiSolverInterface::writeLp (FILE * fp, double epsilon = 1e-5, int numberAcross = 10, int decimals = 5, double objSense = 0.0. bool useRowNames = true) const [virtual]

Write the problem into the file pointed to by the parameter fp.

Other parameters are similar to those of writeLp() with first parameter filename.

7.31.3.94 int OsiSolverInterface::writeLpNative (const char * filename, char const *const *const rowNames, char const *const *const columnNames, const double epsilon = 1 . 0e-5, const int numberAcross = 10, const int decimals = 5, const double objSense = 0 . 0, const bool useRowNames = true) const

Write the problem into an Lp file.

Parameters are similar to those of writeLp(), but in addition row names and column names may be given.

Parameter rowNames may be NULL, in which case default row names are used. If rowNames is not NULL, it must have exactly one entry per row in the problem and one additional entry (rowNames[getNumRows()] with the objective function name. These getNumRows()+1 entries must be distinct. If this is not the case, default row names are used. In addition, format restrictions are imposed on names (see CoinLpIO::is_invalid_name() for details).

Similar remarks can be made for the parameter columnNames which must either be NULL or have exactly getNumCols() distinct entries.

Write objective function name and constraint names if useRowNames is true.

7.31.3.95 int OsiSolverInterface::writeLpNative (FILE * fp, char const *const *const rowNames, char const *const *const columnNames, const double epsilon = 1.0e-5, const int numberAcross = 10, const int decimals = 5, const double objSense = 0.0, const bool useRowNames = true) const

Write the problem into the file pointed to by the parameter fp.

Other parameters are similar to those of writeLpNative() with first parameter filename.

7.31.3.96 virtual int OsiSolverInterface::readLp(const char * filename, const double epsilon = 1e-5) [virtual]

Read file in LP format from file with name filename.

See class CoinLpIO for description of this format.

7.31.3.97 int OsiSolverInterface::readLp (FILE * fp, const double epsilon = 1e-5)

Read file in LP format from the file pointed to by fp.

See class CoinLpIO for description of this format.

7.31.3.98 int OsiSolverInterface::differentModel (OsiSolverInterface & other, bool ignoreNames = true)

Check two models against each other.

Return nonzero if different. Ignore names if that set. (Note initial version does not check names) May modify both models by cleaning up

7.31.3.99 void OsiSolverInterface::setApplicationData (void * appData)

Set application data.

This is a pointer that the application can store into and retrieve from the solver interface. This field is available for the application to optionally define and use.

7.31.3.100 void OsiSolverInterface::setAuxiliaryInfo (OsiAuxInfo * auxiliaryInfo)

Create a clone of an Auxiliary Information object.

The base class just stores an application data pointer but can be more general. Application data pointer is designed for one user while this can be extended to cope with more general extensions.

7.31.3.101 virtual void OsiSolverInterface::passInMessageHandler (CoinMessageHandler * handler) [virtual]

Pass in a message handler.

It is the client's responsibility to destroy a message handler installed by this routine; it will not be destroyed when the solver interface is destroyed.

Reimplemented in OsiCpxSolverInterface, OsiMskSolverInterface, and OsiXprSolverInterface.

7.31.3.102 void OsiSolverInterface::findIntegers (bool justCount)

Identify integer variables and create corresponding objects.

Record integer variables and create an OsiSimpleInteger object for each one. All existing OsiSimpleInteger objects will be destroyed. If justCount then no objects created and we just store numberIntegers

7.31.3.103 virtual int OsiSolverInterface::findIntegersAndSOS(bool justCount) [virtual]

Identify integer variables and SOS and create corresponding objects.

Record integer variables and create an OsiSimpleInteger object for each one. All existing OsiSimpleInteger objects will be destroyed. If the solver supports SOS then do the same for SOS.

If justCount then no objects created and we just store numberIntegers Returns number of SOS

7.31.3.104 void OsiSolverInterface::addObjects (int numberObjects, OsiObject ** objects)

Add in object information.

Objects are cloned; the owner can delete the originals.

7.31.3.105 double OsiSolverInterface::forceFeasible ()

Use current solution to set bounds so current integer feasible solution will stay feasible.

Only feasible bounds will be used, even if current solution outside bounds. The amount of such violation will be returned (and if small can be ignored)

7.31.3.106 virtual void OsiSolverInterface::activateRowCutDebugger (const char * modelName) [virtual]

Activate the row cut debugger.

If modelName is in the set of known models then all cuts are checked to see that they do NOT cut off the optimal solution known to the debugger.

7.31.3.107 virtual void OsiSolverInterface::activateRowCutDebugger (const double * solution, bool enforceOptimality = true)
[virtual]

Activate the row cut debugger using a full solution array.

Activate the debugger for a model not included in the debugger's internal database. Cuts will be checked to see that they do NOT cut off the given solution.

solution must be a full solution vector, but only the integer variables need to be correct. The debugger will fill in the continuous variables by solving an Ip relaxation with the integer variables fixed as specified. If the given values for the

continuous variables should be preserved, set keepContinuous to true.

7.31.3.108 const OsiRowCutDebugger * OsiSolverInterface::getRowCutDebugger () const

Get the row cut debugger provided the solution known to the debugger is within the feasible region held in the solver.

If there is a row cut debugger object associated with model AND if the solution known to the debugger is within the solver's current feasible region (i.e., the column bounds held in the solver are compatible with the known solution) then a pointer to the debugger is returned which may be used to test validity of cuts.

Otherwise NULL is returned

7.31.3.109 OsiRowCutDebugger* OsiSolverInterface::getRowCutDebuggerAlways () const

Get the row cut debugger object.

Return the row cut debugger object if it exists. One common usage of this method is to obtain a debugger object in order to execute OsiRowCutDebugger::redoSolution (so that the stored solution is again compatible with the problem held in the solver).

7.31.3.110 virtual int OsiSolverInterface::canDoSimplexInterface() const [virtual]

Return the simplex implementation level.

The return codes are:

- 0: the simplex interface is not implemented.
- 1: the Group 1 (tableau access) methods are implemented.
- · 2: the Group 2 (pivoting) methods are implemented

The codes are cumulative - a solver which implements Group 2 also implements Group 1.

Reimplemented in OsiCpxSolverInterface, and OsiGrbSolverInterface.

7.31.3.111 virtual void OsiSolverInterface::enableFactorization() const [virtual]

Prepare the solver for the use of tableau access methods.

Prepares the solver for the use of the tableau access methods, if any such preparation is required.

The const attribute is required due to the places this method may be called (e.g., within CglCutGenerator::generate-Cuts()).

Reimplemented in OsiCpxSolverInterface, and OsiGrbSolverInterface.

7.31.3.112 virtual void OsiSolverInterface::disableFactorization () const [virtual]

Undo the effects of enableFactorization.

Reimplemented in OsiCpxSolverInterface, and OsiGrbSolverInterface.

7.31.3.113 virtual bool OsiSolverInterface::basisIsAvailable()const [virtual]

Check if an optimal basis is available.

Returns true if the problem has been solved to optimality and a basis is available. This should be used to see if the tableau access operations are possible and meaningful.

Note

Implementors please note that this method may be called before enableFactorization.

Reimplemented in OsiCpxSolverInterface, and OsiGrbSolverInterface.

```
7.31.3.114 virtual void OsiSolverInterface::getBasisStatus (int * cstat, int * rstat ) const [virtual]
```

Retrieve status information for column and row variables.

This method returns status as integer codes:

- 0: free
- 1: basic
- · 2: nonbasic at upper bound
- · 3: nonbasic at lower bound

The getWarmStart method provides essentially the same functionality for a simplex-oriented solver, but the implementation details are very different.

Note

Logical variables associated with rows are all assumed to have +1 coefficients, so for a \leq = constraint the logical will be at lower bound if the constraint is tight.

Implementors may choose to implement this method as a wrapper which converts a **CoinWarmStartBasis** to the requested representation.

Reimplemented in OsiCpxSolverInterface, and OsiGrbSolverInterface.

```
7.31.3.115 virtual int OsiSolverInterface::setBasisStatus ( const int * cstat, const int * rstat ) [virtual]
```

Set the status of column and row variables and update the basis factorization and solution.

Status information should be coded as documented for getBasisStatus. Returns 0 if all goes well, 1 if something goes wrong.

This method differs from setWarmStart in the format of the input and in its immediate effect. Think of it as setWarmStart immediately followed by resolve, but no pivots are allowed.

Note

Implementors may choose to implement this method as a wrapper that calls setWarmStart and resolve if the no pivot requirement can be satisfied.

```
7.31.3.116 virtual void OsiSolverInterface::getReducedGradient ( double * columnReducedCosts, double * duals, const double * c ) const [virtual]
```

Calculate duals and reduced costs for the given objective coefficients.

The solver's objective coefficient vector is not changed.

```
7.31.3.117 virtual void OsiSolverInterface::getBlnvARow(int row, double * z, double * slack = NULL) const [virtual]
```

Get a row of the tableau.

If slack is not null, it will be loaded with the coefficients for the artificial (logical) variables (i.e., the row of the basis inverse).

Reimplemented in OsiCpxSolverInterface.

7.31.3.118 virtual void OsiSolverInterface::getBasics (int * index) const [virtual]

Get indices of basic variables.

If the logical (artificial) for row i is basic, the index should be coded as (getNumCols + i). The order of indices must match the order of elements in the vectors returned by getBlnvACol and getBlnvCol.

Reimplemented in OsiCpxSolverInterface.

7.31.3.119 virtual void OsiSolverInterface::enableSimplexInterface (bool doingPrimal) [virtual]

Enables normal operation of subsequent functions.

This method is supposed to ensure that all typical things (like reduced costs, etc.) are updated when individual pivots are executed and can be queried by other methods. says whether will be doing primal or dual

7.31.3.120 virtual int OsiSolverInterface::pivot (int colln, int colOut, int outStatus) [virtual]

Perform a pivot by substituting a colln for colOut in the basis.

The status of the leaving variable is given in outStatus. Where 1 is to upper bound, -1 to lower bound Return code was undefined - now for OsiClp is 0 for okay, 1 if inaccuracy forced re-factorization (should be okay) and -1 for singular factorization

7.31.3.121 virtual int OsiSolverInterface::primalPivotResult (int *colln*, int *sign*, int & *colOut*, int & *outStatus*, double & t, CoinPackedVector * dx) [virtual]

Obtain a result of the primal pivot Outputs: colOut – leaving column, outStatus – its status, t – step size, and, if dx!=NU-LL, *dx – primal ray direction.

Inputs: colln – entering column, sign – direction of its change (+/-1). Both for colln and colOut, artificial variables are index by the negative of the row index minus 1. Return code (for now): 0 – leaving variable found, -1 – everything else? Clearly, more informative set of return values is required Primal and dual solutions are updated

7.31.3.122 virtual OsiSolverInterface* OsiSolverInterface::clone(bool copyData = true) const [pure virtual]

Clone.

The result of calling clone(false) is defined to be equivalent to calling the default constructor OsiSolverInterface().

Implemented in OsiGlpkSolverInterface, OsiMskSolverInterface, OsiCpxSolverInterface, OsiXprSolverInterface, OsiGrbSolverInterface, and OsiSpxSolverInterface.

7.31.3.123 virtual void OsiSolverInterface::reset() [virtual]

Reset the solver interface.

A call to reset() returns the solver interface to the same state as it would have if it had just been constructed by calling the default constructor OsiSolverInterface().

Reimplemented in OsiGlpkSolverInterface, OsiCpxSolverInterface, and OsiGrbSolverInterface.

7.31.3.124 virtual void OsiSolverInterface::applyRowCut (const OsiRowCut & rc) [protected], [pure virtual]

Apply a row cut (append to the constraint matrix).

Implemented in OsiCpxSolverInterface, OsiGrbSolverInterface, OsiGlpkSolverInterface, OsiMskSolverInterface, OsiXprSolverInterface, and OsiSpxSolverInterface.

7.31.3.125 virtual void OsiSolverInterface::applyColCut (const OsiColCut & cc) [protected], [pure virtual]

Apply a column cut (adjust the bounds of one or more variables).

Implemented in OsiCpxSolverInterface, OsiGrbSolverInterface, OsiGlpkSolverInterface, OsiMskSolverInterface, OsiMsk

7.31.3.126 void OsiSolverInterface::setInitialData() [protected]

Set OsiSolverInterface object state for default constructor.

This routine establishes the initial values of data fields in the OsiSolverInterface object when the object is created using the default constructor.

7.31.4 Friends And Related Function Documentation

7.31.4.1 void OsiSolverInterfaceCommonUnitTest (const OsiSolverInterface * emptySi, const std::string & mpsDir, const std::string & netlibDir) [friend]

A function that tests the methods in the OsiSolverInterface class.

Some time ago, if this method is compiled with optimization, the compilation took 10-15 minutes and the machine pages (has 256M core memory!)...

7.31.4.2 void OsiSolverInterfaceMpsUnitTest (const std::vector < OsiSolverInterface * > & vecSiP, const std::string & mpsDir) [friend]

A function that tests that a lot of problems given in MPS files (mostly the NETLIB problems) solve properly with all the specified solvers.

The routine creates a vector of NetLib problems (problem name, objective, various other characteristics), and a vector of solvers to be tested.

Each solver is run on each problem. The run is deemed successful if the solver reports the correct problem size after loading and returns the correct objective value after optimization.

If multiple solvers are available, the results are compared pairwise against the results reported by adjacent solvers in the solver vector. Due to limitations of the volume solver, it must be the last solver in vecEmptySiP.

7.31.5 Member Data Documentation

7.31.5.1 OsiRowCutDebugger* OsiSolverInterface::rowCutDebugger [mutable], [protected]

Pointer to row cut debugger object.

Mutable so that we can update the solution held in the debugger while maintaining const'ness for the Osi object.

Definition at line 2016 of file OsiSolverInterface.hpp.

7.31.5.2 bool OsiSolverInterface::defaultHandler_ [protected]

Flag to say if the currrent handler is the default handler.

Indicates if the solver interface object is responsible for destruction of the handler (true) or if the client is responsible (false).

Definition at line 2025 of file OsiSolverInterface.hpp.

The documentation for this class was generated from the following file:

· OsiSolverInterface.hpp

7.32 OsiSolverResult Class Reference

Solver Result Class.

#include <OsiSolverBranch.hpp>

Public Member Functions

Add and Get methods

- void createResult (const OsiSolverInterface &solver, const double *lowerBefore, const double *upperBefore)
- void restoreResult (OsiSolverInterface &solver) const

Restore result.

const CoinWarmStartBasis & basis () const

Get basis.

• double objective Value () const

Objective value (as minimization)

• const double * primalSolution () const

Primal solution.

• const double * dualSolution () const

Dual solution.

· const OsiSolverBranch & fixed () const

Extra fixed.

Constructors and destructors

• OsiSolverResult ()

Default Constructor.

OsiSolverResult (const OsiSolverInterface &solver, const double *lowerBefore, const double *upperBefore)

Constructor from solver.

OsiSolverResult (const OsiSolverResult &rhs)

Copy constructor.

• OsiSolverResult & operator= (const OsiSolverResult &rhs)

Assignment operator.

∼OsiSolverResult ()

Destructor.

7.32.1 Detailed Description

Solver Result Class.

This provides information on a result as a set of tighter bounds on both ways

Definition at line 83 of file OsiSolverBranch.hpp.

The documentation for this class was generated from the following file:


OsiSolverBranch.hpp

7.33 OsiSOS Class Reference


Define Special Ordered Sets of type 1 and 2.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiSOS:



Collaboration diagram for OsiSOS:



Public Member Functions

 OsiSOS (const OsiSolverInterface *solver, int numberMembers, const int *which, const double *weights, int type=1) Useful constructor - which are indices and weights are also given.

virtual OsiObject * clone () const

Clone.

virtual double infeasibility (const OsiBranchingInformation *info, int &whichWay) const

Infeasibility - large is 0.5.

• virtual double feasibleRegion (OsiSolverInterface *solver, const OsiBranchingInformation *info) const

Set bounds to fix the variable at the current (integer) value.

 virtual OsiBranchingObject * createBranch (OsiSolverInterface *solver, const OsiBranchingInformation *info, int way) const

Creates a branching object.

• virtual double upEstimate () const

Return "up" estimate (default 1.0e-5)

· virtual double downEstimate () const

Return "down" estimate (default 1.0e-5)

virtual void resetSequenceEtc (int numberColumns, const int *originalColumns)

Redoes data when sequence numbers change.

• int numberMembers () const

Number of members.

• const int * members () const

Members (indices in range 0 ... numberColumns-1)

int sosType () const

SOS type.

int setType () const

SOS type.

· const double * weights () const

Array of weights.

· virtual bool canDoHeuristics () const

Return true if object can take part in normal heuristics.

void setIntegerValued (bool yesNo)

Set whether set is integer valued or not.

· virtual bool canHandleShadowPrices () const

Return true if knows how to deal with Pseudo Shadow Prices.

void setNumberMembers (int value)

Set number of members.

• int * mutableMembers () const

Members (indices in range 0 ... numberColumns-1)

void setSosType (int value)

Set SOS type.

• double * mutableWeights () const

Array of weights.

Protected Attributes

int * members

data

double * weights

Weights.

· int numberMembers_

Number of members.

int sosType_

SOS type.

bool integerValued_

Whether integer valued.

7.33.1 Detailed Description

Define Special Ordered Sets of type 1 and 2.

These do not have to be integer - so do not appear in lists of integers.

which_ points columns of matrix

Definition at line 674 of file OsiBranchingObject.hpp.

7.33.2 Constructor & Destructor Documentation

7.33.2.1 OsiSOS::OsiSOS (const OsiSolverInterface * solver, int numberMembers, const int * which, const double * weights, int type = 1)

Useful constructor - which are indices and weights are also given.

If null then 0,1,2.. type is SOS type

7.33.3 Member Function Documentation

7.33.3.1 virtual double OsiSOS::feasibleRegion (OsiSolverInterface * solver, const OsiBranchingInformation * info) const [virtual]

Set bounds to fix the variable at the current (integer) value.

Given an integer value, set the lower and upper bounds to fix the variable. Returns amount it had to move variable. Implements OsiObject.

```
7.33.3.2 virtual OsiBranchingObject* OsiSOS::createBranch ( OsiSolverInterface * solver, const OsiBranchingInformation * info, int way ) const [virtual]
```

Creates a branching object.

The preferred direction is set by way, 0 for down, 1 for up.

Reimplemented from OsiObject.

7.33.4 Member Data Documentation

7.33.4.1 int* OsiSOS::members_ [protected]

data

Members (indices in range 0 ... numberColumns-1)

Definition at line 774 of file OsiBranchingObject.hpp.

The documentation for this class was generated from the following file:


OsiBranchingObject.hpp

7.34 OsiSOSBranchingObject Class Reference


Branching object for Special ordered sets.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiSOSBranchingObject:



Collaboration diagram for OsiSOSBranchingObject:



Public Member Functions

- virtual OsiBranchingObject * clone () const
 - Clone.
- virtual double branch (OsiSolverInterface *solver)

Does next branch and updates state.

• virtual void print (const OsiSolverInterface *solver=NULL)

Print something about branch - only if log level high.

Additional Inherited Members

7.34.1 Detailed Description

Branching object for Special ordered sets.

Definition at line 789 of file OsiBranchingObject.hpp.

The documentation for this class was generated from the following file:


OsiBranchingObject.hpp

7.35 OsiSpxSolverInterface Class Reference


SoPlex Solver Interface Instantiation of OsiSpxSolverInterface for SoPlex.

#include <OsiSpxSolverInterface.hpp>

Inheritance diagram for OsiSpxSolverInterface:



Collaboration diagram for OsiSpxSolverInterface:



Public Member Functions

virtual void setObjSense (double s)

Set objective function sense (1 for min (default), -1 for max,)

virtual void setColSolution (const double *colsol)

Set the primal solution column values.

virtual void setRowPrice (const double *rowprice)

Set dual solution vector.

Solve methods

• virtual void initialSolve ()

Solve initial LP relaxation.

• virtual void resolve ()

Resolve an LP relaxation after problem modification.

• virtual void branchAndBound ()

Invoke solver's built-in enumeration algorithm.

Parameter set/get methods

The set methods return true if the parameter was set to the given value, false otherwise.

There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the volume algorithm), the parameter is not yet implemented for the solver or simply the value of the parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.

The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.

• bool setIntParam (OsiIntParam key, int value)

Set an integer parameter.

bool setDblParam (OsiDblParam key, double value)

Set a double parameter.

bool getIntParam (OsiIntParam key, int &value) const

Get an integer parameter.

• bool getDblParam (OsiDblParam key, double &value) const

Get a double parameter.

bool getStrParam (OsiStrParam key, std::string &value) const

Get a string parameter.

- void setTimeLimit (double value)
- double getTimeLimit () const

Methods returning info on how the solution process terminated

· virtual bool isAbandoned () const

Are there a numerical difficulties?

virtual bool isProvenOptimal () const

Is optimality proven?

· virtual bool isProvenPrimalInfeasible () const

Is primal infeasiblity proven?

• virtual bool isProvenDualInfeasible () const

Is dual infeasiblity proven?

virtual bool isDualObjectiveLimitReached () const

Is the given dual objective limit reached?

virtual bool isIterationLimitReached () const

Iteration limit reached?

· virtual bool isTimeLimitReached () const

Time limit reached?

WarmStart related methods

CoinWarmStart * getEmptyWarmStart () const

Get empty warm start object.

virtual CoinWarmStart * getWarmStart () const

Get warmstarting information.

virtual bool setWarmStart (const CoinWarmStart *warmstart)

Set warmstarting information.

Hotstart related methods (primarily used in strong branching).

 tr>

The user can create a hotstart (a snapshot) of the optimization process then reoptimize over and over again always starting from there.

NOTE: between hotstarted optimizations only bound changes are allowed.

virtual void markHotStart ()

Create a hotstart point of the optimization process.

virtual void solveFromHotStart ()

Optimize starting from the hotstart.

virtual void unmarkHotStart ()

Delete the snapshot.

Methods related to querying the input data

virtual int getNumCols () const

Get number of columns.

virtual int getNumRows () const

Get number of rows.

virtual int getNumElements () const

Get number of nonzero elements.

virtual const double * getColLower () const

Get pointer to array[getNumCols()] of column lower bounds.

virtual const double * getColUpper () const

Get pointer to array[getNumCols()] of column upper bounds.

virtual const char * getRowSense () const

Get pointer to array[getNumRows()] of row constraint senses.

virtual const double * getRightHandSide () const

Get pointer to array[getNumRows()] of rows right-hand sides.

virtual const double * getRowRange () const

Get pointer to array[getNumRows()] of row ranges.

virtual const double * getRowLower () const

Get pointer to array[getNumRows()] of row lower bounds.

virtual const double * getRowUpper () const

Get pointer to array[getNumRows()] of row upper bounds.

virtual const double * getObjCoefficients () const

Get pointer to array[getNumCols()] of objective function coefficients.

• virtual double getObjSense () const

Get objective function sense (1 for min (default), -1 for max)

· virtual bool isContinuous (int colNumber) const

Return true if column is continuous.

virtual const CoinPackedMatrix * getMatrixByRow () const

Get pointer to row-wise copy of matrix.

virtual const CoinPackedMatrix * getMatrixByCol () const

Get pointer to column-wise copy of matrix.

· virtual double getInfinity () const

Get solver's value for infinity.

Methods related to querying the solution

virtual const double * getColSolution () const

Get pointer to array[getNumCols()] of primal solution vector.

virtual const double * getRowPrice () const

Get pointer to array[getNumRows()] of dual prices.

virtual const double * getReducedCost () const

Get a pointer to array[getNumCols()] of reduced costs.

virtual const double * getRowActivity () const

Get pointer to array[getNumRows()] of row activity levels (constraint matrix times the solution vector.

virtual double getObjValue () const

Get objective function value.

virtual int getIterationCount () const

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

virtual std::vector< double * > getDualRays (int maxNumRays, bool fullRay=false) const

Get as many dual rays as the solver can provide.

virtual std::vector< double * > getPrimalRays (int maxNumRays) const

Get as many primal rays as the solver can provide.

Changing bounds on variables and constraints

virtual void setObjCoeff (int elementIndex, double elementValue)

Set an objective function coefficient.

virtual void setColLower (int elementIndex, double elementValue)

Set a single column lower bound

Use -COIN_DBL_MAX for -infinity.

virtual void setColUpper (int elementIndex, double elementValue)

Set a single column upper bound

Use COIN DBL MAX for infinity.

virtual void setColBounds (int elementIndex, double lower, double upper)

Set a single column lower and upper bound

The default implementation just invokes setColLower and setColUpper

virtual void setRowLower (int elementIndex, double elementValue)

Set a single row lower bound

Use -COIN DBL MAX for -infinity.

virtual void setRowUpper (int elementIndex, double elementValue)

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

• virtual void setRowBounds (int elementIndex, double lower, double upper)

Set a single row lower and upper bound

The default implementation just invokes setRowUower and setRowUpper

virtual void setRowType (int index, char sense, double rightHandSide, double range)

Set the type of a single row

Integrality related changing methods

virtual void setContinuous (int index)

Set the index-th variable to be a continuous variable.

virtual void setInteger (int index)

Set the index-th variable to be an integer variable.

Methods to expand a problem. < br>

Note that if a column is added then by default it will correspond to a continuous variable.

virtual void addCol (const CoinPackedVectorBase &vec, const double collb,
Add a column (primal variable) to the problem.

virtual void deleteCols (const int num, const int *colIndices)

Remove a set of columns (primal variables) from the problem.

virtual void addRow (const CoinPackedVectorBase &vec, const double rowlb, const double rowlb)

Add a row (constraint) to the problem.

 virtual void addRow (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng)

Add a row (constraint) to the problem.

virtual void deleteRows (const int num, const int *rowIndices)

Delete a set of rows (constraints) from the problem.

Methods to input a problem

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowlb, const double *rowlb)

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&colub, double *&colub, double *&rowub)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowrng)

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

 virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, char *&rowsen, double *&rowrhs, double *&rowrng)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowlb, const double *rowlb, const double *rowlb

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

 virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *colub, const double *obj, const char *rowsen, const double *rowrhs, const double *rowrng)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

virtual int readMps (const char *filename, const char *extension="mps")

Read an mps file from the given filename.

• virtual void writeMps (const char *filename, const char *extension="mps", double objSense=0.0) const Write the problem into an mps file of the given filename.

Constructors and destructor

• OsiSpxSolverInterface ()

Default Constructor.

virtual OsiSolverInterface * clone (bool copyData=true) const

Clone

OsiSpxSolverInterface (const OsiSpxSolverInterface &)

Copy constructor.

OsiSpxSolverInterface & operator= (const OsiSpxSolverInterface &rhs)

Assignment operator.

virtual ∼OsiSpxSolverInterface ()

Destructor.

Protected Member Functions

Protected methods

virtual void applyRowCut (const OsiRowCut &rc)

Apply a row cut. Return true if cut was applied.

virtual void applyColCut (const OsiColCut &cc)

Apply a column cut (bound adjustment).

Protected Attributes

Protected member data

 soplex::SoPlex * soplex_ SoPlex solver object.

Friends

void OsiSpxSolverInterfaceUnitTest (const std::string &mpsDir, const std::string &netlibDir)
 A function that tests the methods in the OsiSpxSolverInterface class.

Additional Inherited Members

7.35.1 Detailed Description

SoPlex Solver Interface Instantiation of OsiSpxSolverInterface for SoPlex.

Definition at line 36 of file OsiSpxSolverInterface.hpp.

7.35.2 Member Function Documentation

```
7.35.2.1 virtual bool OsiSpxSolverInterface::setWarmStart ( const CoinWarmStart * warmstart ) [virtual]
```

Set warmstarting information.

Return true/false depending on whether the warmstart information was accepted or not.

Implements OsiSolverInterface.

```
7.35.2.2 virtual const char* OsiSpxSolverInterface::getRowSense() const [virtual]
```

Get pointer to array[getNumRows()] of row constraint senses.

- 'L': <= constraint
- 'E': = constraint
- 'G': >= constraint
- · 'R': ranged constraint
- · 'N': free constraint

Implements OsiSolverInterface.

```
7.35.2.3 virtual const double* OsiSpxSolverInterface::getRightHandSide( ) const [virtual]
```

Get pointer to array[getNumRows()] of rows right-hand sides.

```
if rowsense()[i] == 'L' then rhs()[i] == rowupper()[i]
```

- if rowsense()[i] == 'G' then rhs()[i] == rowlower()[i]
- if rowsense()[i] == 'R' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'N' then rhs()[i] == 0.0

Implements OsiSolverInterface.

7.35.2.4 virtual const double* OsiSpxSolverInterface::getRowRange() const [virtual]

Get pointer to array[getNumRows()] of row ranges.

- if rowsense()[i] == 'R' then rowrange()[i] == rowupper()[i] rowlower()[i]
- if rowsense()[i] != 'R' then rowrange()[i] is 0.0

Implements OsiSolverInterface.

```
7.35.2.5 virtual int OsiSpxSolverInterface::getIterationCount() const [virtual]
```

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

Implements OsiSolverInterface.

```
7.35.2.6 virtual std::vector<double*> OsiSpxSolverInterface::getDualRays ( int maxNumRays, bool fullRay = false ) const [virtual]
```

Get as many dual rays as the solver can provide.

(In case of proven primal infeasibility there should be at least one.)

The first getNumRows() ray components will always be associated with the row duals (as returned by getRowPrice()). If fullRay is true, the final getNumCols() entries will correspond to the ray components associated with the nonbasic variables. If the full ray is requested and the method cannot provide it, it will throw an exception.

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumRows() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

```
7.35.2.7 virtual std::vector<double*> OsiSpxSolverInterface::getPrimalRays ( int maxNumRays ) const [virtual]
```

Get as many primal rays as the solver can provide.

(In case of proven dual infeasibility there should be at least one.)

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumCols() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

```
7.35.2.8 virtual void OsiSpxSolverInterface::setColLower( int elementIndex, double elementValue ) [virtual]
```

Set a single column lower bound

Use -COIN_DBL_MAX for -infinity.

Implements OsiSolverInterface.

```
7.35.2.9 virtual void OsiSpxSolverInterface::setColUpper(int elementIndex, double elementValue) [virtual]
```

Set a single column upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.35.2.10 virtual void OsiSpxSolverInterface::setRowLower(int elementIndex, double elementValue) [virtual]

Set a single row lower bound

Use -COIN DBL MAX for -infinity.

Implements OsiSolverInterface.

7.35.2.11 virtual void OsiSpxSolverInterface::setRowUpper(int elementIndex, double elementValue) [virtual]

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.35.2.12 virtual void OsiSpxSolverInterface::setColSolution (const double * colsol) [virtual]

Set the primal solution column values.

colsol[numcols()] is an array of values of the problem column variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of colsol() until changed by another call to setColsol() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.35.2.13 virtual void OsiSpxSolverInterface::setRowPrice (const double * rowprice) [virtual]

Set dual solution vector.

rowprice[numrows()] is an array of values of the problem row dual variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of rowprice() until changed by another call to setRowprice() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.35.2.14 virtual void OsiSpxSolverInterface::addCol (const CoinPackedVectorBase & vec, const double collb, const double collb, const double obj) [virtual]

Add a column (primal variable) to the problem.

Implements OsiSolverInterface.

7.35.2.15 virtual void OsiSpxSolverInterface::deleteCols (const int num, const int * colIndices) [virtual]

Remove a set of columns (primal variables) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted variables are nonbasic.

Implements OsiSolverInterface.

7.35.2.16 virtual void OsiSpxSolverInterface::addRow (const CoinPackedVectorBase & vec, const double rowlb, const double rowub) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.35.2.17 virtual void OsiSpxSolverInterface::addRow (const CoinPackedVectorBase & vec, const char rowsen, const double rowrng) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.35.2.18 virtual void OsiSpxSolverInterface::deleteRows (const int num, const int * rowIndices) [virtual]

Delete a set of rows (constraints) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted rows are loose. Implements OsiSolverInterface.

7.35.2.19 virtual void OsiSpxSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowlb, const double * rowlb) [virtual]

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds). If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- rowub: all rows have upper bound infinity
- rowlb: all rows have lower bound -infinity
- obj: all variables have 0 objective coefficient

Implements OsiSolverInterface.

7.35.2.20 virtual void OsiSpxSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& rowlb, double *& rowlb) [virtual]

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

```
7.35.2.21 virtual void OsiSpxSolverInterface::loadProblem ( const CoinPackedMatrix & matrix, const double * collb, const double * colub, const double * colub, const double * rowrns, const double * rowrns, const double * rowrns )

[virtual]
```

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets). If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- obj: all variables have 0 objective coefficient
- rowsen: all rows are >=

- rowrhs: all right hand sides are 0
- rowrng: 0 for the ranged rows

Implements OsiSolverInterface.

7.35.2.22 virtual void OsiSpxSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowrhs, double *& rowrng) [virtual]

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

7.35.2.23 virtual void OsiSpxSolverInterface::loadProblem (const int *numcols*, const int *numrows*, const int * *start*, const int * *index*, const double * *value*, const double * *collb*, const double * *colub*, const double * *obj*, const double * *rowub*) [virtual]

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

7.35.2.25 virtual void OsiSpxSolverInterface::writeMps (const char * filename, const char * extension = "mps", double objSense = 0.0) const [virtual]

Write the problem into an mps file of the given filename.

If objSense is non zero then -1.0 forces the code to write a maximization objective and +1.0 to write a minimization one. If 0.0 then solver can do what it wants

Implements OsiSolverInterface.

7.35.2.26 virtual void OsiSpxSolverInterface::applyColCut (const OsiColCut & cc) [protected], [virtual]

Apply a column cut (bound adjustment).

Return true if cut was applied.

Implements OsiSolverInterface.

7.35.3 Friends And Related Function Documentation

7.35.3.1 void OsiSpxSolverInterfaceUnitTest (const std::string & mpsDir, const std::string & netlibDir) [friend]

A function that tests the methods in the OsiSpxSolverInterface class.

The documentation for this class was generated from the following file:


OsiSpxSolverInterface.hpp

7.36 OsiTwoWayBranchingObject Class Reference


This just adds two-wayness to a branching object.

#include <OsiBranchingObject.hpp>

Inheritance diagram for OsiTwoWayBranchingObject:



Collaboration diagram for OsiTwoWayBranchingObject:



Public Member Functions

- OsiTwoWayBranchingObject ()
 - Default constructor.
- OsiTwoWayBranchingObject (OsiSolverInterface *solver, const OsiObject *originalObject, int way, double value)
 - Create a standard tw0-way branch object.
- OsiTwoWayBranchingObject (const OsiTwoWayBranchingObject &)

Copy constructor.

OsiTwoWayBranchingObject & operator= (const OsiTwoWayBranchingObject &rhs)

Assignment operator.

virtual ~OsiTwoWayBranchingObject ()

Destructor.

virtual double branch (OsiSolverInterface *solver)=0

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next arm.

· int way () const

Way returns -1 on down +1 on up.

Protected Attributes

int firstBranch

Which way was first branch -1 = down, +1 = up.

7.36.1 Detailed Description

This just adds two-wayness to a branching object.

Definition at line 467 of file OsiBranchingObject.hpp.

7.36.2 Constructor & Destructor Documentation

7.36.2.1 OsiTwoWayBranchingObject::OsiTwoWayBranchingObject (OsiSolverInterface * solver, const OsiObject * originalObject, int way, double value)

Create a standard tw0-way branch object.

Specifies a simple two-way branch. Specify way = -1 to set the object state to perform the down arm first, way = 1 for the up arm.

7.36.3 Member Function Documentation

7.36.3.1 virtual double OsiTwoWayBranchingObject::branch (OsiSolverInterface * solver) [pure virtual]

Sets the bounds for the variable according to the current arm of the branch and advances the object state to the next

state. Returns change in guessed objective on next branch

Implements OsiBranchingObject.

Implemented in OsiLotsizeBranchingObject, OsiSOSBranchingObject, and OsiIntegerBranchingObject.

The documentation for this class was generated from the following file:


OsiBranchingObject.hpp

7.37 OsiXprSolverInterface Class Reference

XPRESS-MP Solver Interface.

#include <OsiXprSolverInterface.hpp>

Inheritance diagram for OsiXprSolverInterface:



Collaboration diagram for OsiXprSolverInterface:



Public Member Functions

virtual void setObjSense (double s)

Set objective function sense (1 for min (default), -1 for max,)

virtual void setColSolution (const double *colsol)

Set the primal solution column values.

virtual void setRowPrice (const double *rowprice)

Set dual solution vector.

Solve methods

• virtual void initialSolve ()

Solve initial LP relaxation.

• virtual void resolve ()

Resolve an LP relaxation after problem modification.

virtual void branchAndBound ()

Invoke solver's built-in enumeration algorithm.

Parameter set/get methods

The set methods return true if the parameter was set to the given value, false otherwise.

There can be various reasons for failure: the given parameter is not applicable for the solver (e.g., refactorization frequency for the volume algorithm), the parameter is not yet implemented for the solver or simply the value of the

parameter is out of the range the solver accepts. If a parameter setting call returns false check the details of your solver.

The get methods return true if the given parameter is applicable for the solver and is implemented. In this case the value of the parameter is returned in the second argument. Otherwise they return false.

bool setIntParam (OsiIntParam key, int value)

Set an integer parameter.

bool setDblParam (OsiDblParam key, double value)

Set a double parameter.

bool setStrParam (OsiStrParam key, const std::string &value)

Set a string parameter.

• bool getIntParam (OsiIntParam key, int &value) const

Get an integer parameter.

• bool getDblParam (OsiDblParam key, double &value) const

Get a double parameter.

• bool getStrParam (OsiStrParam key, std::string &value) const

Get a string parameter.

- void setMipStart (bool value)
- bool getMipStart () const

Methods returning info on how the solution process terminated

· virtual bool isAbandoned () const

Are there a numerical difficulties?

virtual bool isProvenOptimal () const

Is optimality proven?

virtual bool isProvenPrimalInfeasible () const

Is primal infeasiblity proven?

• virtual bool isProvenDualInfeasible () const

Is dual infeasiblity proven?

virtual bool isPrimalObjectiveLimitReached () const

Is the given primal objective limit reached?

virtual bool isDualObjectiveLimitReached () const

Is the given dual objective limit reached?

· virtual bool isIterationLimitReached () const

Iteration limit reached?

WarmStart related methods

CoinWarmStart * getEmptyWarmStart () const

Get empty warm start object.

• virtual CoinWarmStart * getWarmStart () const

Get warmstarting information.

virtual bool setWarmStart (const CoinWarmStart *warmstart)

Set warmstarting information.

Hotstart related methods (primarily used in strong branching).

 tr>

The user can create a hotstart (a snapshot) of the optimization process then reoptimize over and over again always starting from there.

NOTE: between hotstarted optimizations only bound changes are allowed.

virtual void markHotStart ()

Create a hotstart point of the optimization process.

virtual void solveFromHotStart ()

Optimize starting from the hotstart.

virtual void unmarkHotStart ()

Delete the snapshot.

Methods related to querying the input data

virtual int getNumCols () const

Get number of columns.

virtual int getNumRows () const

Get number of rows.

virtual int getNumElements () const

Get number of nonzero elements.

virtual const double * getColLower () const

Get pointer to array[getNumCols()] of column lower bounds.

virtual const double * getColUpper () const

Get pointer to array[getNumCols()] of column upper bounds.

virtual const char * getRowSense () const

Get pointer to array[getNumRows()] of row constraint senses.

virtual const double * getRightHandSide () const

Get pointer to array[getNumRows()] of rows right-hand sides.

virtual const double * getRowRange () const

Get pointer to array[getNumRows()] of row ranges.

virtual const double * getRowLower () const

Get pointer to array[getNumRows()] of row lower bounds.

virtual const double * getRowUpper () const

Get pointer to array[getNumRows()] of row upper bounds.

virtual const double * getObjCoefficients () const

Get pointer to array[getNumCols()] of objective function coefficients.

• virtual double getObjSense () const

Get objective function sense (1 for min (default), -1 for max)

virtual bool isContinuous (int colIndex) const

Return true if variable is continuous.

virtual const CoinPackedMatrix * getMatrixByRow () const

Get pointer to row-wise copy of matrix.

virtual const CoinPackedMatrix * getMatrixByCol () const

Get pointer to column-wise copy of matrix.

· virtual double getInfinity () const

Get solver's value for infinity.

Methods related to querying the solution

virtual const double * getColSolution () const

Get pointer to array[getNumCols()] of primal solution vector.

virtual const double * getRowPrice () const

Get pointer to array[getNumRows()] of dual prices.

virtual const double * getReducedCost () const

Get a pointer to array[getNumCols()] of reduced costs.

virtual const double * getRowActivity () const

Get pointer to array[getNumRows()] of row activity levels (constraint matrix times the solution vector.

virtual double getObjValue () const

Get objective function value.

virtual int getIterationCount () const

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

• virtual std::vector< double * > getDualRays (int maxNumRays, bool fullRay=false) const

Get as many dual rays as the solver can provide.

virtual std::vector< double * > getPrimalRays (int maxNumRays) const

Get as many primal rays as the solver can provide.

Changing bounds on variables and constraints

virtual void setObjCoeff (int elementIndex, double elementValue)

Set an objective function coefficient.

• virtual void setColLower (int elementIndex, double elementValue)

Set a single column lower bound

Use -COIN_DBL_MAX for -infinity.

virtual void setColUpper (int elementIndex, double elementValue)

Set a single column upper bound

Use COIN_DBL_MAX for infinity.

virtual void setColBounds (int elementIndex, double lower, double upper)

Set a single column lower and upper bound

The default implementation just invokes setColLower() and setColUpper()

virtual void setColSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of columns simultaneously

The default implementation just invokes setColLower() and setColUpper() over and over again.

virtual void setRowLower (int elementIndex, double elementValue)

Set a single row lower bound

Use -COIN DBL MAX for -infinity.

virtual void setRowUpper (int elementIndex, double elementValue)

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

virtual void setRowBounds (int elementIndex, double lower, double upper)

Set a single row lower and upper bound

The default implementation just invokes setRowLower() and setRowUpper()

virtual void setRowType (int index, char sense, double rightHandSide, double range)

Set the type of a single row

virtual void setRowSetBounds (const int *indexFirst, const int *indexLast, const double *boundList)

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

 virtual void setRowSetTypes (const int *indexFirst, const int *indexLast, const char *senseList, const double *rhsList, const double *rangeList)

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType() over and over again.

Integrality related changing methods

virtual void setContinuous (int index)

Set the index-th variable to be a continuous variable.

virtual void setInteger (int index)

Set the index-th variable to be an integer variable.

virtual void setContinuous (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be continuous variables.

• virtual void setInteger (const int *indices, int len)

Set the variables listed in indices (which is of length len) to be integer variables.

Methods to expand a problem.

Note that if a column is added then by default it will correspond to a continuous variable.

virtual void addCol (const CoinPackedVectorBase &vec, const double collb, const double colub, const double obj)

Add a column (primal variable) to the problem.

virtual void addCols (const int numcols, const CoinPackedVectorBase *const *cols, const double *collb, const double *collb, const double *obj)

Add a set of columns (primal variables) to the problem.

virtual void deleteCols (const int num, const int *colIndices)

Remove a set of columns (primal variables) from the problem.

virtual void addRow (const CoinPackedVectorBase &vec, const double rowlb, const double rowlb)

Add a row (constraint) to the problem.

 virtual void addRow (const CoinPackedVectorBase &vec, const char rowsen, const double rowrhs, const double rowrng)

Add a row (constraint) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const double *rowlb, const double *rowub)

Add a set of rows (constraints) to the problem.

virtual void addRows (const int numrows, const CoinPackedVectorBase *const *rows, const char *rowsen, const double *rowrhs, const double *rowrng)

Add a set of rows (constraints) to the problem.

virtual void deleteRows (const int num, const int *rowIndices)

Delete a set of rows (constraints) from the problem.

Methods to input a problem

virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowlb, const double *rowlb)

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds).

virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&colub, double *&rowlb, double *&rowlb)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

• virtual void loadProblem (const CoinPackedMatrix &matrix, const double *collb, const double *collb, const double *collb, const double *rowrng)

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

 virtual void assignProblem (CoinPackedMatrix *&matrix, double *&collb, double *&colub, double *&obj, char *&rowsen, double *&rowrhs, double *&rowrng)

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *collb, const double *rowlb, const double *rowlb, const double *rowlb

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

 virtual void loadProblem (const int numcols, const int numrows, const int *start, const int *index, const double *value, const double *collb, const double *colub, const double *obj, const char *rowsen, const double *rowrhs, const double *rowrng)

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

virtual int readMps (const char *filename, const char *extension="mps")

Read an mps file from the given filename.

• virtual void writeMps (const char *filename, const char *extension="mps", double objSense=0.0) const Write the problem into an mps file of the given filename.

Message handling

void passInMessageHandler (CoinMessageHandler *handler)

Pass in a message handler It is the client's responsibility to destroy a message handler installed by this routine; it will not be destroyed when the solver interface is destroyed.

Constructors and destructors

OsiXprSolverInterface (int newrows=50, int newnz=100)

Default Constructor.

• virtual OsiSolverInterface * clone (bool copyData=true) const

Clone

• OsiXprSolverInterface (const OsiXprSolverInterface &)

Copy constructor.

OsiXprSolverInterface & operator= (const OsiXprSolverInterface &rhs)

Assignment operator.

virtual ~OsiXprSolverInterface ()

Destructor.

Static Public Member Functions

• static int version ()

Return XPRESS-MP Version number.

Protected Member Functions

Protected methods

virtual void applyRowCut (const OsiRowCut &rc)

Apply a row cut. Return true if cut was applied.

virtual void applyColCut (const OsiColCut &cc)

Apply a column cut (bound adjustment).

Friends

void OsiXprSolverInterfaceUnitTest (const std::string &mpsDir, const std::string &netlibDir)

A function that tests the methods in the OsiXprSolverInterface class.

Static instance counter methods

XPRSprob getLpPtr ()

Return a pointer to the XPRESS problem.

static void incrementInstanceCounter ()

XPRESS has a context that must be created prior to all other XPRESS calls.

static void decrementInstanceCounter ()

XPRESS has a context that should be deleted after XPRESS calls.

• static unsigned int getNumInstances ()

Return the number of instances of instantiated objects using XPRESS services.

Log File

```
    static int iXprCallCount
```

static FILE * getLogFilePtr ()

Get logfile FILE *.

static void setLogFileName (const char *filename)

Set logfile name.

Additional Inherited Members

7.37.1 Detailed Description

XPRESS-MP Solver Interface.

Instantiation of OsiSolverInterface for XPRESS-MP

Definition at line 21 of file OsiXprSolverInterface.hpp.

7.37.2 Member Function Documentation

7.37.2.1 virtual bool OsiXprSolverInterface::setWarmStart (const CoinWarmStart * warmstart) [virtual]

Set warmstarting information.

Return true/false depending on whether the warmstart information was accepted or not.

Implements OsiSolverInterface.

7.37.2.2 virtual const char* OsiXprSolverInterface::getRowSense() const [virtual]

Get pointer to array[getNumRows()] of row constraint senses.

- 'L': <= constraint
- 'E': = constraint
- 'G': >= constraint
- · 'R': ranged constraint
- · 'N': free constraint

Implements OsiSolverInterface.

7.37.2.3 virtual const double* OsiXprSolverInterface::getRightHandSide() const [virtual]

Get pointer to array[getNumRows()] of rows right-hand sides.

- if rowsense()[i] == 'L' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'G' then rhs()[i] == rowlower()[i]
- if rowsense()[i] == 'R' then rhs()[i] == rowupper()[i]
- if rowsense()[i] == 'N' then rhs()[i] == 0.0

Implements OsiSolverInterface.

7.37.2.4 virtual const double* OsiXprSolverInterface::getRowRange() const [virtual]

Get pointer to array[getNumRows()] of row ranges.

- if rowsense()[i] == 'R' then rowrange()[i] == rowupper()[i] rowlower()[i]
- if rowsense()[i] != 'R' then rowrange()[i] is 0.0

Implements OsiSolverInterface.

```
7.37.2.5 virtual int OsiXprSolverInterface::getIterationCount() const [virtual]
```

Get how many iterations it took to solve the problem (whatever "iteration" mean to the solver.

Implements OsiSolverInterface.

```
7.37.2.6 virtual std::vector<double*> OsiXprSolverInterface::getDualRays ( int maxNumRays, bool fullRay = false ) const [virtual]
```

Get as many dual rays as the solver can provide.

(In case of proven primal infeasibility there should be at least one.)

The first getNumRows() ray components will always be associated with the row duals (as returned by getRowPrice()). If fullRay is true, the final getNumCols() entries will correspond to the ray components associated with the nonbasic variables. If the full ray is requested and the method cannot provide it, it will throw an exception.

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumRows() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

```
7.37.2.7 virtual std::vector<double*> OsiXprSolverInterface::getPrimalRays ( int maxNumRays ) const [virtual]
```

Get as many primal rays as the solver can provide.

(In case of proven dual infeasibility there should be at least one.)

NOTE for implementers of solver interfaces:

The double pointers in the vector should point to arrays of length getNumCols() and they should be allocated via new[].

NOTE for users of solver interfaces:

It is the user's responsibility to free the double pointers in the vector using delete[].

Implements OsiSolverInterface.

```
7.37.2.8 virtual void OsiXprSolverInterface::setColLower( int elementIndex, double elementValue ) [virtual]
```

Set a single column lower bound

Use -COIN_DBL_MAX for -infinity.

Implements OsiSolverInterface.

7.37.2.9 virtual void OsiXprSolverInterface::setColUpper(int elementIndex, double elementValue) [virtual]

Set a single column upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.37.2.10 virtual void OsiXprSolverInterface::setColSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of columns simultaneously

The default implementation just invokes setColLower() and setColUpper() over and over again.

Parameters

i	indexFirst,index-	pointers to the beginning and after the end of the array of the indices of the variables whose either
	Last	bound changes
	boundList	the new lower/upper bound pairs for the variables

Reimplemented from OsiSolverInterface.

7.37.2.11 virtual void OsiXprSolverInterface::setRowLower(int elementIndex, double elementValue) [virtual]

Set a single row lower bound

Use -COIN DBL MAX for -infinity.

Implements OsiSolverInterface.

7.37.2.12 virtual void OsiXprSolverInterface::setRowUpper(int elementIndex, double elementValue) [virtual]

Set a single row upper bound

Use COIN_DBL_MAX for infinity.

Implements OsiSolverInterface.

7.37.2.13 virtual void OsiXprSolverInterface::setRowSetBounds (const int * indexFirst, const int * indexLast, const double * boundList) [virtual]

Set the bounds on a number of rows simultaneously

The default implementation just invokes setRowLower() and setRowUpper() over and over again.

Parameters

indexFirst,index-	pointers to the beginning and after the end of the array of the indices of the constraints whose
Last	either bound changes
boundList	the new lower/upper bound pairs for the constraints

Reimplemented from OsiSolverInterface.

7.37.2.14 virtual void OsiXprSolverInterface::setRowSetTypes (const int * indexFirst, const int * indexLast, const char * senseList, const double * rhsList, const double * rangeList) [virtual]

Set the type of a number of rows simultaneously

The default implementation just invokes setRowType() over and over again.

Parameters

indexFirst,index-	pointers to the beginning and after the end of the array of the indices of the constraints whose any
Last	characteristics changes

senseList	the new senses
rhsList	the new right hand sides
rangeList	the new ranges

Reimplemented from OsiSolverInterface.

7.37.2.15 virtual void OsiXprSolverInterface::setColSolution (const double * colsol) [virtual]

Set the primal solution column values.

colsol[numcols()] is an array of values of the problem column variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of colsol() until changed by another call to setColsol() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.37.2.16 virtual void OsiXprSolverInterface::setRowPrice (const double * rowprice) [virtual]

Set dual solution vector.

rowprice[numrows()] is an array of values of the problem row dual variables. These values are copied to memory owned by the solver object or the solver. They will be returned as the result of rowprice() until changed by another call to setRowprice() or by a call to any solver routine. Whether the solver makes use of the solution in any way is solver-dependent.

Implements OsiSolverInterface.

7.37.2.17 virtual void OsiXprSolverInterface::addCol (const CoinPackedVectorBase & vec, const double collb, const double collb, const double obj) [virtual]

Add a column (primal variable) to the problem.

Implements OsiSolverInterface.

7.37.2.18 virtual void OsiXprSolverInterface::addCols (const int *numcols*, const CoinPackedVectorBase *const * cols, const double * collb, const double * collb, const double * obj) [virtual]

Add a set of columns (primal variables) to the problem.

The default implementation simply makes repeated calls to addCol().

Reimplemented from OsiSolverInterface.

7.37.2.19 virtual void OsiXprSolverInterface::deleteCols (const int num, const int * colIndices) [virtual]

Remove a set of columns (primal variables) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted variables are nonbasic.

Implements OsiSolverInterface.

7.37.2.20 virtual void OsiXprSolverInterface::addRow(const CoinPackedVectorBase & vec, const double rowlb, const double rowlb) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.37.2.21 virtual void OsiXprSolverInterface::addRow (const CoinPackedVectorBase & vec, const char rowsen, const double rowrng) [virtual]

Add a row (constraint) to the problem.

Implements OsiSolverInterface.

7.37.2.22 virtual void OsiXprSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * rows, const double * rowlb, const double * rowub) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.37.2.23 virtual void OsiXprSolverInterface::addRows (const int *numrows*, const CoinPackedVectorBase *const * *rows*, const char * *rowsen*, const double * *rowrhs*, const double * *rowrng*) [virtual]

Add a set of rows (constraints) to the problem.

The default implementation simply makes repeated calls to addRow().

Reimplemented from OsiSolverInterface.

7.37.2.24 virtual void OsiXprSolverInterface::deleteRows (const int num, const int * rowIndices) [virtual]

Delete a set of rows (constraints) from the problem.

The solver interface for a basis-oriented solver will maintain valid warm start information if all deleted rows are loose. Implements OsiSolverInterface.

7.37.2.25 virtual void OsiXprSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * collb, const double * rowlb, const double * rowlb, const double * rowlb) [virtual]

Load in an problem by copying the arguments (the constraints on the rows are given by lower and upper bounds). If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- rowub: all rows have upper bound infinity
- rowlb: all rows have lower bound -infinity
- obj: all variables have 0 objective coefficient

Implements OsiSolverInterface.

7.37.2.26 virtual void OsiXprSolverInterface::assignProblem (CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowlb, double *& rowlb, double *& rowlb) [virtual]

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by lower and upper bounds).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

7.37.2.27 virtual void OsiXprSolverInterface::loadProblem (const CoinPackedMatrix & matrix, const double * collb, const double * colub, const double * const double * rowrng, const double * rowrng, const double * rowrng)

[virtual]

Load in an problem by copying the arguments (the constraints on the rows are given by sense/rhs/range triplets).

If a pointer is 0 then the following values are the default:

- colub: all columns have upper bound infinity
- collb: all columns have lower bound 0
- obj: all variables have 0 objective coefficient
- rowsen: all rows are >=
- rowrhs: all right hand sides are 0
- rowrng: 0 for the ranged rows

Implements OsiSolverInterface.

```
7.37.2.28 virtual void OsiXprSolverInterface::assignProblem ( CoinPackedMatrix *& matrix, double *& collb, double *& collb, double *& collb, double *& rowrng ) [virtual]
```

Load in an problem by assuming ownership of the arguments (the constraints on the rows are given by sense/rhs/range triplets).

For default values see the previous method.

WARNING: The arguments passed to this method will be freed using the C++ delete and delete[] functions. Implements OsiSolverInterface.

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

```
7.37.2.30 virtual void OsiXprSolverInterface::loadProblem ( const int numcols, const int numrows, const int * start, const int * index, const double * value, const double * collb, const double * colub, const double * obj, const char * rowsen, const double * rowrhs, const double * rowrng ) [virtual]
```

Just like the other loadProblem() methods except that the matrix is given in a standard column major ordered format (without gaps).

```
7.37.2.31 virtual void OsiXprSolverInterface::writeMps ( const char * filename, const char * extension = "mps", double objSense = 0.0 ) const [virtual]
```

Write the problem into an mps file of the given filename.

If objSense is non zero then -1.0 forces the code to write a maximization objective and +1.0 to write a minimization one. If 0.0 then solver can do what it wants

Implements OsiSolverInterface.

```
7.37.2.32 static void OsiXprSolverInterface::incrementInstanceCounter() [static]
```

XPRESS has a context that must be created prior to all other XPRESS calls.

This method:

- Increments by 1 the number of uses of the XPRESS environment.
- Creates the XPRESS context when the number of uses is changed to 1 from 0.

7.37.2.33 static void OsiXprSolverInterface::decrementInstanceCounter() [static]

XPRESS has a context that should be deleted after XPRESS calls.

This method:

- Decrements by 1 the number of uses of the XPRESS environment.
- Deletes the XPRESS context when the number of uses is change to 0 from 1.

7.37.2.34 static unsigned int OsiXprSolverInterface::getNumInstances() [static]

Return the number of instances of instantiated objects using XPRESS services.

7.37.2.35 static void OsiXprSolverInterface::setLogFileName (const char * filename) [static]

Set logfile name.

The logfile is an attempt to capture the calls to Xpress functions for debugging.

7.37.2.36 virtual void OsiXprSolverInterface::applyColCut (const OsiColCut & cc) [protected], [virtual]

Apply a column cut (bound adjustment).

Return true if cut was applied.

Implements OsiSolverInterface.

7.37.3 Friends And Related Function Documentation

7.37.3.1 void OsiXprSolverInterfaceUnitTest (const std::string & mpsDir, const std::string & netlibDir) [friend]

A function that tests the methods in the OsiXprSolverInterface class.

The documentation for this class was generated from the following file:


OsiXprSolverInterface.hpp

7.38 OsiUnitTest::TestOutcome Class Reference

A single test outcome record.

#include <OsiUnitTests.hpp>

Collaboration diagram for OsiUnitTest::TestOutcome:



Public Types

· enum SeverityLevel

Test result.

Public Member Functions

• TestOutcome (const std::string &comp, const std::string &tst, const char *cond, SeverityLevel sev, const char *file, int line, bool exp=false)

Standard constructor.

• void print () const

Print the test outcome.

Public Attributes

std::string component

Name of component under test.

• std::string testname

Name of test.

• std::string testcond

Condition being tested.

· SeverityLevel severity

Test result.

· bool expected

Set to true if problem is expected.

· std::string filename

Name of code file where test executed.

· int linenumber

Line number in code file where test executed.

Static Public Attributes

• static std::string SeverityLevelName [LAST] Print strings for SeverityLevel.

7.38.1 Detailed Description

A single test outcome record.

Definition at line 166 of file OsiUnitTests.hpp.

The documentation for this class was generated from the following file:


OsiUnitTests.hpp

7.39 OsiUnitTest::TestOutcomes Class Reference


Utility class to maintain a list of test outcomes.

#include <OsiUnitTests.hpp>

Inheritance diagram for OsiUnitTest::TestOutcomes:



Collaboration diagram for OsiUnitTest::TestOutcomes:



Public Member Functions

• void add (std::string comp, std::string tst, const char *cond, TestOutcome::SeverityLevel sev, const char *file, int line, bool exp=false)

Add an outcome to the list.

• void add (const OsiSolverInterface &si, std::string tst, const char *cond, TestOutcome::SeverityLevel sev, const char *file, int line, bool exp=false)

Add an outcome to the list.

· void print () const

Print the list of outcomes.

• void getCountBySeverity (TestOutcome::SeverityLevel sev, int &total, int &expected) const Count total and expected outcomes at given severity level.

Additional Inherited Members

7.39.1 Detailed Description

Utility class to maintain a list of test outcomes.

Definition at line 204 of file OsiUnitTests.hpp.

7.39.2 Member Function Documentation

7.39.2.1 void OsiUnitTest::TestOutcomes::add (const OsiSolverInterface & si, std::string tst, const char * cond, TestOutcome::SeverityLevel sev, const char * file, int line, bool exp = false)

Add an outcome to the list.

Get the component name from the solver interface.

8 File Documentation 199

7.39.2.2 void OsiUnitTest::TestOutcomes::getCountBySeverity (TestOutcome::SeverityLevel sev, int & total, int & expected) const

Count total and expected outcomes at given severity level.

Given a severity level, walk the list of outcomes and count the total number of outcomes at this severity level and the number expected.

The documentation for this class was generated from the following file:


OsiUnitTests.hpp

8 File Documentation

8.1 OsiRowCutDebugger.hpp File Reference

Provides a facility to validate cut constraints to ensure that they do not cut off a given solution.

```
#include <string>
#include "OsiCuts.hpp"
#include "OsiSolverInterface.hpp"
Include dependency graph for OsiRowCutDebugger.hpp:
```



Classes

· class OsiRowCutDebugger

Validate cuts against a known solution.

8.1.1 Detailed Description

Provides a facility to validate cut constraints to ensure that they do not cut off a given solution.


Definition in file OsiRowCutDebugger.hpp.

8.2 OsiUnitTests.hpp File Reference

Utility methods for OSI unit tests.

```
#include <cstdio>
#include <cstdlib>
#include <iostream>
#include <string>
#include <sstream>
#include <vector>
#include <list>
#include <map>
```

Include dependency graph for OsiUnitTests.hpp:



Classes

class OsiUnitTest::TestOutcome

A single test outcome record.

class OsiUnitTest::TestOutcomes

Utility class to maintain a list of test outcomes.

Namespaces

namespace OsiUnitTest

A namespace so we can define a few 'global' variables to use during tests.

Macros

#define OSIUNITTEST_QUOTEME_(x) #x

Convert parameter to a string (stringification)

#define OSIUNITTEST_QUOTEME(x) OSIUNITTEST_QUOTEME_(x)

Convert to string with one level of expansion of the parameter.

#define OSIUNITTEST_ADD_OUTCOME(component, testname, testcondition, severity, expected)

Add a test outcome to the list held in OsiUnitTest::outcomes.

 #define OSIUNITTEST_ASSERT_SEVERITY_EXPECTED(condition, failurecode, component, testname, severity, expected)

Test for a condition and record the result.

• #define OSIUNITTEST ASSERT ERROR(condition, failurecode, component, testname)

Perform a test with severity OsiUnitTest::TestOutcome::ERROR, failure not expected.

#define OSIUNITTEST ASSERT WARNING(condition, failurecode, component, testname)

Perform a test with severity OsiUnitTest::TestOutcome::WARNING, failure not expected.

#define OSIUNITTEST_CATCH_SEVERITY_EXPECTED(trycode, catchcode, component, testname, severity, expected)

Perform a test surrounded by a try/catch block.

 #define OSIUNITTEST_CATCH_ERROR(trycode, catchcode, component, testname) OSIUNITTEST_CATCH_-SEVERITY_EXPECTED(trycode, catchcode, component, testname, OsiUnitTest::TestOutcome::ERROR, false)

Perform a try/catch test with severity OsiUnitTest::TestOutcome::ERROR, failure not expected.

 #define OSIUNITTEST_CATCH_WARNING(trycode, catchcode, component, testname) OSIUNITTEST_CATC-H_SEVERITY_EXPECTED(trycode, catchcode, component, testname, OsiUnitTest::TestOutcome::WARNING, false)

Perform a try/catch test with severity OsiUnitTest::TestOutcome::WARNING, failure not expected.

Functions

void OsiSolverInterfaceMpsUnitTest (const std::vector< OsiSolverInterface * > &vecEmptySiP, const std::string &mpsDir)

A function that tests that a lot of problems given in MPS files (mostly the NETLIB problems) solve properly with all the specified solvers.

 void OsiSolverInterfaceCommonUnitTest (const OsiSolverInterface *emptySi, const std::string &mpsDir, const std::string &netlibDir)

A function that tests the methods in the OsiSolverInterface class.

void OsiColCutUnitTest (const OsiSolverInterface *baseSiP, const std::string &mpsDir)

A function that tests the methods in the OsiColCut class.

void OsiRowCutUnitTest (const OsiSolverInterface *baseSiP, const std::string &mpsDir)

A function that tests the methods in the OsiRowCut class.

void OsiRowCutDebuggerUnitTest (const OsiSolverInterface *siP, const std::string &mpsDir)

A function that tests the methods in the OsiRowCutDebugger class.

void OsiCutsUnitTest ()

A function that tests the methods in the OsiCuts class.

void OsiUnitTest::failureMessage (const std::string &solverName, const std::string &message)

Print an error message.

- void OsiUnitTest::failureMessage (const OsiSolverInterface &si, const std::string &message)
- void OsiUnitTest::failureMessage (const std::string &solverName, const std::string &testname, const std::string &testna

Print an error message, specifying the test name and condition.

- void OsiUnitTest::failureMessage (const OsiSolverInterface &si, const std::string &testname, const std::string &testcond)
- void OsiUnitTest::testingMessage (const char *const msg)

Print a message.

• bool OsiUnitTest::equivalentVectors (const OsiSolverInterface *si1, const OsiSolverInterface *si2, double tol, const double *v1, const double *v2, int size)

Utility method to check equality.

bool OsiUnitTest::compareProblems (OsiSolverInterface *osi1, OsiSolverInterface *osi2)

Compare two problems for equality.

bool OsiUnitTest::isEquivalent (const CoinPackedVectorBase &pv, int n, const double *fv)

Compare a packed vector with an expanded vector.

bool OsiUnitTest::processParameters (int argc, const char **argv, std::map< std::string, std::string > &parms, const std::map< std::string, int > &ignorekeywords=std::map< std::string, int >())

Process command line parameters.

Variables

- unsigned int OsiUnitTest::verbosity
 - Verbosity level of unit tests.
- · unsigned int OsiUnitTest::haltonerror
 - Behaviour on failing a test.
- TestOutcomes OsiUnitTest::outcomes

Test outcomes.

8.2.1 Detailed Description

Utility methods for OSI unit tests.

Definition in file OsiUnitTests.hpp.

- 8.2.2 Macro Definition Documentation
- 8.2.2.1 #define OSIUNITTEST_ASSERT_SEVERITY_EXPECTED(condition, failurecode, component, testname, severity, expected)

Value:

```
{
   if (!OsiUnitTestAssertSeverityExpected(condition, #condition, \
        __FILE__, __LINE__, component, testname, severity, expected)) { \
      failurecode; \
   } \
}
```

Test for a condition and record the result.

Test condition and record the result in OsiUnitTest::outcomes. If it succeeds, record the result as OsiUnitTest::TestOutcome::PASSED and print a message for OsiUnitTest::verbosity >= 2. If it fails, record the test as failed with severity and expected and react as specified by OsiUnitTest::haltonerror.

failurecode is executed when failure is not fatal.

Definition at line 281 of file OsiUnitTests.hpp.

8.2.2.2 #define OSIUNITTEST_CATCH_SEVERITY_EXPECTED(trycode, catchcode, component, testname, severity, expected)

Perform a test surrounded by a try/catch block.

trycode is executed in a try/catch block; if there's no throw the test is deemed to have succeeded and is recorded in OsiUnitTest::outcomes with status OsiUnitTest::TestOutcome::PASSED. If the trycode throws a CoinError, the failure is recorded with status severity and expected and the value of OsiUnitTest::haltonerror is consulted. If the failure is not fatal, catchcode is executed. If any other error is thrown, the failure is recorded as for a CoinError and catchcode is executed (haltonerror is not consulted).

Definition at line 314 of file OsiUnitTests.hpp.

8.2.3 Function Documentation

8.2.3.1 void OsiSolverInterfaceMpsUnitTest (const std::vector< OsiSolverInterface * > & vecEmptySiP, const std::string & mpsDir)

A function that tests that a lot of problems given in MPS files (mostly the NETLIB problems) solve properly with all the specified solvers.

The routine creates a vector of NetLib problems (problem name, objective, various other characteristics), and a vector of solvers to be tested.

Each solver is run on each problem. The run is deemed successful if the solver reports the correct problem size after loading and returns the correct objective value after optimization.

If multiple solvers are available, the results are compared pairwise against the results reported by adjacent solvers in the solver vector. Due to limitations of the volume solver, it must be the last solver in vecEmptySiP.

8.2.3.2 void OsiSolverInterfaceCommonUnitTest (const OsiSolverInterface * emptySi, const std::string & mpsDir, const std::string & netlibDir)

A function that tests the methods in the OsiSolverInterface class.

Some time ago, if this method is compiled with optimization, the compilation took 10-15 minutes and the machine pages (has 256M core memory!)...

8.2.3.3 void OsiColCutUnitTest (const OsiSolverInterface * baseSiP, const std::string & mpsDir)

A function that tests the methods in the OsiColCut class.

8.2.3.4 void OsiRowCutUnitTest (const OsiSolverInterface * baseSiP, const std::string & mpsDir)

A function that tests the methods in the OsiRowCut class.

8.2.3.5 void OsiRowCutDebuggerUnitTest (const OsiSolverInterface * siP, const std::string & mpsDir)

A function that tests the methods in the OsiRowCutDebugger class.

8.2.3.6 void OsiCutsUnitTest ()

A function that tests the methods in the OsiCuts class.

Index

activate	applyRowCuts
OsiRowCutDebugger, 125	OsiSolverInterface, 155
activateRowCutDebugger	assignProblem
OsiSolverInterface, 160	OsiCpxSolverInterface, 45, 46
add	OsiGlpkSolverInterface, 64, 65
OsiUnitTest::TestOutcomes, 198	OsiGrbSolverInterface, 80
addCol	OsiMskSolverInterface, 106
OsiCpxSolverInterface, 44	OsiSolverInterface, 156
OsiGlpkSolverInterface, 63	OsiSpxSolverInterface, 179, 180
•	•
OsiGrbSolverInterface, 79	OsiXprSolverInterface, 193, 194
OsiMskSolverInterface, 104	basisIsAvailable
OsiSolverInterface, 152	
OsiSpxSolverInterface, 178	OsiSolverInterface, 161
OsiXprSolverInterface, 192	branch
addCols	OsiBranchingObject, 22, 23
OsiCpxSolverInterface, 44	OsiIntegerBranchingObject, 87
OsiGlpkSolverInterface, 63	OsiLotsizeBranchingObject, 92
OsiGrbSolverInterface, 79	OsiTwoWayBranchingObject, 182
OsiMskSolverInterface, 104	branchIndex_
OsiSolverInterface, 152	OsiBranchingObject, 23
OsiXprSolverInterface, 192	
addObjects	canDoSimplexInterface
OsiSolverInterface, 160	OsiSolverInterface, 161
addRow	clone
	OsiSolverInterface, 163
OsiCpxSolverInterface, 44	columnType
OsiGlpkSolverInterface, 63	OsiSolverInterface, 146
OsiGrbSolverInterface, 79	compareProblems
OsiMskSolverInterface, 105	OsiUnitTest, 10
OsiSolverInterface, 153	consistent
OsiSpxSolverInterface, 178	
OsiXprSolverInterface, 192	OsiColCut, 32
addRows	OsiCut, 48
OsiCpxSolverInterface, 44, 45	OsiRowCut, 121
OsiGlpkSolverInterface, 64	copyParameters
OsiGrbSolverInterface, 79	OsiSolverInterface, 144
OsiMskSolverInterface, 105	createBranch
OsiSolverInterface, 153, 154	OsiLotsize, 89
OsiXprSolverInterface, 193	OsiObject, 110
applyColCut	OsiSimpleInteger, 128
OsiCpxSolverInterface, 46	OsiSOS, 168
OsiGlpkSolverInterface, 66	
OsiGrbSolverInterface, 82	decrementInstanceCounter
OsiMskSolverInterface, 107	OsiGlpkSolverInterface, 66
	OsiGrbSolverInterface, 81
OsiSolverInterface, 163	OsiMskSolverInterface, 107
OsiSpxSolverInterface, 180	OsiXprSolverInterface, 195
OsiXprSolverInterface, 195	defaultHandler
applyCuts	OsiSolverInterface, 164
OsiGrbSolverInterface, 82	deleteColNames
OsiSolverInterface, 155	OsiSolverInterface, 151
applyRowCut	deleteCols
OsiSolverInterface, 163	OsiCpxSolverInterface, 44
	Osiophodiverilleriade, 44

OsiGlpkSolverInterface, 63	FREECACHED_ROW
OsiGrbSolverInterface, 79	OsiCpxSolverInterface, 40
OsiMskSolverInterface, 105	OsiGlpkSolverInterface, 59
OsiSolverInterface, 152	OsiGrbSolverInterface, 74
OsiSpxSolverInterface, 178	OsiMskSolverInterface, 101
OsiXprSolverInterface, 192	failureMessage
deleteRowNames	OsiUnitTest, 9, 10
OsiSolverInterface, 151	feasibleRegion
deleteRows	OsiLotsize, 89
OsiCpxSolverInterface, 45	OsiObject, 110
OsiGlpkSolverInterface, 64	OsiSimpleInteger, 128
OsiGrbSolverInterface, 79	OsiSOS, 168
OsiMskSolverInterface, 105	findIntegers
OsiSolverInterface, 154	OsiSolverInterface, 160
OsiSpxSolverInterface, 179	findIntegersAndSOS
OsiXprSolverInterface, 193	OsiSolverInterface, 160
dfltRowColName	findRange
OsiSolverInterface, 150	OsiLotsize, 90
differentModel	forceFeasible
OsiSolverInterface, 159	OsiSolverInterface, 160
disableFactorization	
OsiSolverInterface, 161	getBInvARow
doStrongBranching	OsiSolverInterface, 162
OsiChooseStrong, 25	getBasics
dumpCuts	OsiSolverInterface, 162
OsiCuts, 52	getBasisStatus
	OsiSolverInterface, 162
enableFactorization	getColName
OsiSolverInterface, 161	OsiSolverInterface, 151
enableSimplexInterface	getColNames
OsiSolverInterface, 163	OsiSolverInterface, 151
equivalentVectors	getColType
OsiUnitTest, 10	OsiSolverInterface, 146
eraseAndDumpCuts	getCountBySeverity
OsiCuts, 52	OsiUnitTest::TestOutcomes, 198
extraCharacteristics	getDualRays
OsiBabSolver, 17	OsiCpxSolverInterface, 42
extraCharacteristics	OsiGlpkSolverInterface, 61
OsiBabSolver, 17	OsiGrbSolverInterface, 76
00:200001, 17	OsiMskSolverInterface, 102
FREECACHED_COLUMN	OsiSolverInterface, 147
OsiCpxSolverInterface, 40	OsiSpxSolverInterface, 177
OsiGlpkSolverInterface, 59	·
OsiGrbSolverInterface, 74	OsiXprSolverInterface, 190
OsiMskSolverInterface, 101	getEmptyWarmStart
FREECACHED MATRIX	OsiCpxSolverInterface, 41
OsiCpxSolverInterface, 40	OsiGlpkSolverInterface, 60
OsiGlpkSolverInterface, 59	OsiGrbSolverInterface, 75
•	OsiMskSolverInterface, 101
OsiGrbSolverInterface, 74	OsiSolverInterface, 144
OsiMskSolverInterface, 101	getFractionalIndices
FREECACHED_RESULTS	OsiSolverInterface, 147
OsiCpxSolverInterface, 40	getHintParam
OsiGlpkSolverInterface, 59	OsiGrbSolverInterface, 75
OsiGrbSolverInterface, 74	OsiSolverInterface, 143, 144
OsiMskSolverInterface 101	

getIntegerTolerance OsiSolverInterface, 144	OsiXprSolverInterface, 189 getRowSense
getIterationCount	_
	OsiCpxSolverInterface, 41
OsiClark SolverInterface, 41	OsiGlpkSolverInterface, 60
OsiGlpkSolverInterface, 61	OsiGrbSolverInterface, 75
OsiGrbSolverInterface, 76	OsiMskSolverInterface, 10
OsiMskSolverInterface, 102	OsiSolverInterface, 145
OsiSpxSolverInterface, 177	OsiSpxSolverInterface, 176
OsiXprSolverInterface, 190	OsiXprSolverInterface, 189
getMutableMatrixByCol	getWarmStart
OsiSolverInterface, 146	OsiSolverInterface, 144
getMutableMatrixByRow	glp_prob, 12
OsiSolverInterface, 146	gutsOfDestroy
getNumInstances	OsiPresolve, 116
OsiXprSolverInterface, 195	1. 10
getObjSense	haltonerror
OsiSolverInterface, 145	OsiUnitTest, 11
getPointerToWarmStart	hasSolution
OsiSolverInterface, 144	OsiBabSolver, 16
getPrimalRays	
OsiCpxSolverInterface, 42	incrementInstanceCounter
OsiGlpkSolverInterface, 61	OsiGlpkSolverInterface, 66
OsiGrbSolverInterface, 77	OsiGrbSolverInterface, 81
OsiMskSolverInterface, 102	OsiMskSolverInterface, 107
OsiSolverInterface, 147	OsiXprSolverInterface, 194
OsiSpxSolverInterface, 177	infeasibility
OsiXprSolverInterface, 190	OsiObject, 110
getReducedGradient	infeasibility_
OsiSolverInterface, 162	OsiObject, 111
getRightHandSide	infeasible
OsiCpxSolverInterface, 41	OsiColCut, 32
OsiGlpkSolverInterface, 60	OsiCut, 49
OsiGrbSolverInterface, 76	OsiRowCut, 121
OsiMskSolverInterface, 101	insert
OsiSolverInterface, 145	OsiCuts, 52
OsiSpxSolverInterface, 176	insertIfNotDuplicate
OsiXprSolverInterface, 189	OsiCuts, 52
getRowActivity	invalidCut
OsiSolverInterface, 146	OsiRowCutDebugger, 125
getRowCutDebugger	isEquivalent
OsiSolverInterface, 161	OsiUnitTest, 10
getRowCutDebuggerAlways	isInteger
	OsiSolverInterface, 146
OsiSolverInterface, 161	,
getRowName	KEEPCACHED_ALL
OsiSolverInterface, 150	OsiCpxSolverInterface, 40
getRowNames	OsiGlpkSolverInterface, 59
OsiSolverInterface, 150	OsiGrbSolverInterface, 74
getRowRange	OsiMskSolverInterface, 10
OsiCpxSolverInterface, 41	KEEPCACHED COLUMN
OsiGlpkSolverInterface, 60	OsiCpxSolverInterface, 40
OsiGrbSolverInterface, 76	OsiGlpkSolverInterface, 59
OsiMskSolverInterface, 102	OsiGrbSolverInterface, 74
OsiSolverInterface, 145	OsiMskSolverInterface, 10
OsiSpxSolverInterface, 176	KEEPCACHED_MATRIX
	TEEL STOTIED_WITTIN

OsiCpxSolverInterface, 40	KEEPCACHED_MATRIX, 40
OsiGlpkSolverInterface, 59	KEEPCACHED_NONE, 40
OsiGrbSolverInterface, 74	KEEPCACHED_PROBLEM, 40
OsiMskSolverInterface, 101	KEEPCACHED_RESULTS, 40
KEEPCACHED_NONE	KEEPCACHED_ROW, 40
OsiCpxSolverInterface, 40	OsiGlpkSolverInterface
OsiGlpkSolverInterface, 59	FREECACHED COLUMN, 59
OsiGrbSolverInterface, 74	FREECACHED MATRIX, 59
OsiMskSolverInterface, 101	FREECACHED RESULTS, 59
KEEPCACHED_PROBLEM	FREECACHED ROW, 59
OsiCpxSolverInterface, 40	KEEPCACHED ALL, 59
OsiGlpkSolverInterface, 59	KEEPCACHED COLUMN, 59
OsiGrbSolverInterface, 74	KEEPCACHED MATRIX, 59
OsiMskSolverInterface, 101	KEEPCACHED NONE, 59
KEEPCACHED_RESULTS	KEEPCACHED PROBLEM, 59
OsiCpxSolverInterface, 40	KEEPCACHED RESULTS, 59
OsiGlpkSolverInterface, 59	KEEPCACHED ROW, 59
OsiGrbSolverInterface, 74	OsiGrbSolverInterface
OsiMskSolverInterface, 101	FREECACHED COLUMN, 74
KEEPCACHED_ROW	FREECACHED_MATRIX, 74
OsiCpxSolverInterface, 40	FREECACHED_RESULTS, 74
OsiGlpkSolverInterface, 59	FREECACHED ROW, 74
OsiGrbSolverInterface, 74	KEEPCACHED ALL, 74
OsiMskSolverInterface, 101	KEEPCACHED_COLUMN, 74
keepCachedFlag	KEEPCACHED MATRIX, 74
OsiCpxSolverInterface, 40	KEEPCACHED NONE, 74
OsiGlpkSolverInterface, 59	KEEPCACHED_PROBLEM, 74
OsiGrbSolverInterface, 74	KEEPCACHED_RESULTS, 74
OsiMskSolverInterface, 101	KEEPCACHED_ROW, 74
Commonconvermentace, 101	OsiMskSolverInterface
IoadFromCoinModel	FREECACHED_COLUMN, 101
OsiSolverInterface, 157	FREECACHED_MATRIX, 101
loadProblem	FREECACHED_RESULTS, 101
OsiCpxSolverInterface, 45, 46	FREECACHED_ROW, 101
OsiGlpkSolverInterface, 64, 65	KEEPCACHED_ALL, 101
OsiGrbSolverInterface, 80, 81	KEEPCACHED_COLUMN, 101
OsiMskSolverInterface, 105, 106	KEEPCACHED_MATRIX, 101
OsiSolverInterface, 155d	KEEPCACHED_NONE, 101
OsiSpxSolverInterface, 179, 180	KEEPCACHED_PROBLEM, 101
OsiXprSolverInterface, 193, 194	KEEPCACHED_RESULTS, 101
	KEEPCACHED ROW, 101
members_	OsiAuxInfo, 13
OsiSOS, 169	OsiBabSolver, 14
model	extraCharacteristics, 17
OsiPresolve, 115	extraCharacteristics, 17 extraCharacteristics_, 17
,	
onOptimalPath	hasSolution, 16 setExtraCharacteristics, 17
OsiRowCutDebugger, 125	
OsiCpxSolverInterface	setSolution, 16
FREECACHED_COLUMN, 40	setSolverType, 16
FREECACHED_MATRIX, 40	solverType, 17
FREECACHED_RESULTS, 40	solverType_, 17
FREECACHED_ROW, 40	OsiBranchingInformation, 18
KEEPCACHED_ALL, 40	stateOfSearch_, 20
KEEPCACHED COLUMN, 40	OsiBranchingObject, 20

branch 22 22	inpart 50
branch, 22, 23	insert, 52
branchIndex_, 23	insertlfNotDuplicate, 52
OsiChooseStrong, 23	OsiCutsUnitTest, 52
doStrongBranching, 25	OsiCuts::const_iterator, 12
setupList, 25	OsiCuts::iterator, 12
OsiChooseVariable, 26	OsiCutsUnitTest
setupList, 29	OsiCuts, 52
OsiColCut, 30	OsiUnitTests.hpp, 203
consistent, 32	OsiGlpkSolverInterface, 53
infeasible, 32	addCol, 63
OsiColCutUnitTest, 33	addCols, 63
violated, 32	addRow, 63
OsiColCutUnitTest	addRows, 64
OsiColCut, 33	applyColCut, 66
OsiUnitTests.hpp, 203	assignProblem, 64, 65
OsiCpxSolverInterface, 33	decrementInstanceCounter, 66
addCol, 44	deleteCols, 63
addCols, 44	deleteRows, 64
addRow, 44	getDualRays, 61
addRows, 44, 45	getEmptyWarmStart, 60
applyColCut, 46	getIterationCount, 61
assignProblem, 45, 46	getPrimalRays, 61
deleteCols, 44	getRightHandSide, 60
deleteRows, 45	getRowRange, 60
getDualRays, 42	getRowSense, 60
getEmptyWarmStart, 41	incrementInstanceCounter, 66
getIterationCount, 41	keepCachedFlag, 59
getPrimalRays, 42	loadProblem, 64, 65
getRightHandSide, 41	OsiGlpkSolverInterfaceUnitTest, 66
	•
getRowRange, 41	setColLower, 61
getRowSense, 41	setColName, 66
keepCachedFlag, 40	setColSetBounds, 62
loadProblem, 45, 46	setColSolution, 63
OsiCpxSolverInterfaceUnitTest, 47	setColUpper, 61
setColLower, 42	setHintParam, 60
setColSetBounds, 42	setRowLower, 62
setColSolution, 43	setRowName, 65
setColUpper, 42	setRowPrice, 63
setRowLower, 43	setRowSetBounds, 62
setRowPrice, 44	setRowSetTypes, 62
setRowSetBounds, 43	setRowUpper, 62
setRowSetTypes, 43	setWarmStart, 60
setRowUpper, 43	writeMps, 65
setWarmStart, 41	OsiGlpkSolverInterfaceUnitTest
writeMps, 46	OsiGlpkSolverInterface, 66
OsiCpxSolverInterfaceUnitTest	OsiGrbSolverInterface, 66
OsiCpxSolverInterface, 47	addCol, 79
OsiCut, 47	addCols, 79
consistent, 48	addRow, 79
infeasible, 49	addRows, 79
violated, 49	applyColCut, 82
OsiCuts, 49	applyCuts, 82
dumpCuts, 52	assignProblem, 80
eraseAndDumpCuts, 52	decrementInstanceCounter, 81
orasor madampouts, se	acordinatinatantecounital, of

deleteCols, 79	getDualRays, 102
deleteRows, 79	getEmptyWarmStart, 101
getDualRays, 76	getIterationCount, 102
getEmptyWarmStart, 75	getPrimalRays, 102
getHintParam, 75	getRightHandSide, 101
getIterationCount, 76	getRowRange, 102
getPrimalRays, 77	getRowSense, 101
getRightHandSide, 76	incrementInstanceCounter, 107
getRowRange, 76	keepCachedFlag, 101
getRowSense, 75	loadProblem, 105, 106
incrementInstanceCounter, 81	setColLower, 103
keepCachedFlag, 74	setColSetBounds, 103
loadProblem, 80, 81	setColSolution, 104
OsiGrbSolverInterfaceUnitTest, 82	setColUpper, 103
setColLower, 77	setRowLower, 103
setColSetBounds, 77	setRowPrice, 104
setColSolution, 78	setRowSetBounds, 103
setColUpper, 77	setRowSetTypes, 104
setHintParam, 75	setRowUpper, 103
setRowLower, 77	setWarmStart, 101
setRowPrice, 78	writeMps, 107
setRowSetBounds, 78	OsiNameVec
setRowSetTypes, 78	OsiSolverInterface, 143
setRowUpper, 77	
setWarmStart, 75	OsiObject, 107
	createBranch, 110
switchToLP, 81	feasibleRegion, 110
writeMps, 81 OsiGrbSolverInterfaceUnitTest	infeasibility, 110
	infeasibility_, 111
OsiGrbSolverInterface, 82	resetBounds, 111
OsiHotInfo, 82	setWhichWay, 111
updateInformation, 85	whichWay, 111
OsiIntegerBranchingObject, 85	OsiObject2, 111
branch, 87	OsiPresolve, 113
OsiIntegerBranchingObject, 87	gutsOfDestroy, 116
OsiIntegerBranchingObject, 87	model, 115
OsiLotsize, 87	postsolve, 115, 116
createBranch, 89	presolve, 116
feasibleRegion, 89	presolvedModel, 115
findRange, 90	setNonLinearValue, 115
resetBounds, 90	setPresolveActions, 115
OsiLotsizeBranchingObject, 90	OsiPseudoCosts, 116
branch, 92	OsiRowCut, 117
OsiLotsizeBranchingObject, 92	consistent, 121
OsiLotsizeBranchingObject, 92	infeasible, 121
OsiMskSolverInterface, 93	OsiRowCut, 120
addCol, 104	OsiRowCutUnitTest, 121
addCols, 104	OsiRowCut, 120
addRow, 105	violated, 121
addRows, 105	OsiRowCut2, 121
applyColCut, 107	OsiRowCutDebugger, 123
assignProblem, 106	activate, 125
decrementInstanceCounter, 107	invalidCut, 125
deleteCols, 105	onOptimalPath, 125
deleteRows, 105	OsiRowCutDebugger, 125

OsiRowCutDebuggerUnitTest, 126	getBasics, 162
OsiRowCutDebugger, 125	getBasisStatus, 162
redoSolution, 125	getColName, 151
validateCuts, 125	getColNames, 151
OsiRowCutDebugger.hpp, 199	getColType, 146
OsiRowCutDebuggerUnitTest	getDualRays, 147
OsiRowCutDebugger, 126	getEmptyWarmStart, 144
OsiUnitTests.hpp, 203	getFractionalIndices, 147
OsiRowCutUnitTest	getHintParam, 143, 144
OsiRowCut, 121	getIntegerTolerance, 144
OsiUnitTests.hpp, 203	getMutableMatrixByCol, 146
OsiSOS, 166	getMutableMatrixByRow, 146
createBranch, 168	getObjSense, 145
feasibleRegion, 168	getPointerToWarmStart, 144
members_, 169	getPrimalRays, 147
OsiSOS, 168	getReducedGradient, 162
OsiSOS, 168	getRightHandSide, 145
OsiSOSBranchingObject, 169	getRowActivity, 146
OsiSimpleInteger, 126	getRowCutDebugger, 161
createBranch, 128	getRowCutDebuggerAlways, 161
feasibleRegion, 128	getRowName, 150
resetBounds, 128	getRowNames, 150
OsiSolverBranch, 129	getRowRange, 145
OsiSolverInterface, 130	getRowSense, 145
activateRowCutDebugger, 160	getWarmStart, 144
addCol, 152	isInteger, 146
addCols, 152	loadFromCoinModel, 157
addObjects, 160	loadProblem, 155d
addRow, 153	OsiNameVec, 143
addRows, 153, 154	OsiSolverInterfaceCommonUnitTest, 164
applyColCut, 163	OsiSolverInterfaceMpsUnitTest, 164
applyCuts, 155	passInMessageHandler, 160
applyRowCut, 163	pivot, 163
applyRowCuts, 155	primalPivotResult, 163
assignProblem, 156	readGMPL, 158
basisIsAvailable, 161	readLp, 159
canDoSimplexInterface, 161	readMps, 157, 158
clone, 163	reducedCostFix, 150
columnType, 146	replaceMatrix, 154
copyParameters, 144	replaceMatrixOptional, 154
defaultHandler , 164	reset, 163
deleteColNames, 151	resolve, 143
deleteCols, 152	restoreBaseModel, 154
deleteRowNames, 151	rowCutDebugger_, 164
deleteRows, 154	saveBaseModel, 154
dfltRowColName, 150	setApplicationData, 159
differentModel, 159	setApplicationData, 139 setAuxiliaryInfo, 159
disableFactorization, 161	setAuxiliaryinio, 159 setBasisStatus, 162
enableFactorization, 161	setColBounds, 148
enableSimplexInterface, 163	setColLower, 148
findIntegers, 160	setColName, 151
findIntegersAndSOS, 160	setColNames, 151
forceFeasible, 160	setColSetBounds, 148
getBlnvARow, 162	setColSolution, 149

setColUpper, 148	OsiTwoWayBranchingObject, 182
setHintParam, 143	OsiTwoWayBranchingObject, 182
setInitialData, 164	OsiUnitTest, 8
setObjSense, 147	compareProblems, 10
setObjective, 147	equivalentVectors, 10
setRowBounds, 149	failureMessage, 9, 10
setRowColNames, 151	haltonerror, 11
setRowLower, 148	isEquivalent, 10
setRowName, 150	outcomes, 11
setRowNames, 150	processParameters, 10
setRowPrice, 149	testingMessage, 10
setRowSetBounds, 149	verbosity, 10
setRowSetTypes, 149	OsiUnitTest::TestOutcome, 195
setRowUpper, 149	OsiUnitTest::TestOutcomes, 197
setWarmStart, 145	add, 198
writeLp, 158	getCountBySeverity, 198
writeLpNative, 159	OsiUnitTests.hpp, 199
writeMps, 158	OsiColCutUnitTest, 203
writeMpsNative, 158	OsiCutsUnitTest, 203
OsiSolverInterface::ApplyCutsReturnCode, 11	OsiRowCutDebuggerUnitTest, 203
OsiSolverInterfaceCommonUnitTest	OsiRowCutUnitTest, 203
OsiSolverInterface, 164	OsiSolverInterfaceCommonUnitTest, 203
OsiUnitTests.hpp, 203	OsiSolverInterfaceMpsUnitTest, 202
OsiSolverInterfaceMpsUnitTest	OsiXprSolverInterface, 182
OsiSolverInterface, 164	addCol, 192
OsiUnitTests.hpp, 202	addCols, 192
OsiSolverResult, 165	addRow, 192
OsiSpxSolverInterface, 170	addRows, 193
addCol, 178	applyColCut, 195
addRow, 178	assignProblem, 193, 194
applyColCut, 180	decrementInstanceCounter, 195
assignProblem, 179, 180	deleteCols, 192
deleteCols, 178	deleteRows, 193
deleteRows, 179	getDualRays, 190
getDualRays, 177	getIterationCount, 190
getIterationCount, 177	getNumInstances, 195
getPrimalRays, 177	getPrimalRays, 190
getRightHandSide, 176	getRightHandSide, 189
getRowRange, 176	getRowRange, 189
getRowSense, 176	getRowSense, 189
loadProblem, 179, 180	incrementInstanceCounter, 194
OsiSpxSolverInterfaceUnitTest, 180	loadProblem, 193, 194
setColLower, 177	OsiXprSolverInterfaceUnitTest, 195
setColSolution, 178	setColLower, 190
setColUpper, 177	setColSetBounds, 191
setRowLower, 178	setColSolution, 192
setRowPrice, 178	setColUpper, 190
setRowUpper, 178	setLogFileName, 195
• •	
setWarmStart, 176	setRowPrice 193
writeMps, 180	setRowPrice, 192
OsiSpxSolverInterfaceUnitTest	setRowSetBounds, 191
OsiSpxSolverInterface, 180	setRowSetTypes, 191
OsiTwoWayBranchingObject, 181	setNowUpper, 191
branch, 182	setWarmStart, 189

writeMps, 194	OsiSolverInterface, 162
OsiXprSolverInterfaceUnitTest	setColBounds
OsiXprSolverInterface, 195	OsiSolverInterface, 148
outcomes	setColLower
OsiUnitTest, 11	OsiCpxSolverInterface, 42
	OsiGlpkSolverInterface, 61
passInMessageHandler	OsiGrbSolverInterface, 77
OsiSolverInterface, 160	OsiMskSolverInterface, 103
pivot	OsiSolverInterface, 148
OsiSolverInterface, 163	OsiSpxSolverInterface, 177
postsolve	OsiXprSolverInterface, 190
OsiPresolve, 115, 116	setColName
presolve OciPresolve 116	OsiGlpkSolverInterface, 66
OsiPresolve, 116	OsiSolverInterface, 151
presolvedModel OsiPresolve, 115	setColNames
primalPivotResult	OsiSolverInterface, 151
OsiSolverInterface, 163	setColSetBounds
processParameters	OsiCpxSolverInterface, 42
OsiUnitTest, 10	OsiGlpkSolverInterface, 62
Osloniciest, 10	OsiGrbSolverInterface, 77
readGMPL	OsiMskSolverInterface, 103
OsiSolverInterface, 158	OsiSolverInterface, 148
readLp	OsiXprSolverInterface, 191 setColSolution
OsiSolverInterface, 159	OsiCpxSolverInterface, 43
readMps	OsiGlpkSolverInterface, 63
OsiSolverInterface, 157, 158	OsiGrbSolverInterface, 78
redoSolution	OsiMskSolverInterface, 104
OsiRowCutDebugger, 125	OsiSolverInterface, 149
reducedCostFix	OsiSpxSolverInterface, 178
OsiSolverInterface, 150	OsiXprSolverInterface, 192
replaceMatrix	setColUpper
OsiSolverInterface, 154	OsiCpxSolverInterface, 42
replaceMatrixOptional	OsiGlpkSolverInterface, 61
OsiSolverInterface, 154	OsiGrbSolverInterface, 77
reset	OsiMskSolverInterface, 103
OsiSolverInterface, 163	OsiSolverInterface, 148
resetBounds	OsiSpxSolverInterface, 177
OsiLotsize, 90	OsiXprSolverInterface, 190
OsiObject, 111	setExtraCharacteristics
OsiSimpleInteger, 128	OsiBabSolver, 17
resolve	setHintParam
OsiSolverInterface, 143	OsiGlpkSolverInterface, 60
restoreBaseModel	OsiGrbSolverInterface, 75
OsiSolverInterface, 154	OsiSolverInterface, 143
rowCutDebugger_	setInitialData
OsiSolverInterface, 164	OsiSolverInterface, 164
saveBaseModel	setLogFileName
OsiSolverInterface, 154	OsiXprSolverInterface, 195
setApplicationData	setNonLinearValue
OsiSolverInterface, 159	OsiPresolve, 115
setAuxiliaryInfo	setObjSense
OsiSolverInterface, 159	OsiSolverInterface, 147
setBasisStatus	setObjective

selPresolve, 115 SelRowBounds OsiPresolve, 115 SelRowBounds OsiSolverInterface, 149 SelRowColNames OsiSolverInterface, 151 SelRowLower OsiCpxSolverInterface, 151 SelRowLower OsiCpxSolverInterface, 151 SelRowLower OsiCpxSolverInterface, 162 OsiGhkSolverInterface, 176 OsiSpxSolverInterface, 189 SelSpxSolverInterface, 189 OsiGpkSolverInterface, 189 OsiSpxSolverInterface, 189 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 SetRowName OsiGlpkSolverInterface, 150 SetRowNames OsiSolverInterface, 150 SelRowPrice OsiCpxSolverInterface, 150 SelRowPrice OsiSpxSolverInterface, 144 OsiGlpkSolverInterface, 144 OsiGlpkSolverInterface, 149 OsiSpxSolverInterface, 192 SetRowSelBounds OsiCpxSolverInterface, 192 SetRowSelBounds OsiCpxSolverInterface, 193 OsiGlpkSolverInterface, 194 OsiSolverInterface, 149 OsiSpxSolverInterface, 140 OsiSolverInterface, 140 OsiSolverI	OsiSolverInterface, 147	setWarmStart
OsiPresolve, 115 setRowBounds OsiSolverInterface, 149 setRowColNames OsiSolverInterface, 151 setRowColNames OsiSolverInterface, 151 SetRowLower OsiCpxSolverInterface, 43 OsiGpxSolverInterface, 43 OsiGpxSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 178 OsiMskSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 setRowName OsiGlpkSolverInterface, 150 setRowPrice OsiSolverInterface, 150 setRowPrice OsiGpxSolverInterface, 44 OsiGpxSolverInterface, 44 OsiGpxSolverInterface, 44 OsiGpxSolverInterface, 160 OsiSolverInterface, 178 OsiSolverInterface, 189 OsiSolverInterface, 191 SetRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 193 OsiSolverInterface, 194 OsiSolverInterface, 195 SetRowSetTypes OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 191 SetRowSetTypes OsiCpxSolverInterface, 193 OsiSolverInterface, 194 OsiSolverInterface, 194 OsiSolverInterface, 194 OsiSolverInterface, 194 OsiSolverInterface, 194 OsiSolverInterface, 194 OsiSolverInterface, 195 SetRowSetPropes OsiCpxSolverInterface, 196 OsiGpkSolverInterface, 197 OsiMskSolverInterface, 198 OsiCpxSolverInterface, 199 SetRowSetPounds OsiGpkSolverInterface, 199 SetSolverInterface, 199 OsiSolverInterface, 199 OsiSolverInterface, 199 OsiSolverInterface, 199 SetSolverInterface, 158 OsiSolverInterface, 199 SetSolverInterface, 158 OsiSolverInterface, 199 SetSolverInterface, 158 OsiSolverInterface, 158 OsiSolverInterface, 199 SetSolverInterface, 158 OsiSolverInterface, 158 OsiSolverInterface, 158 OsiSolverInterface, 159 SetSolverInterface, 158 OsiSolverInterface, 158 OsiSolverInterface, 159 SetSolverInterface, 159 SetSolve	setPresolveActions	OsiCpxSolverInterface, 41
OsiSolverInterface, 149 setRowColNames OsiSolverInterface, 151 setRowLower OsiCpxSolverInterface, 43 OsiGpkSolverInterface, 43 OsiGpkSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 178 OsiXprSolverInterface, 191 setRowName OsiGlpkSolverInterface, 150 setRowPrice OsiSolverInterface, 150 setRowPrice OsiGpkSolverInterface, 150 setRowSolverInterface, 160 OsiGpxSolverInterface, 178 OsiSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiGpkSolverInterface, 193 OsiSolverInterface, 194 OsiSpxSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 192 setRowSetRoverInterface, 193 OsiGpkSolverInterface, 194 OsiSolverInterface, 195 OsiMskSolverInterface, 196 OsiSolverInterface, 197 OsiSolverInterface, 198 OsiSpxSolverInterface, 199 setRowDeper OsiCpxSolverInterface, 191 SetSolverInterface, 178 OsiSolverInterface, 180 OsiSolverInterface, 180 OsiSolverInterface, 180 OsiSolverInterface, 180 OsiSpxSolverInterface, 180 OsiSpxSolverInterface, 191 setSolverInterface, 191 setSolverInterface, 191 setSolverInterface, 158 osiSpxSolverInterface, 194 writeMpsNative OsiSolverInterface, 158 osiSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	OsiPresolve, 115	
setRowCollNames OsiSolverInterface, 151 SosiSoxSolverInterface, 175 OsiSolverInterface, 175 OsiSpxSolverInterface, 189 OsiCpxSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 SetRowName OsiGlpkSolverInterface, 150 SetRowName OsiGlpkSolverInterface, 150 SetRowPrice OsiCpxSolverInterface, 150 SetRowPrice OsiCpxSolverInterface, 150 SetRowPrice OsiGpkSolverInterface, 150 SetRowPrice OsiGpxSolverInterface, 140 OsiSolverInterface, 178 OsiSpxSolverInterface, 191 SetRowSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 193 OsiSpxSolverInterface, 193 OsiSpxSolverInterface, 193 OsiSpxSolverInterface, 194 OsiSolverInterface, 199 OsiCpxSolverInterface, 199 SetRowSetTypes OsiCpxSolverInterface, 191 SetRowSetTypes OsiCpxSolverInterface, 191 SetRowSetTypes OsiCpxSolverInterface, 191 SetRowSetTypes OsiCpxSolverInterface, 191 SetRowUper OsiCpxSolverInterface,	setRowBounds	OsiGrbSolverInterface, 75
setRowCollNames OsiSolverInterface, 151 SosiSoxSolverInterface, 175 OsiSolverInterface, 175 OsiSpxSolverInterface, 189 OsiCpxSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 SetRowName OsiGlpkSolverInterface, 150 SetRowName OsiGlpkSolverInterface, 150 SetRowPrice OsiCpxSolverInterface, 150 SetRowPrice OsiCpxSolverInterface, 150 SetRowPrice OsiGpkSolverInterface, 150 SetRowPrice OsiGpxSolverInterface, 140 OsiSolverInterface, 178 OsiSpxSolverInterface, 191 SetRowSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 193 OsiSpxSolverInterface, 193 OsiSpxSolverInterface, 193 OsiSpxSolverInterface, 194 OsiSolverInterface, 199 OsiCpxSolverInterface, 199 SetRowSetTypes OsiCpxSolverInterface, 191 SetRowSetTypes OsiCpxSolverInterface, 191 SetRowSetTypes OsiCpxSolverInterface, 191 SetRowSetTypes OsiCpxSolverInterface, 191 SetRowUper OsiCpxSolverInterface,	OsiSolverInterface, 149	OsiMskSolverInterface, 101
OsiSolverInterface, 151 setRowLower OsiCpxSolverInterface, 43 OsiGpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 138 OsiSolverInterface, 148 OsiSpxSolverInterface, 148 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 setRowName OsiGlpkSolverInterface, 65 OsiGolverInterface, 150 setRowNames OsiSolverInterface, 150 setRowNames OsiSolverInterface, 150 setRowNames OsiGpkSolverInterface, 150 setRowPrice OsiCpxSolverInterface, 150 setRowPrice OsiGpkSolverInterface, 150 setRowPrice OsiCpxSolverInterface, 164 OsiSolverInterface, 150 SetRowPrice OsiCpxSolverInterface, 104 OsiSolverInterface, 168 OsiGpkSolverInterface, 104 OsiSolverInterface, 149 OsiSpxSolverInterface, 169 OsiGpkSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 149 OsiSpxSolverInterface, 159 writeLp OsiSolverInterface, 159 writeLp OsiSolverInterface, 159 writeLp OsiSolverInterface, 159 osiCpxSolverInterface, 150 OsiGpkSolverInterface, 150 Osi		
setRowLower OsiCpxSolverInterface, 43 OsiGpkSolverInterface, 62 OsiGpkSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 SetRowName OsiGpkSolverInterface, 65 OsiSolverInterface, 150 SetRowName OsiSolverInterface, 150 SetRowName OsiGpkSolverInterface, 150 SetRowPrice OsiCpxSolverInterface, 150 SetRowPrice OsiGpkSolverInterface, 44 OsiGpkSolverInterface, 63 OsiGrbSolverInterface, 63 OsiGrbSolverInterface, 63 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 178 OsiSpxSolverInterface, 178 OsiCpxSolverInterface, 178 OsiCpxSolverInterface, 178 OsiCpxSolverInterface, 178 OsiGpkSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 193 SotiCptterface, 149 OsiSpxSolverInterface, 194 OsiSpxSolverInterface, 195 SetSolverInterface, 191 SetRowSottSpyes OsiCpxSolverInterface, 191 SetSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 159 WriteMps OsiCpxSolverInterface, 159 WriteMps OsiCpxSolverInterface, 159 OsiGpkSolverInterface, 169 OsiSpxSolverInterface, 169 OsiSpxSolverInterface, 169 OsiSpxSolverInterface, 169 OsiSpxSolverInterface, 169 OsiSpxSolverInterface, 169 OsiGpkSolverInterface, 169 OsiGpkSolverInterface, 169 OsiSpxSolverInterface, 169 OsiGpkSolverInterface, 169 OsiGpkSolverIn		
OsiCpxSolverInterface, 43 OsiGpkSolverInterface, 62 OsiGrbSolverInterface, 177 OsiMskSolverInterface, 178 OsiSolverInterface, 148 OsiSolverInterface, 191 SetRowName OsiGpkSolverInterface, 150 SetRowName OsiSolverInterface, 150 SetRowNames OsiCpxSolverInterface, 164 OsiGpkSolverInterface, 163 OsiGpkSolverInterface, 164 OsiSolverInterface, 178 OsiSolverInterface, 178 OsiSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 193 OsiGpkSolverInterface, 164 OsiSolverInterface, 178 OsiMskSolverInterface, 178 OsiMskSolverInterface, 178 OsiSolverInterface, 179 OsiCpxSolverInterface, 179 OsiCpxSolverInterface, 179 OsiSolverInterface, 180 OsiSolverInterface, 159 writeLp OsiSolverInterface, 159 osiCpxSolverInterface, 159 osiCpxSolverInterface, 159 OsiCpxSolverInterface, 159 OsiCpxSolverInterface, 159 OsiSolverInterface, 150 OsiSolverInt		
OsiGipkSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 148 OsiSpxSolverInterface, 148 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 SetRowName OsiGipkSolverInterface, 65 OsiSolverInterface, 150 SetRowPrice OsiSolverInterface, 150 SetRowPrice OsiGpkSolverInterface, 150 SetRowPrice OsiGpxSolverInterface, 140 OsiSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 192 SetRowSetTypes OsiCpxSolverInterface, 149 OsiSpxSolverInterface, 159 writeMps OsiCpxSolverInterface, 159 writeMps OsiCpxSolverInterface, 159 osiGpkSolverInterface, 160 OsiGpkSolverInterface, 160 OsiGpkSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 180 OsiSpxSolverInterface, 180 OsiSpxSolverInterface, 191 SetSolution OsiBabSolver, 17 SolverInterface, 192 SetSolution OsiBabSolver, 16 SetSolverInterface, 158		
OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 148 OsiSpxSolverInterface, 178 OsiKhsKolverInterface, 178 OsiSpxSolverInterface, 191 SetRowName OsiGlpkSolverInterface, 65 OsiSolverInterface, 150 SetRowNames OsiSolverInterface, 150 SetRowPrice OsiGlpkSolverInterface, 150 SetRowPrice OsiGlpkSolverInterface, 44 OsiGpkSolverInterface, 63 OsiGrbSolverInterface, 63 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSpxSolverInterface, 104 OsiSpxSolverInterface, 104 OsiSpxSolverInterface, 192 SetRowSetBounds OsiCpxSolverInterface, 192 SetRowSetBounds OsiGpkSolverInterface, 103 OsiGlpkSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 191 SetRowSetTypes OsiCpxSolverInterface, 104 OsiSolverInterface, 105 OsiGpkSolverInterface, 104 OsiSolverInterface, 105 OsiGpkSolverInterface, 106 OsiSolverInterface, 107 OsiMskSolverInterface, 108 OsiGpkSolverInterface, 109 OsiSpxSolverInterface, 158 OsiSpxSolverInterface, 159 WriteMpsNative OsiSolverInterface, 158 OsiSolverInterface, 159 WriteMpsNative OsiSolverInterface, 158 OsiSolverInterface, 159 WriteMpsNative OsiSolverInterface, 158	•	•
OsiMskSolverInterface, 148 OsiSpxSolverInterface, 148 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 189 OsiSpxSolverInterface, 191 SetRowName OsiGlpkSolverInterface, 65 OsiSolverInterface, 150 SetRowNames OsiSolverInterface, 150 SetRowNames OsiSolverInterface, 150 SetRowNames OsiSolverInterface, 150 SetRowNames OsiCpxSolverInterface, 150 SetRowNames OsiSpxSolverInterface, 150 SetRowNames OsiCpxSolverInterface, 163 OsiGpkSolverInterface, 164 OsiGpkSolverInterface, 104 OsiSpxSolverInterface, 104 OsiSpxSolverInterface, 105 OsiGpkSolverInterface, 106 OsiGpkSolverInterface, 107 OsiMskSolverInterface, 108 OsiCpxSolverInterface, 109 OsiSpxSolverInterface, 109 OsiSpxSolverInterface, 109 OsiSpxSolverInterface, 109 OsiSpxSolverInterface, 178 OsiSolverInterface, 180 OsiSpxSolverInterface, 158 OsiSpxSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType		
OsiSolverInterface, 148 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 setRowName OsiGlpkSolverInterface, 65 OsiSolverInterface, 150 setRowName OsiGlpkSolverInterface, 150 setRowName OsiSolverInterface, 150 setRowPrice OsiSolverInterface, 150 setRowPrice OsiCpxSolverInterface, 44 OsiGlpkSolverInterface, 63 OsiGpxSolverInterface, 63 OsiGpkSolverInterface, 63 OsiGrbSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 178 OsiMskSolverInterface, 104 OsiGpxSolverInterface, 178 OsiGpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiGpkSolverInterface, 130 OsiSolverInterface, 149 OsiSpxSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiGpxSolverInterface, 149 OsiGpxSolverInterface, 149 OsiGpxSolverInterface, 149 OsiGpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 162 OsiGrbSolverInterface, 163 OsiGlpkSolverInterface, 163 OsiGlpkSolverInterface, 163 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 180 OsiSpxSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType		•
OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 setRowName OsiGlpkSolverInterface, 65 OsiSolverInterface, 150 setRowNames OsiSolverInterface, 150 setRowPrice OsiGlpkSolverInterface, 150 setRowPrice OsiGlpkSolverInterface, 44 OsiGlpkSolverInterface, 63 OsiGlpkSolverInterface, 63 OsiGlpkSolverInterface, 63 OsiGrbSolverInterface, 81 OsiGrbSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSpxSolverInterface, 105 SetRowSetBounds OsiCpxSolverInterface, 103 OsiGlpkSolverInterface, 103 OsiGlpkSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 104 OsiSolverInterface, 105 OsiGlpkSolverInterface, 106 OsiGlpkSolverInterface, 107 OsiGlpkSolverInterface, 108 OsiGlpkSolverInterface, 109 OsiCpxSolverInterface, 109 OsiCpxSolverInterface, 109 OsiSolverInterface, 100 OsiSolverInterface, 100 OsiSolverInterface, 100 OsiSolverInterface, 101 OsiSolverInterface, 103 OsiSolverInterface, 104 OsiSpxSolverInterface, 105 OsiSpxSolverInterface, 105 OsiSpxSolverInterface, 107 OsiSolverInterface, 107 OsiSolverInterface, 108 OsiXprSolverInterface, 109 OsiSpxSolverInterface, 109 OsiXprSolverInterface, 109 OsiXprSolverInterface, 109 OsiSpxSolverInterface, 109		
OsiSprSolverInterface, 191 setRowName OsiGlpkSolverInterface, 65 OsiSolverInterface, 150 setRowNames OsiSolverInterface, 150 setRowNames OsiSolverInterface, 150 setRowPrice OsiCpxSolverInterface, 44 OsiGlpkSolverInterface, 63 OsiGrbSolverInterface, 63 OsiGrbSolverInterface, 63 OsiGrbSolverInterface, 63 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiSpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 191 setRowSetPouper OsiCpxSolverInterface, 104 OsiSolverInterface, 149 OsiSprSolverInterface, 149 OsiSprSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 SetRowUpper OsiSolverInterface, 191 OsiSolverInterface, 191 OsiSolverInterface, 192 OsiSpxSolverInterface, 193 OsiSpxSolverInterface, 194 OsiSpxSolverInterface, 195 OsiGrbSolverInterface, 196 OsiSpxSolverInterface, 197 OsiSolverInterface, 198 OsiSpxSolverInterface, 199 OsiSpxSolver		
setRowName OsiGlpkSolverInterface, 65 OsiSolverInterface, 150 setRowNames OsiSolverInterface, 150 setRowPrice OsiGpxSolverInterface, 63 OsiGpxSolverInterface, 63 OsiGpxSolverInterface, 63 OsiGpxSolverInterface, 63 OsiGpxSolverInterface, 104 OsiSpxSolverInterface, 104 OsiSpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiGpxSolverInterface, 192 setRowSetBounds OsiGpxSolverInterface, 192 setRowSetBounds OsiGpxSolverInterface, 193 OsiGpxSolverInterface, 194 OsiSpyrSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 192 setRowSetTypes OsiGpxSolverInterface, 193 SetRowSetTypes OsiGpxSolverInterface, 194 OsiSpyrSolverInterface, 195 setRowSetPypes OsiGpxSolverInterface, 196 OsiSolverInterface, 197 OsiMskSolverInterface, 199 SetRowUpper OsiCpxSolverInterface, 199 SetRowInterface, 199 SetSolverInterface,		
OsiGlpkSolverInterface, 150 SetRowNames OsiSolverInterface, 150 setRowPrice OsiGpxSolverInterface, 44 OsiGlpkSolverInterface, 63 OsiGpxSolverInterface, 63 OsiGpSolverInterface, 63 OsiGpSolverInterface, 63 OsiGpSolverInterface, 104 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiMskSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiGpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 193 OsiSolverInterface, 194 OsiSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 194 OsiSolverInterface, 149 OsiSpxSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiSolverInterface, 191 setRowUpper OsiSolverInterface	•	
OsiSolverInterface, 150 setRowNames OsiSolverInterface, 150 setRowPrice OsiCpxSolverInterface, 44 OsiGlpkSolverInterface, 63 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiMskSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiGpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 191 setRowSetTypes OsiGrbSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 191 setRowSetTypes OsiGrbSolverInterface, 149 OsiSolverInterface, 149 OsiSolverInterface, 149 OsiSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiCpxSolverInter		
setRowNames OsiSolverInterface, 150 setRowPrice OsiCpxSolverInterface, 44 OsiCipkSolverInterface, 63 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiGrbSolverInterface, 192 setRowSetBounds OsiGrbSolverInterface, 192 setRowSetBounds OsiGrbSolverInterface, 192 setRowSetBounds OsiGrbSolverInterface, 193 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 191 setRowSetTypes OsiGpxSolverInterface, 194 OsiSpxSolverInterface, 194 OsiSpxSolverInterface, 194 OsiSpxSolverInterface, 194 OsiSpxSolverInterface, 194 OsiSpxSolverInterface, 195 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiGpkSolverInterface, 191 setRowCutbebugger, 125 verbosity osiHottlnfo, 85 validateCuts osiHottlnfo, 85 validateCuts osiPowCutDebugger, 125 verbosity osiHottlnfo, 85 validateCuts osiPowCutDebugger, 125 verbosity osiHottlnfo, 85 osiGpkSolverInterface, 191 violated osiColott, 49 os		
OsiSolverInterface, 150 setRowPrice OsiCpxSolverInterface, 44 OsiGlpkSolverInterface, 63 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 178 OsiXprSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 104 OsiMskSolverInterface, 104 OsiMskSolverInterface, 104 OsiSpxSolverInterface, 105 OsiGpkSolverInterface, 106 OsiGpkSolverInterface, 107 OsiSpxSolverInterface, 108 OsiGpkSolverInterface, 109 SetRowUpper OsiCpxSolverInterface, 103 OsiSpxSolverInterface, 103 OsiSpxSolverInterface, 103 OsiSpxSolverInterface, 103 OsiSpxSolverInterface, 103 OsiSpxSolverInterface, 104 OsiSpxSolverInterface, 105 OsiSpxSolverInterface, 106 OsiSpxSolverInterface, 107 OsiSpxSolverInterface, 108 OsiXprSolverInterface, 109 SetSolverInterface, 119 SetSolution OsiBabSolver, 16 SetSolverType		
setRowPrice OsiGrpxSolverInterface, 44 OsiGlpkSolverInterface, 63 OsiGrbSolverInterface, 63 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiMskSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 192 setRowSetBounds OsiGpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 105 OsiGrbSolverInterface, 106 OsiGrbSolverInterface, 107 OsiSolverInterface, 108 OsiGrbSolverInterface, 109 OsiSolverInterface,		
OsiCpxSolverInterface, 44 OsiGlpkSolverInterface, 63 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 191 setRowSetTypes OsiGrbSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 109 OsiCpxSolverInterface, 101 OsiGpkSolverInterface, 104 OsiSolverInterface, 105 OsiGpkSolverInterface, 107 OsiGpkSolverInterface, 108 OsiGpkSolverInterface, 109 OsiCpxSolverInterface, 109 OsiSolverInterface, 109 OsiSolverInterface, 159 writeUpNative OsiSolverInterface, 159 writeMps OsiCpxSolverInterface, 159 writeMps OsiCpxSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 104 OsiSolverInterface, 105 OsiGpkSolverInterface, 107 OsiSolverInterface, 108 OsiSpxSolverInterface, 119 SetRowUpper OsiCpxSolverInterface, 129 OsiCpxSolverInterface, 159 writeMps OsiSolverInterface, 159 writeMps OsiSolverInterface, 159 osiGpkSolverInterface, 159 osiGpkSolverInterface, 159 OsiGpkSolverInterface, 159 OsiGpkSolverInterface, 159 OsiSolverInterface, 159 OsiSpxSolverInterface, 159 OsiSpxSolverInte		
OsiGlpkSolverInterface, 63 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiSpxSolverInterface, 192 setRowSetBounds OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 191 setRowSetTypes OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 101 OsiBosolverInterface, 102 OsiGrbSolverInterface, 103 OsiSolverInterface, 104 OsiSolverInterface, 105 OsiGrbSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 105 OsiGpkSolverInterface, 104 OsiSolverInterface, 105 OsiGpkSolverInterface, 107 OsiSolverInterface, 108 OsiGpkSolverInterface, 109 OsiSolverInterface, 119		OsiGrbSolverInterface, 81
OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiMskSolverInterface, 178 OsiSpxSolverInterface, 192 setRowSetBounds OsiGpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 104 OsiSpxSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 109 SetRowUpper OsiCpxSolverInterface, 101 OsiSolverInterface, 102 OsiCpxSolverInterface, 104 OsiSolverInterface, 105 OsiGpkSolverInterface, 106 OsiCpxSolverInterface, 107 OsiSolverInterface, 108 OsiGpkSolverInterface, 109 SetRowUpper OsiCpxSolverInterface, 109 OsiSolverInterface, 109		tooting Managan
OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 103 OsiSolverInterface, 104 OsiSpxSolverInterface, 105 OsiGrbSolverInterface, 107 OsiSolverInterface, 108 OsiCpxSolverInterface, 109 OsiCpxSolverInterface, 191 OsiCpxSolverInterface, 191 OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 109 SetRowUpper OsiCpxSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 191 OsiGlpkSolverInterface, 191 OsiGlpkSolverInterface, 191 OsiGlpkSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 104 OsiSpxSolverInterface, 105 OsiSpxSolverInterface, 107 OsiSolverInterface, 108 OsiSpxSolverInterface, 109 SetSolverInterface, 109 OsiSpxSolverInterface, 109 Os		
OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiXprSolverInterface, 43 OsiGlpkSolverInterface, 191 setRowSetTypes OsiGpxSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSpxSolverInterface, 104 OsiSpxSolverInterface, 105 OsiSpxSolverInterface, 107 OsiSpxSolverInterface, 108 OsiSpxSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType	•	Osionitiest, 10
OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 103 OsiSpvsColverInterface, 103 OsiSpvsColverInterface, 191 setRowSetTypes OsiGpxSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 62 OsiGrbSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 62 OsiGrbSolverInterface, 63 OsiSpxSolverInterface, 103 OsiSpxSolverInterface, 103 OsiSpxSolverInterface, 105 OsiSpxSolverInterface, 107 OsiSolverInterface, 108 OsiSpxSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType		undateInformation
OsiXprSolverInterface, 192 setRowSetBounds OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowSetTypes OsiGpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 109 OsiXprSolverInterface, 109 OsiCpxSolverInterface, 119 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 65 OsiGrbSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 158 OsiSpxSolverInterface, 158 OsiSpxSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType		
setRowSetBounds OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowSetTypes OsiGpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 62 OsiGrbSolverInterface, 104 OsiSolverInterface, 149 OsiSolverInterface, 149 OsiCpxSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiGpkSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 65 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 107 OsiSolverInterface, 107 OsiSolverInterface, 107 OsiSolverInterface, 107 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158 setSolverType		Osiriotimo, 85
OsiRowCutDebugger, 125 OsiGpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 62 OsiGrbSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType		validateCuts
OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 78 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiXprSolverInterface, 191 SetRowSetTypes OsiGpkSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 149 OsiXprSolverInterface, 149 OsiXprSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 104 OsiSpxSolverInterface, 105 OsiGrbSolverInterface, 107 OsiSolverInterface, 108 OsiSpxSolverInterface, 109 SetSolution OsiBabSolver, 16 SetSolverType		
OsiGipkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiXprSolverInterface, 191 SetRowSetTypes OsiGpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 149 OsiSolverInterface, 149 OsiSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 191 SetRowUpper OsiGpkSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType		
OsiGrbSolverInterface, 78 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiXprSolverInterface, 191 SetRowSetTypes OsiCpxSolverInterface, 62 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType	OsiGlpkSolverInterface, 62	-
OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 103 OsiSpxSolverInterface, 103 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 178 OsiXprSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType	OsiGrbSolverInterface, 78	
OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowSetTypes OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 104 OsiSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 158 OsiGrbSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 158 OsiSpxSolverInterface, 158 OsiSpxSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType	OsiMskSolverInterface, 103	
OsiRowCut, 121 setRowSetTypes OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType	OsiSolverInterface, 149	
OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiXprSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType whichWay OsiObject, 111 writeLp OsiSolverInterface, 158 writeLpNative OsiSolverInterface, 159 writeMps OsiCpxSolverInterface, 46 OsiGlpkSolverInterface, 46 OsiGlpkSolverInterface, 65 OsiGrbSolverInterface, 81 OsiMskSolverInterface, 107 OsiSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	OsiXprSolverInterface, 191	
OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 178 OsiXprSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType OsiObject, 111 writeLp OsiSolverInterface, 158 writeLpNative OsiSolverInterface, 159 writeMps OsiCpxSolverInterface, 46 OsiGlpkSolverInterface, 65 OsiGrbSolverInterface, 81 OsiMskSolverInterface, 107 OsiSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	setRowSetTypes	Osinowout, 121
OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiXprSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSpxSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType OsiObject, 111 writeLp OsiSolverInterface, 158 writeLpNative OsiSolverInterface, 159 writeMps OsiCpxSolverInterface, 46 OsiGlpkSolverInterface, 46 OsiGlpkSolverInterface, 65 OsiGrbSolverInterface, 81 OsiMskSolverInterface, 107 OsiSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	OsiCpxSolverInterface, 43	whichWay
OsiGrbSolverInterface, 78 OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiXprSolverInterface, 191 SetRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 SetSolution OsiBabSolver, 16 SolverInterface, 158 WriteLp OsiSolverInterface, 159 writeMps OsiCpxSolverInterface, 46 OsiGlpkSolverInterface, 46 OsiGlpkSolverInterface, 65 OsiGrbSolverInterface, 81 OsiMskSolverInterface, 107 OsiSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158 SetSolverType	OsiGlpkSolverInterface, 62	
OsiMskSolverInterface, 104 OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType OsiSolverInterface, 104 OsiSolverInterface, 158 writeLpNative OsiSolverInterface, 159 writeMps OsiCpxSolverInterface, 46 OsiGlpkSolverInterface, 65 OsiGrbSolverInterface, 81 OsiMskSolverInterface, 107 OsiSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	OsiGrbSolverInterface, 78	-
OsiSolverInterface, 149 OsiXprSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType writeLpNative OsiSolverInterface, 159 writeMps OsiCpxSolverInterface, 46 OsiGlpkSolverInterface, 65 OsiGrbSolverInterface, 81 OsiMskSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	OsiMskSolverInterface, 104	•
OsiXprSolverInterface, 191 setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType OsiSolverInterface, 191 OsiSolverInterface, 194 OsiSolverInterface, 194 OsiSolverInterface, 195 OsiSpxSolverInterface, 194 OsiSolverInterface, 195 OsiSpxSolverInterface, 194 WriteMpsNative OsiSolverInterface, 158	OsiSolverInterface, 149	
setRowUpper OsiCpxSolverInterface, 43 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType writeMps OsiCpxSolverInterface, 46 OsiGlpkSolverInterface, 65 OsiGrbSolverInterface, 81 OsiMskSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158		-
OsiCpxSolverInterface, 43 OsiGpkSolverInterface, 62 OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 1049 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType OsiCpxSolverInterface, 46 OsiGpkSolverInterface, 81 OsiMskSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	•	
OsiGlpkSolverInterface, 62 OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiXprSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType OsiGrbSolverInterface, 81 OsiGrbSolverInterface, 107 OsiGrbSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	• •	•
OsiGrbSolverInterface, 77 OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType OsiGrbSolverInterface, 81 OsiMskSolverInterface, 107 OsiSolverInterface, 158 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	•	•
OsiMskSolverInterface, 103 OsiSolverInterface, 149 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 180 OsiSpxSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType OsiGrbSolverInterface, 107 OsiMskSolverInterface, 158 OsiSpxSolverInterface, 158 OsiSpxSolverInterface, 194 writeMpsNative OsiSolverInterface, 158	•	•
OsiSolverInterface, 149 OsiSpxSolverInterface, 158 OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 158 OsiSpxSolverInterface, 180 OsiSpxSolverInterface, 180 OsiSpxSolverInterface, 194 setSolution OsiBabSolver, 16 setSolverType OsiSolverInterface, 158	,	
OsiSpxSolverInterface, 178 OsiSpxSolverInterface, 180 OsiXprSolverInterface, 191 SetSolution OsiBabSolver, 16 SetSolverType OsiSolverInterface, 180 OsiXprSolverInterface, 194 writeMpsNative OsiSolverInterface, 158		
OsiXprSolverInterface, 191 setSolution OsiBabSolver, 16 setSolverType OsiSpXoSolverInterface, 194 writeMpsNative OsiSolverInterface, 158		
setSolution OsiBabSolver, 16 setSolverType WriteMpsNative OsiSolverInterface, 158	•	
OsiBabSolver, 16 OsiSolverInterface, 158 setSolverType		•
setSolverType Oslovermenace, 156		•
••		OsiSolverInterface, 158
UsiBabSolver, 16	OsiBabSolver, 16	