Linux操作系统分析 2基于x86的Linux启动代码分析

陈香兰 (xlanchen@ustc.edu.cn)

计算机应用教研室@计算机学院 嵌入式系统实验室@苏州研究院 中国科学技术大学 Fall 2010



Outline

① 基于x86的Linux启动代码分析

② 小结和作业

源代码来源

- 内核版本: 2.6.26
- ftp://ftp.kernel.org/pub/linux/kernel/v2.6/linux-2.6.26.tar.gz
 - 解压缩后,成功编译一次
 - 建立Source Insight工程
 - Windows+Source Insight
 - Wine+Source Insight
 安装wine: sudo apt-get install wine
 在wine中安装SourceInsight: wine XXX.exe

基于x86的Linux启动代码分析

- 了解linux的源码组织
 - 看目录结构
- 了解linux的内核代码结构
 - 看Makefile
- 了解基于x86的linux的boot image的结构
 - 看Makefile文件和链接描述文件
- 掌握x86的启动流程
 - 阅读启动源码文件

Linux-2.6.26

- 阅读linux目录下的README
 - 关于Linux的介绍(WHAT IS LINUX?)
 - 该版本内核支持的体系结构(ON WHAT HARDWARE DOES IT RUN?)
 - Linux源代码目录中的文档目录(DOCUMENTATION)
 - 如何配置、编译、安装
 - INSTALLING the kernel
 - BUILD directory for the kernel
 - CONFIGURING the kernel
 - COMPILING the kernel
 - 等等

Linux内核源代码中的主要子目录 |

- Documentation 内核方面的相关文档。
- arch 与体系结构相关的代码。
 对应于每个支持的体系结构,有一个相应的目录如x86、
 arm、alpha等。每个体系结构子目录下包含几个主要的子目录:
 - kernel 与体系结构相关的核心代码
 - mm 与体系结构相关的内存管理代码
 - lib 与体系结构相关的库代码
- include 内核头文件。
 对每种支持的体系结构有相应的子目录,如asm-x86、
 asm-arm、asm-alpha等。
 符号链接asm,如"asm-> asm-x86"。
 实际上,"#include 'asm/xxxx.h'"?

Linux内核源代码中的主要子目录 ||

- init 内核初始化代码。提供main.c,包含start_kernel函数。
- kernel 内核管理代码。
- mm 内存管理代码。
- ipc 进程间通讯代码。
- net 网络部分代码。
- lib 与体系结构无关的内核库代码。
- drivers设备驱动代码。每类设备有相应的子目录,如char、block、net等
- fs 文件系统代码。每个支持文件系统有相应的子目录, 如ext2、proc等。
- modules 可动态加载的模块。
- Scripts 配置核心的脚本文件。
- 等等



考虑Arch为i386 考察如下目录

- 观察Linux源码的根目录
- 观察arch目录
- 观察arch下的x86目录
 - arch/x86/boot
 - arch/x86/boot/compressed
 - arch/x86/kernel
- 观察Linux的init目录

阅读documentation/i386/boot.txt I

- 由于一些历史的原因,基于x86的Linux的启动比较复杂
- 这个文档(THE LINUX/I386 BOOT PROTOCOL)包含如下内容
 - ① Linux/i386的启动协议(若干个)
 - ② 内存布局图 (MEMORY LAYOUT)
 - ③ 实模式下的内核头结构及细节 (THE REAL-MODE KERNEL HEADER)
 - 内核的命令行 (THE KERNEL COMMAND LINE)
 - MEMORY LAYOUT OF THE REAL-MODE CODE
 - 启动配置示例 (SAMPLE BOOT CONFIGURATION)
 - ▼ 装载Linux的剩余部分 (LOADING THE REST OF THE KERNEL)



阅读documentation/i386/boot.txt II

- 特殊的命令行参数 (SPECIAL COMMAND LINE OPTIONS)
- 运行内核 (RUNNING THE KERNEL)
- 高级启动回调函数 (ADVANCED BOOT LOADER HOOKS)
- 32-bit BOOT PROTOCOL

阅读Linux源码根目录下的Makefile

找到缺省目标all

```
# The all: target is the default when no target is given on the # command line.
# This allow a user to issue only 'make' to build a kernel including modules # Defaults vmlinux but it is usually overridden in the arch makefile all: vmlinux
```

找到vmlinux目标,并阅读

```
解释:关于
$(call if_changed_rule, vmlinux__)
↓
rule vmlinux
```

```
# Link of vmlinux
# If CONFIG KALLSYMS is set .version is already updated
# Generate System.map and verify that the content is consistent
# Use + in front of the vmlinux version rule to silent warning with make -j2
# First command is ':' to allow us to use + in front of the rule
define rule_vmlinux
        $(if $(CONFIG KALLSYMS)..+$(call cmd.vmlinux version))
        $(call cmd.vmlinux )
        (0) echo 'cmd (0) := (cmd \ vmlinux)' > ((0)/.$((0)/.$(0).cmd)
        $(0)$(if $($(quiet)cmd sysmap),
          echo ' $($(quiet)cmd_sysmap) System.map' &&)
        $(cmd_sysmap) $@ System.map;
        if [ $$? -ne 0 1: then
                rm -f $0:
                /bin/false:
        fi:
        $(verify kallsyms)
endef
```

• 链接描述文件?

- 链接顺序:
 - vmlinux-init
 - vmlinux-main

● 参见 "Documentation/kbuild/makefiles.txt"

--- 6.7 Custom kbuild commands

```
When kbuild is executing with KBUILD VERBOSE=0 then only a shorthand
of a command is normally displayed.
To enable this behaviour for custom commands kbuild requires
two variables to be set:
quiet cmd <command> - what shall be echoed
      cmd <command> - the command to execute
Example:
        quiet cmd image = BUILD $@
              cmd image = $(obj)/tools/build $(BUILDFLAGS) \
                                             $(obi)/vmlinux.bin > $@
        targets += bzImage
        $(obj)/bzImage: $(obj)/vmlinux.bin $(obj)/tools/build FORCE
                $(call if changed.image)
                @echo 'Kernel: $@ is readv'
When updating the $(obj)/bzImage target the line:
BUTI D
        arch/i386/boot/bzImage
will be displayed with "make KBUILD VERBOSE=0".
```

• 注意:

- vmlinux-init
- vmlinux-main

```
vmlinux-init := $(head-y) $(init-y)
vmlinux-main := $(core-y) $(libs-y) $(drivers-y) $(net-y)
vmlinux-all := $(vmlinux-init) $(vmlinux-main)
```

vmlinux-dirs

主要目标文件的编译

vmlinux

```
# The actual objects are generated when descending,
# make sure no implicit rule kicks in
$(sort $(vmlinux-init) $(vmlinux-main)) $(vmlinux-lds): $(vmlinux-dirs) :
  # Handle descending into subdirectories listed in $(vmlinux-dirs)
  # Preset locale variables to speed up the build process. Limit locale
  # tweaks to this spot to avoid wrong language settings when running
  # make menuconfig etc.
  # Error messages still appears in the original language
  PHONY += $(vmlinux-dirs)
  $(vmlinux-dirs): prepare scripts
         $(0)$(MAKE) $(build)=$@
 vmlinux-dirs
                  := $(patsubst %/,%,$(filter %/, $(init-y) $(init-m) \
                       $(core-v) $(core-m) $(drivers-v) $(drivers-m) \
                       $(net-y) $(net-m) $(libs-y) $(libs-m)))
```

不妨以core-y为例,观察体系相关和体系无关部分的代码是 如何被包含进来的

x86的启动文件

- 根据vmlinux-init找到head-y, init-y
 - 关于arch/x86/Makefile的引入 根Makefile中以include的方式包含了X86体系结构相关部分 的Makefile

```
# Read arch specific Makefile to set KBUILD_DEFCONFIG as needed.
# KBUILD_DEFCONFIG may point out an alternative default configuration
# used for 'make defconfig'
include $\forall \text{synctree} / \text{synctr
```

• 在这个Makefile中 161 head-y := arch/x86/kernel/head_\$(BITS).o 162 head-y += arch/x86/kernel/head\$(BITS).o 163 head-y += arch/x86/kernel/init_task.o

- 其中,变量BITS为32或者64,我们只考虑32位的情况
- 在根Makefile中

- 可以看到vmlinux包含如下内容
 - i386/kernel/head_32.S等 +
 - init/main.c + init/version.o +
 - CORE_FILES + DRIVERS +
 - NETWORKS + LIBS

为便于阅读,了解关于命令输出的相关内容

```
# Beautify output
# Normally, we echo the whole command before executing it. By making
# that echo $($(quiet)$(cmd)), we now have the possibility to set
# $(quiet) to choose other forms of output instead, e.g.
         quiet cmd cc o c = Compiling $(RELDIR)/$@
         cmd_cc_o_c = $(CC) $(c_flags) -c -o $@ $<
# If $(quiet) is empty, the whole command will be printed.
# If it is set to "quiet ", only the short version will be printed.
# If it is set to "silent_", nothing wil be printed at all, since
# the variable $(silent cmd cc o c) doesn't exist.
# A simple variant is to prefix commands with $(0) - that's useful
# for commands that shall be hidden in non-verbose mode.
        $(0)ln $@:<
# If KBUILD VERBOSE equals 0 then the above command will be hidden.
# If KBUILD VERBOSE equals 1 then the above command is displayed.
ifeq ($(KBUILD VERBOSE).1)
 quiet =
 0 =
else
 quiet=quiet
 0 = 0
endif
```

make XXX

- 若make install
 - 在x86的Makefile中有install规则
- 若make bzlmage/zlmage等,则要找到对应的目标然后进行
 - bzlmage/zlmage可在arch/x86的Makefile中找到相应规则
 - 其他的zXXX/bzXXX也都依赖于boot下的zImage/bzImage
- 它们最终都找到i386/boot/Makefile

考虑boot bzlmage I

- Make bzlmage …
- 在arch/X86/Makefile中

- z代表压缩; b代表大内核
- 到boot目录下的Makefile
 - 观察boot目录和boot下的Makefile
 - 观察compressed目录及该目录下的Makefile



考虑boot bzlmage II

最后:

- 在Linux内核源代码顶层目录下生成一个vmlinux
 - arch/x86/kernel/head_32.S···+init/main.c+···
- compressed下的vmlinux为
 - compressed/head_32.S + 压缩后的顶层目录下的vmlinux ···
- boot下的bzlmage为
 - boot下header.S等(即setup.bin)+compressed/vmlinux

x86的启动(小结)

- boot/header.S等
- compressed/head_32.S等
- kernel/head_32.S等
- init/main.c

1386机器的启动层次

- BIOS (Basic I/O System)
- 2 Bootloader
 - 软盘启动
 - 硬盘启动
 - 嵌套boot loader
 - 例如:grub、lilo、......
- Linux kernel

Bootloader必须完成内核代码的加载,然后跳转到入口处运行

BIOS I

· 加电,RESET引脚

CPU加电后,将会初始化程序指针到某个约定好的地址上取指令运行,在这个地指处,往往安排了启动相关的代码,例如BIOS或者reset向量处理入口

- 初始化寄存器; CS:IP = 0xfffffff0, in ROM
- ROM←□BIOS
- · BIOS启动内容
 - POST (上电自检)
 - 初始化硬件设备
 - 搜索一个操作系统来启动 根据配置,操作系统可以在软盘/硬盘/CD_ROM上
 - 把对应设备的第一个扇区的内容(bootloader或部分)拷贝到RAM(0x7c00)处
 - 跳转到0x7c00处执行

Bootloader (引导装载程序)

 BIOS调用Bootloader把操作系统内核映像装载到RAM中 考虑IBM PC的启动

软盘启动:

BIOS拷贝第一个扇区的内容(bootsect)到RAM(0x7c00)中

硬盘启动:

硬盘的第一个扇区:主引导记录MBR, Master Boot Record

- MBR存储该硬盘的分区表+ 一小段引导程序
- 这个引导程序用来装载OS所在分区的第一个扇区(boot loader)的内容到RAM中
- 这个引导程序也可以被替换

Linux的BootLoader

- 典型的有:LILO和Grub
- LILO (Linux Loader)
 - 可以被安装在OS分区的第一个扇区(启动扇区)
 - · 也可以代替MBR中的引导程序
- 事实上,LILO的代码尺寸大于一个扇区,因此被分成两个部分
 - · MBR或启动扇区部分
 - 剩余部分
- 第一部分也被BIOS装载到RAM中0x7c00的位置
- 第一部分在运行时将自己完整的装载到RAM中
- 通常LILO或GRUB会显示一个已安装操作系统的列表
 - 按照用户的选择(或者按照缺省项)装载目标操作系统运行
 - 可能装载操作系统指定的启动代码运行(嵌套的情况)
 - 可能直接装载操作系统内核来运行

LILO的OS启动过程

- 显示 "Loading…"
- header内容被装载到RAM的0x90000
- 操作系统内核的其他内容被装载到
 - 对于小内核: 0×10000 (即64K处), 称为低装载
 - 对于大内核: 0x100000 (即1M处), 称为高装载
- 跳转到0×90200处运行

1386内核的启动

• 启动方式

• 软盘启动:Linux2.6.26不支持

• 硬盘启动:从header的_start开始运行


BIOS

0x7c00: LILO, Grub等boot loader

0x90200: Header: _start(即0x200偏移处)

在进入源代码讲解之前,先看一下加载;386内核的内存布局图

硬件角度: 1386实模式下的内存布局图




1386内核从实模式开始启动运行

什么是实模式?

- 实模式是为了兼容早期的CPU而设置的
- i386系统总是始于实模式
- 实模式下
 - 地址总线:20位
 - 内存范围:0~1MB
 - 逻辑地址 = 段地址 + 段内偏移
 - 段地址 = 段寄存器中的值*16 (或左移4位)
 - 段寄存器: cs/ds/es/fs/gs
 - 段寄存器长度:16bit
 - 段长:16位偏移=64KB

加载1386内核的内存布局图

- zlmage/lmage的内核加载器所使用的经典的内存布局 (1M=0x100000)
- 参见boot.txt



Do not use. Reserved for BIOS EBDA.

For use by the kernel real-mode code.

The kernel real-mode code.

The kernel legacy boot sector.

The bulk of the kernel image.

<- Boot sector entry point 0000:7C00

硬盘启动, 两阶段引导

- 装载LILO (LInuxLOader)
 - 第一个扇区
 - …
- 装载LINUX
 - header.S等→0x90000,其中_start在0x90200处
 - 系统
 - 0×10000
 - 0×100000
- 跳转到_start

启动第一步,小结

- 总之,在跳转到header.S的_start的时候,内存里面的代码布 局为
 - 0x90000: header.S 前512字节内容
 - 0x90200: header.S 的_start及其后
 - 低装载:
 - 0x10000: 带解压的vmlinux
 - 高装载:
 - 0×100000: 带解压的vmlinux
- 实模式下的内核头结构
 - 包括512字节的最后和_start 之后的一些位置
 - 从偏移0x1F1开始,具体描述参 见documentation/i386/boot.txt


Header.S之_start: 0x90200

- __start:
 - 跳转到start_of_setup
 - 检查setup的signature
 - ·清除BSS段
 - 跳转到main执行
- 其中,Main用来初始化硬件设备并为内核程序的执行建立 环境
 - 内存检测、键盘、视频 、...
 - go_to_protected_mode

关于保护模式

- 在setup.bin中,从实模式→保护模式
- 保护模式下,地址总线32位,访存范围为4GB
- 原来的段寄存器现在被称作段选择子,与GDT表配合使用
 - GDT表由gdtr指示其位置和长度
 - 使用特殊的指令进行操作:sgdt/lgdt

图示



段描述符的格式

Data Segment Descriptor



Code Seament Descriptor



System Segment Descriptor

	I I I I I I I I I I I I I I I I I I I	D S	39 38 37 36 35 34 33 32
BASE(24-31)	G 0 (16-19)	1 P = TYPE	BASE (16-23)
BASE(0-15)	LIMIT (0	⊢15)
31 30 20 28 27 26 25 2	4 23 22 21 20 19 18 17 16	15 14 13 12 11 10 9 8	7 6 5 4 3 2 1 0

- 一般装载gdt和idt之后,要重新装载段寄存器
 - cs ` ds ` es ` fs ` gs
 - · cs通常通过一条长跳转指令装载
 - 其他数据段寄存器直接设置
 - 如在arch/x86/boot/header.S

```
54
           limp
                    $BOOTSEG, $start2
55
56 start2:
57
           movw
                   %cs, %ax
58
           movw
                  %ax. %ds
59
                  %ax. %es
           movw
60
                  %ax. %ss
           movw
61
           xorw
                   %SD. %SD
62
           sti
63
           cld
64
65
                    $bugger_off_msg, %si
           movw
66
```

go_to_protected_mode I

- arch/x86/boot/main.c中,main函数最后调用go_to_protected_mode函数
 - arch/x86/boot/pm.c中

```
void go to protected mode(void)
        /* Hook before leaving real mode, also disables interrupts */
        realmode switch hook():
        /* Move the kernel/setup to their final resting places */
        move kernel around();
        /* Enable the A20 gate */
        if (enable a20()) {
                puts("A20 gate not responding, unable to boot...\n");
                die();
        /* Reset coprocessor (IGNNE#) */
        reset coprocessor():
        /* Mask all interrupts in the PIC */
        mask all interrupts();
        /* Actual transition to protected mode... */
        setup idt();
        setup qdt();
        protected mode jump(boot params.hdr.code32 start,
                            (u32)\&boot\ params + (ds() << 4));
```

go_to_protected_mode II

● 这里是code32_start的定义在

```
# Kernel attributes; used by setup. This is part 1 of the
        # header, from the old boot sector.
        .section ".header", "a"
        .alobl hdr
hdr:
setup sects:
               .byte SETUPSECTS
root flags: .word ROOT RDONLY
              .long SYSSIZE
syssize:
ram_size: .word RAMDISK
vid_mode: .word SVGA_MODE
root_dev: .word ROOT_DEV boot_flag: .word 0xAA55
        # offset 512, entry point
        .globl _start
start:
```

go_to_protected_mode III

● main函数在一开始就调用了copy_boot_params

```
static void copy boot params(void)
        struct old cmdline {
                u16 cl magic:
                u16 cl offset;
        };
        const struct old cmdline * const oldcmd =
                (const struct old cmdline *)OLD CL ADDRESS;
        BUILD BUG ON(sizeof boot params != 4096);
        memcpy(&boot params.hdr, &hdr, sizeof hdr);
        if (!boot params.hdr.cmd line ptr &&
            oldcmd->cl magic == OLD CL MAGIC) {
                /* Old-style command line protocol. */
                u16 cmdline sea:
                /* Figure out if the command line falls in the region
                   of memory that an old kernel would have copied up
                   to 0x90000... */
                if (oldcmd->cl offset < boot params.hdr.setup move size)</pre>
                        cmdline seg = ds();
                else
                        cmdline seq = 0x9000;
                boot params.hdr.cmd line ptr =
                        (cmdline seg << 4) + oldcmd->cl offset;
```

arch/boot/compressed

- 具有自解压功能的vmlinux.bin
 - zlmage中,在0x1000处
 - 关于100000, 10000, 1000 (参见move_kernel_arround)
 - bzlmage中,在0x100000处
- compressed/head_32.S的startup_32
 - 初始化段寄存器和一个临时堆栈
 - · 初始化BSS段
 - 解压缩decompress_kernel
 - 无论高装载或低装载→解压缩后,都在物理地址0x100000 (1MB)处
 - 跳转到0×100000处
- linux-2.6.26\arch\x86\configs\i386_defconfig中定义 CONFIG_PHYSICAL_START=0x100000

- 解压缩后, vmlinux在0x100000处
 - 根据vmlinux.lds,vmlinux的地址被链接 为0xc0000000+0x100000处
 - 如何正确运行呢?
- 最初是实模式,然后进入保护模式,还没有分页、映射好
- 期间,
 - 没有长跳转,只使用采用相对地址的近距离跳转
 - 不使用符号名

Kernel/Head_32.S

• Startup_32

- 初始化段寄存器
- 设置页目录和页表,分页
- 建立进程0的内核堆栈
- Setup_idt
- 拷贝系统参数
- 识别处理器
- GDT \ IDT
- i386_start_kernel

如何进入start_kernel?

???如何从0~8M的空间中转入3G以上的地址空间中运行的???

```
void __init i386_start_kernel(void)
{
      start_kernel();
}
```

关于页目录和页表的定义及初始化 |

```
arch/x86/kernel/head_32.S中定义了swap_pg_dir

/*
    * BSS section
    */
    * section ".bss.page_aligned","wa"
```

```
"section ".bss.page_aligned","wa"
.align PAGE_SIZE_asm
#ifdef CONFIG_X86_PAE
swapper_pg_pmd:
.fill 1024*KPMDS,4,0
#else
ENTRY(swapper_pg_dir)
.fill 1024,4,0
#endif
swapper_pg_fixmap:
.fill 1024,4,0
ENTRY(empty_zero_page)
.fill 4096,1,0
```

arch/x86/kernel/vmlinux_32.lds.S文件中

关于页目录和页表的定义及初始化 ||

分页使能

```
* Enable paging
       movl $pa(swapper pg dir), %eax
       movl %eax,%cr3
                              /* set the page table pointer.. */
       movl %cr0,%eax
       orl $X86 CR0 PG.%eax
       movl %eax.%cr0
                       /* ..and set paging (PG) bit */
       limp $ BOOT CS.$1f /* Clear prefetch and normalize %eip */
1:
在使用页目录和页表之前,首先要进行页目录和页表的初始化(部分)
* This is how much memory *in addition to the memory covered up to
* and including end* we need mapped initially.
* We need:
   - one bit for each possible page, but only in low memory, which means
      2^32/4096/8 = 128K \text{ worst case } (4G/4G \text{ split.})
   - enough space to map all low memory, which means
      (2^32/4096) / 1024 pages (worst case, non PAE)
     (2^32/4096) / 512 + 4 pages (worst case for PAE)
   - a few pages for allocator use before the kernel pagetable has
      been set up
* Modulo rounding, each megabyte assigned here requires a kilobyte of
* memory, which is currently unreclaimed.
* This should be a multiple of a page.
LOW PAGES = 1 << (32 - PAGE SHIFT asm)
```

关于页目录和页表的定义及初始化 |||

```
* To preserve the DMA pool in PAGEALLOC kernels, we'll allocate
 * pagetables from above the 16MB DMA limit, so we'll have to set
 * up pagetables 16MB more (worst-case):
 */
#ifdef CONFIG DEBUG PAGEALLOC
LOW PAGES = LOW PAGES + 0x1000000
#endif
#if PTRS PER PMD > 1
PAGE TABLE SIZE = (LOW PAGES / PTRS PER PMD) + PTRS PER PGD
#else
PAGE TABLE SIZE = (LOW PAGES / PTRS PER PGD)
#endif
BOOTBITMAP SIZE = LOW PAGES / 8
ALLOCATOR SLOP = 4
INIT MAP BEYOND END = BOOTBITMAP SIZE + (PAGE TABLE SIZE + ALLOCATOR SLOP)*PAGE SIZE asm
 * Initialize page tables. This creates a PDE and a set of page
 * tables, which are located immediately beyond end. The variable
 * init pg tables end is set up to point to the first "safe" location.
 * Mappings are created both at virtual address 0 (identity mapping)
 * and PAGE OFFSET for up to end+sizeof(page tables)+INIT MAP BEYOND END.
 * Note that the stack is not yet set up!
 */
#define PTE ATTR
                        0x007
                                         /* PRESENT+RW+USER */
#define PDE ATTR
                        0x067
                                         /* PRESENT+RW+USER+DIRTY+ACCESSED */
#define PGD ATTR
                        0x001
                                         /* PRESENT (no other attributes) */
```

关于页目录和页表的定义及初始化 IV

```
page pde offset = ( PAGE OFFSET >> 20);
        movl $pa(pq0), %edi
        movl $pa(swapper pg dir), %edx
        movl $PTE ATTR, %eax
10:
        leal PDE ATTR(%edi),%ecx
                                             /* Create PDE entry */
        movl %ecx.(%edx)
                                             /* Store identity PDE entry */
        movl %ecx,page_pde_offset(%edx)
                                              /* Store kernel PDE entry */
        addl $4.%edx
        movl $1024. %ecx
11:
        stosl
        addl $0x1000,%eax
        loop 11b
         * End condition: we must map up to and including INIT MAP BEYOND END
         * bytes beyond the end of our own page tables; the +0x007 is
         * the attribute bits
        leal (INIT MAP BEYOND END+PTE ATTR)(%edi).%ebp
        cmpl %ebp.%eax
        ib 10b
        movl %edi.pa(init pg tables end)
        /* Do early initialization of the fixmap area */
        movl $pa(swapper pg fixmap)+PDE ATTR,%eax
        movl %eax,pa(swapper pg dir+0xffc)
#endif
        imp 3f
```

关于kernel/head_32.S的内核堆栈

```
/* Set up the stack pointer */
lss stack_start,%esp
```

控制寄存器(Control Registers)

- CR0
- CR1
- CR2
- CR3

大多与内存相关

CR0 I

- CR0, MSW register (Machine Status Word, 32-bit version)
 - 包含系统控制位,用于控制操作模式和状态

31 30 29	30 19 18 17 16 15	6 5 4 3 2 1 0	
P C N	A W P	N E T S M P E	R0

- Instruction: Imsw
- To turn on the PE-bit (enables protected-mode)
 - LINUX' setup.S (回版本):
 movw \$1, %ax
 lmsw %ax
 jmp flush_instr // why?
 flush instr:

CR₀ II

• in Linux-2.6.26/arch/x86/boot/pmjump.S

```
movl
                %cr0, %edx
        orb
               $X86_CR0_PE, %dl
                                         # Protected mode
        mov1
                %edx, %cr0
                1f
                                         # Short jump to serialize on 386/486
        jmp
1:
        # Transition to 32-bit mode
        .byte
                0x66, 0xea
                                         # ljmpl opcode
2:
        .long
                in_pm32
                                         # offset
```

CR1 \ CR2 \ CR3

- CR1:保留
- CR2:在缺页异常的时候,记录缺页地址



CR3:记录页目录所在的物理地址和两个标记(PCD & PWT)



小结

① 基于x86的Linux启动代码分析

② 小结和作业

作业2

- i386实模式下是如何解决20位地址空间和16位段寄存器之间 的不匹配问题的?
- i386保护模式下的段寄存器的内容与实模式下段寄存器的内容一样么?如何解释?

Project2

- 基于x86的linux-2.6.26的启动分析
 - 首先进行Makefile的分析,了解bzlmage的代码结构
 - 考虑grub为启动引导程序,分析代码的启动过程。
- 提供详细分析报告

Thanks!

The end.