
The Legend Of Random



www.TheLegendOfRandom.com

Tutorial #4: Using Olly, Part 2

by R4ndom on Jun.05, 2012, under Reverse Engineering, Tutorials

Introduction

In this tutorial we are going to continue with learning to use Olly. We will use the same program used in the last tutorial (I will also include it in the downloads of this one again).

DIIG

As I told you in an earlier tutorial, DLLs are loaded by the system loader when you start your app. Let me be more specific this time. DLL (Dynamic Link Libraries) are collections of function, usually provided by Windows (though they can be provided by anyone) that contain functions that are used a lot in windows programs. They are also functions that make it easier for programmers to perform what would otherwise be tedious, repetitive tasks.

For example, converting a string to all uppercase is something that needs to be done in a lot of applications. You have three choices if your app uses this functionality multiple times in your app; 1) you can code it yourself and put it in your app. The problem is, what if you know that your next app is also going to use this same function many times? You would need to cut and paste it into every app you make that uses it! 2) You can create your own library that any app you make can call. In this case, you would create a DLL that you would include with every app, and this DLL would have convertToUpper, as well as other common functions, that your apps can call, thereby only having to code it once. Another good thing about this is, say you come up with a nice optimization for converting a string to all uppercase. In the first example, you would need to copy this new code to every app that uses it, but in the the case of a common DLL, you would just change the code in the DLL and every app that used that DLL would get the benefit of the faster code. Sweet. This was really the reason DLLs came in to being.


The last option is to use one of the thousands of functions that Windows has included in it's own set of DLLs. There are many benefits to this. The first is that the coders at Microsoft have been spending years optimizing their functions, so chances are they're better than yours. Secondly, you do not have to include any of your own DLLs with your app as all windows systems have these DLLs built in. And lastly, if Windows decides to change their operating system, your custom DLLs may not be compatible with the new operating system, while if you use Windows DLLs, they are guaranteed to be compatible.

How DLLs Are Used


Now that you know what a DLL is, let's talk about how they're used. A DLL is basically just a library of functions that your app can call. When you first load your app, the Windows Loader checks a special section of the PE Header (remember the PE Header?) and checks to see what functions your app calls and from what DLL's these functions reside in. After loading your app into memory, it then iterates through these DLLs and loads each one into your app's memory space. It then goes through all of your app's code and injects the correct address of where it put these DLL functions into your program everywhere your program calls that function. For example, if one of your first calls is to convert a buffer of letters to uppercase by calling StrToUpper in the kernel32 DLL (just an example), the loader will find the place it loaded the kernel32 DLL, find the address of the StrToUpper function, and inject that address into the lines of code in your app that call that function. Your app will then call into the kernel32's DLL space in memory, perform the StrToUpper function, and then return back to your program.


Let's see this in action. Load the FirstProgram.exe program included with this tutorial into Olly. Olly will break at the first line of code (from now on called the Entry Point – this is important as this is what the PE Header calls it for when we start discussing that in detail.)





If you look at the second line of the code, you will see a call to a function called kernel32.GetModuleHandleA. First off, let's see what this function does. In case you did not get it in the last tutorial, I have included in the downloads for this tutorial a file called WIN32.HLP as well as a text document explaining how to install it into Olly. This file allows you to right-click on a Windows API you are unfamiliar with and it will show you what the API does. You may need to restart Olly after you copy it over. Right click on GetModuleHandleA and select "Help on Symbolic Name". Olly will bring up a cheat sheet of this API:





So, basically, this functions gets a handle to a window we are going to create. In Windows, if you want to do ANYTHING to a window (or pretty much any other object for that matter) you must get a handle to it. This is basically just a unique identifier so Windows knows which object you're referring to.

Close the help window and let's see exactly where this call is going. As Olly has tried to help and replaced the actual address of the GetModuleHandleA with the name of the function, let's see what address it resides at. Click once on the GetModuleHandleA call line and hit the space bar. That will open up the assembly window:



This window serves two purposes; it first shows you the exact assembly language instructions that are being computed (in case Olly has helpfully replaced the address) and secondly it allows us to edit the assembly language. We will not be doing any editing until next tutorial, so for this time lets just look at the address: 4012D6. There are two ways to jump to this address (without actually running the code) to see what's there. You can highlight the "CALL GetModuleHandleA" line and hit "Enter". You can also hit Ctrl-G and enter the address manually. Let's try the first way- select the line at address 401002 (in the third column with the actual instruction in it) and click enter, and you will be taken to the code that that call has called into:

004012D6	\$- FF25 24204000	JMP DWORD PTR DS:[<&kernel32.GetModuleHandleA>] kernel32.GetModuleHandleA	
004012DC 004012E2	\$- FF25 00204000 \$- FF25 0C204000	<pre>JMP DWORD PTR DS:[<%comct 32.ImageList_Add>]</pre>	
004012E2	\$- FF25 06204000 \$- FF25 08204000	<pre>JMP DWORD FIR DS:[<&comctl32.ImageList_Create/]</pre>	
004012EE	\$- FF25 04204000	JMP DWORD PTR DS:[<&comct 32.In tCommonControls comct 32.In tCommonControl	s
004012F4	00	DB 00	
004012F5	99	DB 00	
004012F6	00	DB 00	
004012F7 004012F8	00 00	DB 00 DB 00	
004012F9	90	DB 99	
004012FA	00 00 00	DB 00	
004012FB	00	DB 00	
004012FC	00	DB 00	

Now this is interesting: it sure doesn't look like code that would perform GetModuleHandleA. It look more like a series of jumps. There is a very good reason for this, but unfortunately, one that requires a little explanation.

The Address Jump Table

The first thing to know is that DLLs do not always get loaded into memory at the same spot. The Windows loader, which is responsible for loading your app and all of the support DLLs that your program needs, is allowed to change where in memory these DLLs can be loaded (and frankly, can even change where your app can be loaded, but we'll get to that later). The reason for this is let's say a Windows DLL, one of the

first ones loaded, is mapped into address 80000000. Well let's say you have also included a DLL in your app that wants to be loaded at that same address. Since both DLLs can't be loaded at the same address, the loader must move one of these DLLs to another address. This happens all the time, and is called relocation

Here's the problem: When you first coded your application and wrote an instruction that called GetModuleHandleA, the compiler knew exactly where the proper DLL was, so it put an address into that instruction, something like "CALL 800000000". Now, when your program is loaded into memory, it still has this call to 800000000 (I'm being overly simple here ②, but what if the loader has decided to move this DLL to 80000E300? Your call will call the wrong function!

The way the PE file, and hence the Windows file, got around this problem was by creating a jump table. What this means is that when your code was first compiled, every call to GetModuleHandleA pointed to a single location in your app, and this single location immediately jumps to an arbitrary address (which will eventually become the proper address). In fact, all function calls into DLLs use this same technique; they each call a specific address that then immediately jumps to an arbitrary address. When the loader loads in all the DLLs, it goes through this 'jump table' and replaces all of the arbitrary address with the real address of the functions in the memory. This is what a jump table looks like after all of the real addresses have been populated:

```
DWORD PTR DS:[(&gdi32.DeleteObject)]

DWORD PTR DS:[(&user32.CreateDialogParamA)]

DWORD PTR DS:[(&user32.DefWindowProcA)]

DWORD PTR DS:[(&user32.DestroyWindow]]

DWORD PTR DS:[(&user32.DestroyWindow]]

DWORD PTR DS:[(&user32.DestroyWindow]]

DWORD PTR DS:[(&user32.GetDigItem)]

DWORD PTR DS:[(&user32.GetDigItem)]

DWORD PTR DS:[(&user32.GetDigItem)]

DWORD PTR DS:[(&user32.DialogMessageA)]

DWORD PTR DS:[(&user32.LoadConA)]

DWORD PTR DS:[(&user32.LoadConA)]

DWORD PTR DS:[(&user32.LoadIconA)]

DWORD PTR DS:[(&user32.LoadIconA)]

DWORD PTR DS:[(&user32.ResisterClassExA)]

DWORD PTR DS:[(&user32.RegisterClassExA)]

DWORD PTR DS:[(&user32.RegisterClassExA)]

DWORD PTR DS:[(&user32.SetDigItemMessageA)]

DWORD PTR DS:[(&user32.SetDigItemMessageA)]

DWORD PTR DS:[(&user32.SetDigItemMessageA)]

DWORD PTR DS:[(&user32.SetDigItemMessageA)]

DWORD PTR DS:[(&user32.TranslateMessageA)]

DWORD PTR DS:[(&user32.TranslateMessageA)]

DWORD PTR DS:[(&user32.SetDousA)]

DWORD PTR DS:[(&user32.SetCousA)]

DWORD PTR DS:[(&user32.SetCousA)]
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               gdi32.DeleteObject
user32.CreateDialogParamA
user32.DefWindowProoA
user32.DestroyWindow
user32.DispatchMessageA
user32.GetDlgItem
user32.GetDlgItem
user32.GetDlgItemTextA
user32.IsDialogMessageA
user32.LoadIconA
user32.LoadIconA
user32.LoadIconA
user32.LoadIconA
user32.PostQuitMessage
user32.PessageBoxA
user32.SetDlgItemTextA
user32.SetDlgIte
                                                                                                                                                                                                                                                                                                                                                                     14284000
74294000
74294000
76294000
68294000
68294000
64294000
55294000
48294000
38294000
34294000
34294000
44294000
54294000
54294000
64294000
64294000
64294000
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          JMP
JMP
JMP
JMP
                                                                                                                                                                                                                                                                            0401264
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          JMP
JMP
JMP
JMP
0401276
0401270
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          0401294
0401294
0401296
0401296
0401292
0401282
0401288
0401284
0401204
0401200
0401200
0401200
0401200
0401288
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          JMP
JMP
JMP
JMP
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          JMP
JMP
JMP
JMP
JMP
JMP
04012EE
04012F4
04012F5
04012F5
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              04204000
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          DB
DB
DB
DB
           34012
```

Just as this is sort of a complicated idea, let me give you an example. We will write a short program, using completely arbitrary information (just to prove our point) that calls a function in kernel32.dll called ShowMarioBrosPicture. Here is our program (in no specific language):

After compiling this, the calls to functions will be replaced by actual address and will look something like this (again, not in any specific language):

and down below would be our jump table (in this case, only showMarioBrosPicture is in it) 402000 JMP XXXXXXXX

Now, since out program has no idea where showMarioBrosPicture is going to be (or where the kernel32 DLL file is going to be for that matter), the compiler of our program is just going to fill in X's for the actual address call (not really but you get the idea).

Now, when the Windows loader loads our app, it first loads our binary into memory, complete with the jump table, but the jump table doesn't have any real addresses in it yet. It then starts loading DLLs into our memory space, and finally starts figuring out where all the functions reside. Once it finds the address for showMarioBrosPicture, it is going to go into our jump table and replace the X's with the actual address of that function. Let's say the showMarioBrosPicture address was at 77CE550A. Our jump table code would then be replaced with:

402000 JMP 77CE550A.

Now, since Olly can figure out that this is pointing to showMarioBrosPicture, it will helpfully go into our jump table and actually show it as:

402000 JMP DWORD PTR DS:[<&kernel32.showMarioBrosPicture>]

Now, let's go back and look at the jump table in our FirstProgram app:

```
DWORD PTR DS:[(&gdi32.DeleteObject)]
DWORD PTR DS:[(&user32.CreateDialogParamA)]
DWORD PTR DS:[(&user32.DefWindowProcA)]
DWORD PTR DS:[(&user32.DefWindowProcA)]
DWORD PTR DS:[(&user32.DestroyWindow]]
DWORD PTR DS:[(&user32.GetDlgltem)]
DWORD PTR DS:[(&user32.GetDlgltem)]
DWORD PTR DS:[(&user32.GetDlgltem)]
DWORD PTR DS:[(&user32.IsOialogMessageA)]
DWORD PTR DS:[(&user32.IsOialogMessageA)]
DWORD PTR DS:[(&user32.LoadCursorA)]
DWORD PTR DS:[(&user32.LoadCursorA)]
DWORD PTR DS:[(&user32.LoadIcnaA)]
DWORD PTR DS:[(&user32.LoadIcnaA)]
DWORD PTR DS:[(&user32.DestGursorA)]
DWORD PTR DS:[(&user32.DestGursorA)]
DWORD PTR DS:[(&user32.SetDlgltemMessageA)]
DWORD PTR DS:[(&user32.TranslateMessageA)]
DWORD PTR DS:[(&user32.SetDlgltemMessageA)]
DWORD PTR DS:[(&user32.SetDlgltemMessageA)]
DWORD PTR DS:[(&user32.SetDlgltemA)]
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  gdi32.DeleteObject
user32.CreateDialogParamA
user32.DefWindowProcA
user32.DefWindowProcA
user32.DestroyWindow
user32.DestroyWindow
user32.GetDlgItem
user32.GetDlgItem
user32.GetDlgItemTextA
user32.IsDialogMessageA
user32.LoadIconA
user32.LoadIconA
user32.LoadIconA
user32.LoadIconA
user32.PessageBoxA
user32.PessageBoxA
user32.SetDlgItemTextA
u
                                                                                                                                                                                                                                                                                                                                                                                                             14294000
74294000
74294000
62294000
62294000
64294000
52294000
52294000
34294000
34294000
34294000
34294000
34294000
44294000
42294000
42294000
42294000
52294000
52294000
52294000
                                                                                                                                                                                                                                                                                               75-
5-
5-
5-
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           JMP
                                                                                                                                                                                                                       .IMP
         3401
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       JMP
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  JMP
JMP
JMP
JMP
JMP
0401288
040128E
0401294
040129A
04012A0
04012A6
04012AC
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       JMP
JMP
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  04012HC
04012B2
04012BB
04012BE
04012C4
04012CA
04012D0
04012D6
04012DC
04012E2
04012E8
04012EE
04012F4
                                                                                                                                                                                                                                                                                                                                                                                                                       24204000
00204000
0C204000
08204000
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  JMP
JMP
JMP
JMP
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              DS:[<&comct|32.ImageList_Destroy>
DS:[<&comct|32.InitCommonControls]
    04012F9
```

When this program was first coded, all of these functions were called in various DLLs, but the compiler did not know where these functions were going to be placed in memory when our program was run, so it would have created something that looked (though not exactly) like this:

```
40124C JMP XXXXX // gdi32.DeleteObject
401252 JMP XXXXX // user32.CreateDialogParamA
401258 JMP XXXXX // user32.DefWindowProcA
40125E JMP XXXXX // user32.DestroyWindow
```

After the loader loaded our app and then loaded all the DLLs and found the address of these functions, it would have then gone through each one of these and replaced them with the actual address these functions now reside at, namely what you saw in the previous picture. If you think about this, this is a pretty smart way to handle this. If not done this way, the loader would be forced to go through our entire app and replace EVERY call to EVERY function in EVERY DLL and replace that address with the true address. That would be a lot of work. This way, the loader only has to replace the address in one place per function call, namely that functions line in the jump table.

Let's See For Ourselves. Reload the app in Olly and hit F7. Click on the instruction in line 401002 (like we did before) and hit the space bar (like we did before):



I just wanted you to notice the address again, 4012D6. Now click F7 to step into the call and you will notice that we will land at address 4012D6, which if you scroll up a little, you will also notice that we have


called into the middle of the jump table:

```
R DS:[(&gdi32.DeleteObject)]
R DS:[(&user32.CreateDialogFaramA)]
R DS:[(&user32.DefWindomProcA)]
R DS:[(&user32.DestWindomProcA)]
R DS:[(&user32.DestroyWindow)]
R DS:[(&user32.DestDigItem)]
R DS:[(&user32.GetDigItem)]
R DS:[(&user32.GetDigItem)]
R DS:[(&user32.GetDigItem)]
R DS:[(&user32.GetDigItem)]
R DS:[(&user32.GetDigItem)]
R DS:[(&user32.JoadCursorA)]
R DS:[(&user32.LoadCursorA)]
R DS:[(&user32.LoadCursorA)]
R DS:[(&user32.DoadCursorA)]
R DS:[(&user32.DeadCursorA)]
R DS:[(&user32.PostQuimMessage)]
R DS:[(&user32.PostQuimMessage)]
R DS:[(&user32.PostQuimMessage)]
R DS:[(&user32.SetDigItemTextA)]
R DS:[(&user32.ImageList_Destroy)]
R DS:[(&user32.ImageList_Destroy)]
R DS:[(&comot132.ImageList_Destroy)]
R DS:[(&comot132.ImageList_Destroy)]
R DS:[(&comot132.ImageList_Destroy)]
R DS:[(&comot132.ImageList_Destroy)]
R DS:[(&comot132.ImageList_Destroy)]
R DS:[(&comot132.ImageList_Destroy)]
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              gdi32.DeleteObject
user32.CreateDialogParamA
user32.DetWindowProoA
user32.DetWindowProoA
user32.DestroyWindow
user32.DestroyWindow
user32.GetDigItem
user32.GetDigItem
user32.GetDigItemTextA
user32.IsDialogMessageA
user32.LoadIconA
user32.LoadIconA
user32.LoadIconA
user32.LoadIconA
user32.PostRuitMessage
user32.RegisterClassExA
user32.RegisterClassExA
user32.SetDigItemTextA
user32.SetDigItemTextA
user32.SetDigItemTextA
user32.SetDigItemTextA
user32.SetDigItemTextA
user32.SetDigItemTextA
user32.SetDous
user32.TranslateMessage
user32.UpdateWindow
kernel32.ExtitProcess
kernel32.ExtitProcess
kernel32.GetModuleHandleA
comott132.ImageList_Destroy
comott132.ImageList_Destroy
comott132.ImageList_Destroy
comott132.InitCommonControls
                                                                                                                       or or or or
                                                                                                                                                                                                                                                                                                                                                                                                                                   DWORD
DWORD
DWORD
DWORD
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          PTR
PTR
PTR
PTR
                                                                                                                                                                                                                          14204000
74204000
76204000
60204000
60204000
60204000
50204000
50204000
40204000
30204000
30204000
30204000
30204000
30204000
30204000
40204000
50204000
50204000
50204000
50204000
                                                                                                                                                             JMP
JMP
                                                                                                                                                                                                                                                                                                                                                                                                                                   DWORD
DWORD
DWORD
                                                                                                                       0401270
                                                                                                                                                                                                                                                                                                                                                                                     JMP
JMP
                                                                                                                                                                                                                                                                                                                                                                                                                                 DWORD
DWORD
DWORD
DWORD
DWORD
DWORD
DWORD
                                                                                                                                                                                                                                                                                                                                                                                   JMP
JMP
JMP
     0401288
                                                                                                                                                                                                                                                                                                                                                                                   JMP
JMP
JMP
JMP
          340129F
                                                                                                                                                                                                                                                                                                                                                                                                                                 DWORD
DWORD
DWORD
DWORD
DWORD
       0401200
                                                                                                                                                                                                                                                                                                                                                                                   JMP
JMP
JMP
JMP
04012B2
04012B8
04012BE
04012C4
04012CA
                                                                                                                                                                                                                                                                                                                                                                                     JMP
JMP
JMP
JMP
                                                                                                                                                                                                                                                                                                                                                                                                                                   DWORD
DWORD
DWORD
                                                                                                                       1 1 1 1 1
                                                                                                                                                                                                                             1C204000
24204000
00204000
0C204000
                                                                                                                                                                                                                                                                                                                                                                                                                                 DWORD
DWORD
DWORD
DWORD
                                                                                                                                                                                                                                                                                                                                                                                   JMP
JMP
JMP
     04012DC
04012E2
04012E8
04012EE
04012F4
       04012F5
                                                                                                                                                                  00
00
00
```

Now, click F7 again and we will be taken to the REAL address of GetModuleHandleA at 7780B741. You can tell we are now in module kernel32 in two ways, both of which you will use at different times. The first is the title of Olly's CPU window:




You can see that it says "module kernel32". And the second way you can tell is by going into the memory window and looking up the address:



You can see that the address we are on (7780B741) falls in the address space of kernel32's code section.


Now let's go back and view a couple of the other function calls. Re-start the app and F8 down to address 40100C, the line that has the call to GetCommandLineA on it. Click on the instruction and hit the space bar so we can see what address it is pointing to, in this case 4012D0:



(Sorry for the mouse right over the address (2) It is 4012D0) Now, let's try manually going to this address, as this is something you will use often. Either click Ctrl-G or click on the GOTO icon and type in the address we want to go to:



Notice your "GOTO" window may look a little different, but that will be fixed soon. Now click OK and we will jump to the jump table for the GetCommandLineA function:



Now click F7 to make the jump and we will land at the beginning of the GetCommandLineA function in kernel32.dll. This function starts at 7C812FBD:

```
7C812F30 A1 F455887C MOV EAX,DWORD PTR DS:[7C8855F4]
7C812FC3 90 NOP
7C812FC4 90 NOP
7C812FC5 90 NOP
7C812FC6 90 NOP
7C812FC6 90 NOP
7C812FC7 98 NOP
7C812FC8 FFFF
7C812FC8 G000 ADD BYTE PTR DS:[EAX],AL
7C812FC0 G000 ADD BYTE PTR DS:[EAX],AL
7C812FC0 G000 ADD BYTE PTR DS:[EAX],AL
7C812FC0 B3 21 MOV BL,21
7C812FD0 B3 21 MOV BYTE PTR DS:[EAX+EDX*4-70],90
7C812FD0 B3 CMP BYTE PTR DS:[EAX+EDX*4-70],90
7C812FD0 B8FF MOV EDI,EDI
7C812FD0 B8FF MOV EDI,EDI
7C812FD0 SBC MOV EBP,ESP
```

Jumping in and out of DLLs

As we step around a program, at various times you will end up in DLLs. This is not generally where you want to be if you are trying to overcome some sort of protection scheme as Windows DLLs do not really contain any. The one caveat to this is if the program you are attempting to reverse engineer comes with it's own DLLs and you want to reverse those as well (or the protection scheme is actually in a DLL). There are a couple ways to get back to our programs code from a DLL. One way is to simply step through all of the DLL's function code until you finally return to your program, though this can take quite a while (and in some cases like Visual Basic, forever). The second option is to go into the "Debug" menu option in Olly and choose "Execute till user code" or press Alt-F9. This means run the code in this DLL until we return to our own programs code. Keep in mind that sometimes this doesn't work because if the DLL accesses a buffer or variable that is in our programs workspace, Olly will stop there, so you could end up calling Alt-F9 several times before you finally get back.


Let's try this option now. We should be currently paused at address 7C812FBD, the beginning of GetCommandLineA. Now press Alt-F9. This will take us back to the instruction in our program after the call we made to kernel32 (if you scroll up one line you'll see the call).

Now let's try another option of getting back to our code. Re-start the program, step over (F8) until the call


to GetCommandLineA (40100C), step in to that call (F7) and step in to the jump in the jump table (F7). We are now back at the beginning of GetCommandLineA:

```
MOV EAX, DWORD PTR DS: [708855F4]
                        A1 F455887C
C3
90
90
90
90
90
90
FFFF
FFFF
70812FBD |
                                                                    NOP
NOP
NOP
                                                                     NOR
                                                                                                                                                                               Unknown command
Unknown command
                                                                            BYTE PTR DS:[EAX],AL
BYTE PTR DS:[EAX],AL
BL,21
BYTE PTR DS:[EAX+EDX*4-70],90
                          9999
9999
                                                                     ADD
                                                                    ADD
MOV
CMP
          ZFCE
ZFDØ
                          B3 21
<u>807C</u>90 90 90
90
90
8BFF
                                                                    CMP BYTE PTR DS: LEAN LOND
NOP
NOP
MOU EDI, EDI
PUSH EBP
MOU EBP, ESP
PUSH ESI
MOU EAX, DWORD PTR FS: [18]
                                                                                                                                                                               ntdll.70910228
             DE
                           8BEC
                          56
64:A1 18000000
```

Now open up the memory window and scroll until you can see the sections with our programs code in it (starting at address 400000 with the PE Header):



now, click on the line at address 401000, the line that has our .text section on it. Now hit F2 to toggle a breakpoint on access for this memory section (or right click and select Breakpoint on access):



Now, run the app. Olly will break on the same line as above at address 401011, the line one after our call to the DLL!!! Now remove the memory breakpoint or you'll wonder why every time you run the app it breaks on the next line 🔠

More On The Stack

The stack is a very important part of reverse engineering, and without a very clear understanding of it, you will never be a great reverse engineer. Let's experiment with it a little...

First, take a look at the registers window (after re-starting the app) and look at the ESP register. This register points to the address of the 'top' of the stack. In this case the value of ESP is 12FFC4. Now look down at the stack window and you'll notice the top address in the list matches this address:

```
| Colored | Colo
```

Now push F8 (or F7) one time to push the value zero onto the stack and look at the stack window:

As we went over in out last tutorial, this pushes zero (null) onto the stack. Now look at our ESP register:

```
Registers (FPU)

ERX 00000000
ECX 0012FFB0

EX 7C90ES14 ntdll.KiFastSystemCallRet

EX 7CFD6000
ESP 0012FFC0
ESP 0012FFFC0
EST FFFFFFFF
EDI 7C910228 ntdll.7C910228

EIP 00401002 FirstPro.00401002

C 0 FS 0023 32bit 01FFFFFFFF
```

It has changed to 12FFc0, because, after pushing a byte onto the stack, this is the new top of the stack. Now press F8 one time, stepping over the call to GetModuleHandleA, and look at the stack window:

```
0012FFC4 7C817077 RETURN to kernel32.7C817077 7C910228 7C910228 7C910228 7C910228 7C910228 7C910228 7C910228 7C910228 7C910228 7C91026 7C910228 7C91026 7C9102
```

You will notice that our stack has gone back down by one (and our ESP register is back to what it was). This is because the GetModuleHandleA function used this zero that was pushed on to the stack as an argument and then 'pop'ed it off the stack as it was no longer needed. As was touched on in the last tutorial, this is one way our program passes arguments to functions: they push them on the stack, the called function pops them off the stack, uses them, and then returns, usually with any information we need in registers (as we'll see shortly).

Let's watch a couple more...If you press F8 twice to step over the call to GetCommandLineA you will notice that the stack didn't change. That's because we didn't push anything onto the stack for that function to use. Next, we reach a PUSH 0A instruction. This is the first argument that we are going to pass to the next called function. Stepping over this you will notice that 0A will be at the top of the stack and the ESP register has gone down by 2 (when you push a value onto the stack, the ESP register goes down as the stack 'grows' down in memory). Now push F8 again, and the ESP register will go DOWN again by 4. This is because we have pushed a 4 byte value onto the stack. If you look at the top of the stack you will notice

that we pushed 00000000 onto the stack. Why?

Let's look at the line that actually made the push at 401013: PUSH DWORD PTR DS:[40302c]

What this line means (as I'm sure you know because you have been studying assembly language :p) is take the contents of the four bytes at address 40302C and PUSH them onto the stack. What's at 40302C? Well, 00000000 of course! (just kidding. Let's look for ourselves Right click on the instruction at address 401013 and select "Follow in Dump" -> "Memory Address". This will load the dump window with the contents of memory starting at 40302C:

Address	Hex	du	IMP														ASCII					
0040302C		00	00	00	00	00	00	00	00	00	00	00	00	00	00	00						
0040303C	00	99	00	99	99	00	99	00	00	99	00	99	00	00	99	99			• •			٠.
0040304C	00	99	99	99	99	99	99	99	00	99	00	99	99	00	99	99			• •			٠.
0040305C	00	99	99	99	00	99	99	99	00	99	00	99	99	00	99	99			• •			٠.
0040306C	00	99	99	99	00	99	99	99	99	99	99	99	99	99	99	99			• •	• •	• • •	٠.
0040307C	00	99	00	00	99	00	99	00	00	99	00	99	00	00	99	00			• •			٠.
0040308C	00	99	99	99	99	99	99	99	00	99	00	99	99	00	99	99			• •			٠.
0040309C	00	99	99	99	99	99	99	99	00	99	00	99	99	00	99	99			• •			٠.
004030AC	00	99	99	99	00	99	99	99	99	99	99	99	99	99	99	00			• •	• •	• • •	٠.
004030BC	00	99	00	00	99	00	99	00	00	99	00	99	99	00	99	00			• •			٠.
004030CC	00	99	99	99	99	99	99	99	00	99	00	99	99	00	99	99			• •			٠.
004030DC	00	99	99	99	99	99	99	99	00	99	00	99	99	00	99	99			• •			٠.
004030EC	00	99	99	99	00	99	99	99	99	99	99	00	99	99	99	99			• •		• • •	٠.
004030FC	00	99	00	00	99	00	99	00	00	99	00	00	00	00	99	00			• •	• •		٠.
0040310C	00	99	99	99	99	00	99	99	00	99	00	99	99	00	99	99			• •			٠.
0040311C	00	99	99	99	99	99	99	99	00	99	00	99	99	00	99	99			• •			٠.
0040312C	00	99	99	99	00	99	99	99	99	99	99	99	99	99	99	99			• •			•
0040313C	00	99	00	00	99	00	99	00	00	99	00	99	99	00	99	00			• •			•
0040314C	99	99	99	99	99	99	99	99	99	99	99	99	99	99	99	99		• • •	• •	• •		٠.

Obviously, there's not much there! But at least you now know where the zero is coming from. If you would like to know more detail as to what's going on here, this memory space is being set up for variables and will eventually be populated with those variables, but for now, all the variables have been initialized to 0's.

Now press F8 once and we will be on another PUSH but this time from address 403028. If you scroll up on the dump window you can see that at this address is yet more zeros (right after the string we changed in the last tutorial (a)). So what this section is doing is pushing pointers to memory addresses, currently set at zero, that our code will use as variables. Step over the last PUSH and step into the call to address 40101C. The first thing you should notice is that something new has been pushed onto the stack: the return address for our call, 401026.

When any code uses a CALL instruction, the address of the next instruction that would have been run had we not made the call is automatically pushed onto the stack. The reason for this is that, after the function we called has done everything it needs to do, it needs to know where to return to. This address that was automatically pushed onto the stack is that return address. Look at the top of the stack window:

You will see that Olly has figured out that it is a return address and it points back to our program (FirstPro) and that the address that needs to be returned to is 40102C (one instruction past the call).

Now, at the end of this function, a RETN instruction will be used (and of course you know this stands for "return" because it was at the beginning of your assembly language book). This return instruction really means "POP the address of the top of the stack and point our running code to this address" (it basically replaces the EIP register- the register of the current line of code we are running- with this pop-ed value). So now, the called function knows exactly where it needs to return to when it's done! In fact, if you scroll down a little you will see the RETN statement at address 4011A3 that will pop this address off the stack and begin running code at that address:

(The 10 after the RETN statement just means give me the return address and also delete 10h bytes off the stack as I don't need them anymore. Just look on the next page of your assembly language book 9)

Let me just take a moment here to start what I am sure will become a famous mantra in the reverse engineering community. I like to call it "Random's Essential Truths About Reversing Data", or R.E.T.A.R.D (since everything sounds better as an acronym). I am officially starting this soon-to-become-legend list with the following commandment:

#1. You MUST learn assembly language.

If you don't, you will not succeed at reverse engineering. It's that simple.

The last thing I am going to talk about in this tutorial is how Olly handles the displaying of arguments and local variables. If you double click on the EIP register so we can jump back to our current line of code (at address 40101C) and look down a couple lines you will see several blue labels that say Local in them (and one that says Arg):

If you do not have any programming experience, you may not know what the difference between a local variable and an argument is. An argument, as we discussed earlier, are variables passed to a function that that function needs, usually passed on the stack. A local variable is a variable that the called function 'creates' to hold something temporary. Here is an example of a small program that has the two different concepts:

```
main()
{
    sayHello( "R4ndom");
}
sayHello( String name)
{
    int numTimes = 3;
    String hello = "Hello, ";

    for( int x = 0; x < numTimes; x++)
        print( hello + name );
}</pre>
```

In this program, the string "R4ndom" is an argument passed into the sayHello function. In normal assembly language, this string (or at least the address of this string) would be pushed on to the stack so that the sayHello function could reference it. Once control transfers to the sayHello function, sayHello needs to set up a couple LOCAL VARIABLES, that is, variables that this function will use but will not be needed once this function is complete. The examples of local variables are the integer numTimes, the string hello, and the integer x. Unfortunately, just in case the stack was not complicated enough, both arguments and local variables are stored on the stack. The way the stack accomplishes this is by using the ESP register, though this register does not have psychic powers. It normally points to the top of the stack, but it can be modified. So let's say we enter the sayHello function and the stack has the following data on it:

- 1. Address of the string "R4ndom"
- 2. The return address from the call that got us here.

Well, if we want to create a local variable, all we have to do is subtract an amount from the ESP register and this will create space on the stack! Let's say we subtract 4 from ESP (which would be 4 bytes, or one 32-bit number). The stack would then look like this:

- 1. Empty 32-bit number
- 2. Address of the string "R4ndom"
- 3. The return address from the call that got us here.

Now we could put anything we wanted into this address, for instance, we could make it stand for the variable numTimes in our sayHello function. Since our function uses three variables (all 32-bits long) it would really subtract 12 bytes (or 0xC in hex) from ESP and then we would have three local variables that

we could use. Here is what the stack may look like then:

- 1. Empty 32-bit address that points to the string 'hello'
- 2. Empty 32-bit number for variable 'x'
- 3. Empty 32-bit number for variable 'numTimes'
- 4. Address of the string "R4ndom"
- 5. The return address from the call that got us here.

Now, sayHello can populate, change, and re-use these addresses to play with our variables, and it still has the argument passed in to this function in the first place (the string "R4ndom"). When sayHello is done, it has two ways that it can delete these local variables and arguments (as they will no longer be needed after this function is done) and return the stack back to the way it was: 1) it can change the ESP register back to what it was before we changed it or 2) use a special RETN instruction with a number after it. In the former case, so that the program can remember what the original value of ESP was, it uses another register, EBP, that's purpose is to keep track of the original location that the stack pointed to when we first entered the sayHello function. When it's ready to return, it simply copies the original value of ESP (stored in EBP at the beginning) out of EBP back into ESP and BAM, the variables are gone. The return address is now at the top of the stack, and when the RETN instruction runs, it will use this tpo get back to our main program.

In the second case, you can tell the CPU how many bytes you don't need on the stack anymore, and it will delete these from the top of the stack. In our case, we would use RETN 16 (0xF in hex) and that would get rid of the first 16 bytes (or 4 32-bit numbers) off the top of the stack, leaving the new top of the stack with the return address to get back to our main program. The type of return mechanism used is usually dependent on the compiler, but you will see both.

Now, let's look back at our FirstProgram.exe:

```
ESP: -54
                       83C4 AC
C745 D0 3006
C745 D0 3006
C745 B0 8611
C745 D0 0006
C745 E0 1E06
F775 B0
8F45 E4
C745 F0 1006
C745 F4 0936
C745 F8 0036
68 007F0000
E8 00220000
                                                                                   .30
                                                                                   FirstPro.004011A6
30401047
3040104E
                                                                                ī.īE
00401055
00401058
                                                                                                                                                 FirstPro.00401026
0040105B
                                                                                                                                                 ASCII "MyMenu"
ASCII "DLGCLASS"
0401062
 10401069
10401070
                                                                                                                                                                = IDI_APPLICATION
                                                                (JMP.&user32.LoadIconA)
 0401079
```

You can see that Olly has deciphered one argument and 12 local variables. These local variables are used in our program to keep track of things like the address of our icon, the address of the buffer for our input text, the length of the text input etc. And when it is done, it will either pop these values off, change the ESP register back to EBP or RETN with a number (in this case, it uses all three!!!).

I know that the stack is a very complicated design, but I guarantee that you will start to get the hang of it after messing with it for a while. That book on assembly language will also help a lot (2)

-till next time

R4ndom