

Game Power Plan Switcher

Overview and quick start

Version 2.3.6 | 6 October 2026 | NN6

Game Power Plan Switcher selects a Gaming plan while a watched game process is running and returns to a Default plan when the last eligible process closes. The native desktop app combines that automation with live CPU activity, optional hardware sensors, per-game profiles and local diagnostics.

This overview explains how to start using version 2.3.6 and what its readings mean. The Full Guide covers configuration, recovery, source structure, building and release verification.

What the app does

Area	Behavior
Power automation	Checks the current Windows power plan before applying a different configured target. Normal monitoring does not edit plan definitions.
Game profiles	Matches executable names, supports aliases and bulk entry, and optionally applies a per-game plan or process tuning.
Live overview	Shows sampled CPU utilization, topology sections, a 30-second chart and recorded plan transitions.
Local integrations	Offers supported NVIDIA or AMD GPU sensors, existing LHM or OHM sensor providers, tray controls and global hotkeys.

Start using the app

1. Open Game-Power-Plan-Switcher-2.3.6.exe on Windows 10 or 11 x64 with a compatible OpenGL driver. The native app does not need PS2EXE.
2. In Settings, choose two installed plans for Gaming and Default. Use `powercfg /list` to check their names and GUIDs. Keep the two roles distinct.
3. In Workspace, check the game executable aliases. Rainbow Six Siege defaults include RainbowSix.exe, RainbowSixSiege.exe and RainbowSix_DX11.exe.
4. If a previous monitor is detected, use Use this app instead only when ready to transfer ownership. Until then, the previous monitor keeps control.
5. Start monitoring. Enable Startup if the native app should launch at user logon after a restart. Review battery and time rules because they can change the selected target.

Everyday controls and important limits

Control	Effect
Start monitoring or Pause	Starts automation or pauses it and restores the configured Default plan and tracked changes.
Main yellow control	Minimizes the main window. Background monitoring continues.
Main red control	Hides to the tray when Close to system tray is enabled; otherwise exits normally.
Maintainer and About red control	Dismisses only that dialog. These dialogs no longer contain a minimize control.
Tray Exit	Closes normally and performs the engine restoration path.
Open the app again	Restores the existing participating GUI for the same Windows user and session.

Read the measurements correctly

CPU chips show sampled Windows utilization, including valid 0% values. They do not identify which individual process owns each core. Intel P and E sections require distinct Windows efficiency classes. AMD cache sections show measured shared L3 domains, not guaranteed physical CCD or CCX identities.

GPU metrics use supported installed NVML or ADL APIs. CPU temperature and package power require an existing LibreHardwareMonitor or OpenHardwareMonitor WMI provider. Missing readings remain unavailable; Connect sensors explains the local sources and Retry refreshes them. Energy savings remains unavailable without a real meter and comparison baseline.

Background behavior

A separate engine owns power changes and a guardian supports restoration after an engine crash. Hidden or fullscreen-suspended views stop visual refresh work while monitoring continues. Slint or the graphics driver may retain the main surface. Neither fixed memory usage nor zero GPU allocation is guaranteed.

Local data and release files

Settings, recovery state and operational logs are stored under %LOCALAPPDATA%\NN6PowerPlan. Switches are logged under %LOCALAPPDATA%\GamePowerPlan\switch.log. Diagnostic exports can contain account, process and plan names; review them before sharing.

The renamed project remains GPL-3.0-or-later and unsigned. Copyright and historical release records retain NN6 attribution. Its source package, checksums and verification report identify the shipped files and the checks performed. A checksum alone does not authenticate a publisher. See [Game-Power-Plan-Switcher-Full-Guide.pdf](#) for the detailed operating and development reference.