用 Sqlserver 存储 Asterisk 的呼叫记录

版本: 1.0.0 作者: Mike E-mail: Mike Zhang@live.com 安装 rpmforge 和 epel 安装 freetds: yum install freetds* vi /etc/freetds.conf 示例如下: ip:port 模式: [SQL2008] host = 172.16.16.100port = 1433tds version = 8.0测试如下: tsql -S SQL2008 -U sa -P password 数据库实例模式: [voipCdrSvr] host = 172.16.16.101instance = sqlexpress tds version = 8.0测试如下: tsql -S voipCdrSvr -U sa -P password 配置 Asterisk 清空 cdr odbc.conf > /etc/asterisk/cdr odbc.conf 编辑 cdr tds.conf vi /etc/asterisk/cdr_tds.conf [global] connection=voipCdrSvr port=1433 dbname=myDB table=cdr user=sa password=myPasswd 创建 Sqlserver 数据表: CREATE TABLE cdr ([accountcode] [varchar] (20) NULL , [src] [varchar] (80) NULL , [varchar] (80) NULL , [dst] [dcontext] [varchar] (80) NULL ,

	[clid]	[varchar]	(80)	NULL	,
	[channel]	[varchar]	(80)	NULL	,
	[dstchannel]	[varchar]	(80)	NULL	,
	[lastapp]	[varchar]	(80)	NULL	,
	[lastdata]	[varchar]	(80)	NULL	,
	[start]	[datetime]		NULL	,
	[answer]	[datetime]		NULL	,
	[end]	[datetime]		NULL	,
	[duration]	[int]		NULL	,
	[billsec]	[int]		NULL	,
	[disposition]	[varchar]	(20)	NULL	,
	[amaflags]	[varchar]	(16)	NULL	,
	[uniqueid]	[varchar]	(150)	NULL	,
	[userfield]	[varchar]	(256)	NULL	
)					

重启 Asterisk 生效: asterisk -rx "core restart now"