
Networking Academy

Lab – RESTCONF with Postman



Objectives

Part 1: Setup HTTP Headers in Postman

Background / Scenario

RESTCONF is a RESTful API interface that provides a programmatic interface for accessing data defined in YANG device models.

In this lab, you will learn how to interact with the RESTCONF interface using the Postman application to retrieve the device's configuration, update and create new interfaces and retrieve operation data.

Required Resources

- Postman
- Access to a router with the IOS XE operating system version 16.6 or higher.

Instructions

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

Part 1: Setup HTTP headers and Authentication in Postman

In this part, you will setup the HTTP Headers in Postman to work with RESTCONF REST API interfaces.


Step 1: Configure Postman.

Configure a Postman setting.

a. Open Postman and create a new tab if necessary.


b. Click **File > Settings**.

c. Under the **General** tab, set the **SSL certificate verification** to **OFF**. Close the **Settings** dialog box.



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com




Step 2: Select the method and enter the required URL.

a. Next to the URL box, select the request method to be **GET**.

b. Enter the URL for API endpoint: https://10.10.20.48/restconf/data/Cisco-IOS-XE-native:native (adjust the IP address to match the router's current address)

2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com




2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com

Step 3: Enter the authentication header information.


a. Below the URL input field, select **Authorization**.



b. Select the type **Basic Auth** and enter the username and password for authenticating to the RESTCONF API service:
`developer`
C1sco12345

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public


www.netacad.com



c. Click on the **Preview Request** to add the Authentication header to the Headers.

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com




Step 4: Enter the additional Headers.

a. Next, below the URL input field, select **Headers**.

b. Under **Headers**, click the **New key** field under the **Key** column and enter **Content-Type** to define what is the encoding of data that are sent with Postman in the REST API request.


c. Next again under **Headers**, click the **New key** field under the **Key** column and enter **Accept** to define in what encoding you wish to receive back the data replies from the REST API request.

d. In the value columns, enter `application/yang-data+json` when sending or receiving data that are in JSON encoding. When sending or receiving data in XML encoding (default), use `application/yang-data+xml`.



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com



Step 5: Send the request.

a. Click **Send**.

b. After a brief delay, you should see the response appear below the request information. Scroll down, if necessary to view the response data.

c. When the **Accept** header was set to `application/yang-data+json` the response consists of JSON encoded data.


d. Uncheck the **Accept** header, or change it to `application/yang-data+xml` (default behavior when no Accept header is defined) and click on **Send**. Now the response consists of XML encoded data:

Note: If there is an error, check the Status of the request. Check the meaning of the status code. 200 means success. A 404 error may mean that the URL was entered incorrectly. A 401 or 403 error could indicate a problem with the authentication, so check that the credentials are entered correctly.

2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com


Lab – RESTCONF with Postman



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com

Lab – RESTCONF with Postman



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com

Part 2: Retrieve Interface Configuration

Step 1: Retrieve YANG data in XML.

a. Duplicate the existing REST API request in Postman by right clicking on the request and selecting Duplicate Tab to create a new request with prefilled existing Headers:


© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com


b. In the URL for the API endpoint, enter after the host and port portion: `/restconf/data/ietf-interfaces:interfaces` to retrieve data defined in the **ietf-interfaces** YANG model in the **interfaces** container.

c. Click **Send** to send the RESTCONF API request. With unchecked **Accept** header or the **Accept** header set to `application/yang-data+xml`, the result YANG data are returned in XML encoding.

d. Check the Accept header and set it to `application/yang-data+json` to receive YANG data formatted in JSON encoding.



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public




Step 2: Retrieve information about a single interface

a. In the URL for the API endpoint, enter after the host and port portion: `/restconf/data/ietf-interfaces:interfaces/interface=Loopback1` to retrieve data for the **Loopback1** interface only.

b. Click **Send** …

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com




Step 3: Retrieve operation data

a. Change the RESTCONF API Endpoint to retrieve operation and statistical data about the interfaces. You can use the “pyang” tool to discover what container in the **ietf-interfaces** YANG model includes the operational and stats data.

2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com

Lab – RESTCONF with Postman



b. What is the new URL?


https://10.10.20.48/restconf/data/ietf-interfaces:interfaces-state
Esta URL permite recuperar información del estado de las interfaces, como su condición operativa, velocidad y estadísticas de tráfico.

Part 3: Update Interface Configuration

a. Duplicate the existing REST API request in Postman by right clicking on the request and selecting Duplicate Tab to create a new request with prefilled existing Headers.

b. In the URL for the API endpoint, change the method from **GET** to **PUT** and enter after the host and port portion: `/restconf/data/ietf-interfaces:interfaces/interface=Loopback99` to create a new interface **Loopback99**.

c. In the Body part of the request, enter the YANG data you want to apply to the device's configuration (copy, paste and customize the JSON data from the previous GET request on Loopback1 – change the interface name and IP address).




d. Click **Send** to create a new interface Loopback99 with the IP address 99.99.99.99/24.

e. In the Output (scroll down), you should see the HTTP Error code **201 Created** indicating that the new interface has been created:

f. Verify using the IOS CLI that the new Loopback99 interface has been created (sh ip int brief).


g. Update the RESTCONF API request to delete the interface **Loopback99**.



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com


Lab – RESTCONF with Postman



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com

Lab – RESTCONF with Postman




h. What changes were needed to be made in the RESTCONF request to delete the interface?
Para eliminar una interfaz mediante RESTCONF, es necesario cambiar el método HTTP de PUT a DELETE, manteniendo la URL que identifica la interfaz que se desea eliminar. En nuestro caso, sería Loopback13. También se debe conservar la autenticación Basic Auth y eliminar el contenido del Body, ya que no es necesario enviar datos JSON para realizar la eliminación.

DESAFÍOS

✔ Enviar la solicitud GET para obtener la configuración global del router (/restconf/data/Cisco-IOS-XE-native:native). Deben hacer una captura donde se observe la respuesta formateada en JSON, y otra donde se observe en XML alterando únicamente los encabezados (Headers).


© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

Lab – RESTCONF with Postman



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com




✔ En lugar de solicitar todas las interfaces (/ietf-interfaces:interfaces), debes modificar la URI para consultar únicamente la interfaz GigabitEthernet1 usando JSON.

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com


Lab – RESTCONF with Postman



✔ Crear una nueva interfaz Loopback utilizando su número de lista o las últimas dos cifras de su matrícula como el ID de la interfaz (ej. Loopback25) y asignarle la IP. Debes obtener un código de estado 201 Created en Postman e incrustar la descripción "Interfaz creada por [Tú Nombre]"

2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

Lab – RESTCONF with Postman




✔ Cambiar el estado de la interfaz recién creada a "deshabilitada" ("enabled": false) o modifica únicamente la description utilizando el método PATCH en lugar de PUT.

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com


Lab – RESTCONF with Postman



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com


Lab – RESTCONF with Postman



✔ Eliminar la interfaz creada en el Desafío 3 utilizando el método **DELETE.**

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public


Lab – RESTCONF with Postman



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com

Lab – RESTCONF with Postman



Preguntas de Reflexión

✔ ¿Qué encabezado HTTP le indica al servidor en qué formato queremos recibir la información?

El encabezado HTTP Accept indica al servidor el formato en el que el cliente desea recibir la información.


✔ ¿Qué código de estado HTTP devuelve el router tras eliminar exitosamente la interfaz?

El router devolvió el código HTTP 204 No Content, indicando que la interfaz Loopback13 fue eliminada correctamente mediante el método DELETE, sin devolver contenido en el cuerpo de la respuesta.

✔ Escribir mal las credenciales en Basic Auth (Ej. intentar con developer / Cisco123) -> Esperado: 401 Unauthorized.

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public


Lab – RESTCONF with Postman



✔ Escribir mal la URL (Ej. /restconf/data/ietf-interfaces:interfases) -> Esperado: 404 Not Found.

2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com




✔ Enviar un cuerpo JSON mal formado o con sintaxis inválida en un POST -> Esperado: 400 Bad Request o 415 Unsupported Media Type.

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com

Lab – RESTCONF with Postman



© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com

Lista de Cotejo: Evaluación de Práctica RESTCONF y Entrega en GitHub

Criterio / Indicador	Puntos Posibles	Puntos Obtenidos	Observaciones
1. Práctica Guiada (RESTCONF Básico)	**2.5 pts**		
* Configuración correcta de la autenticación (*Basic Auth*) y desactivación de SSL en Postman.	0.5		
* Configuración correcta de los encabezados HTTP (Accept y Content-Type) para JSON y XML.	1.0		
* Obtención exitosa de respuestas HTTP 200 al consultar datos del dispositivo (native e interfaces).	1.0		
2. Resolución de Desafíos Prácticos	**4.0 pts**		
* **Creación de Recurso:** Creación correcta de la interfaz asignada mediante solicitud POST/PUT obteniendo código de estado 201 Created.	1.5		
* **Modificación:** Modificación exitosa del estado o descripción de la interfaz mediante PUT o PATCH.	1.0		
* **Eliminación y Depuración:** Eliminación del recurso mediante DELETE y correcta interpretación/provocación de errores de prueba (ej. 401, 404).	1.5		
3. Preguntas de Reflexión y Análisis	**2.0 pts**		
* Explica con precisión la función del encabezado Accept y la diferencia en la respuesta al cambiar entre JSON y XML.	1.0		
* Explica la diferencia práctica entre los métodos HTTP utilizados (GET, POST, PUT, DELETE) y el significado de los códigos de estado obtenidos (200, 201, 401, 404).	1.0		
4. Entrega y Flujo en GitHub	**1.5 pts**		
* El Pull Request fue enviado correctamente desde/hacia la rama con el nombre exacto: feat/unidad4_act01.	0.5		
* La entrega incluye las capturas de pantalla organizadas y/o la colección exportada de Postman dentro del repositorio.	0.5		
* El Pull Request incluye un título claro y una descripción detallada del trabajo realizado.	0.5		
TOTAL	**10.0 pts**		

© 2017 - 2026 Cisco and/or its affiliates. All rights reserved. Cisco Public

www.netacad.com