


Lab - Configure DHCPv6

Topology



Addressing Table

Device	Interface	IPv6 Address
R1	G0/0/0	2001:db8:acad:2::1 /64
		fe80::1
	G0/0/1	2001:db8:acad:1::1/64
		fe80::1
R2	G0/0/0	2001:db8:acad:2::2/64
		fe80::2
	G0/0/1	2001:db8:acad:3::1 /64
		fe80::1
PC-A	NIC	DHCP
PC-B	NIC	DHCP

Objectives

Part 1: Build the Network and Configure Basic Device Settings

Part 2: Verify SLAAC address assignment from R1

Part 3: Configure and verify a Stateless DHCPv6 Server on R1

Part 4: Configure and verify a Stateful DHCPv6 Server on R1

Part 5: Configure and verify a DHCPv6 Relay on R2

Background / Scenario

The dynamic assignment of IPv6 global unicast addresses (GUA) can be configured the following three ways:

- Stateless Address Autoconfiguration (SLAAC)
- Stateless Dynamic Host Configuration Protocol for IPv6 (DHCPv6)
- Stateful DHCPv6

Lab - Configure DHCPv6

When using SLAAC to assign IPv6 addresses to hosts a DHCPv6 server is not used. Because a DHCPv6 server is not used when implementing SLAAC, hosts are unable to receive additional critical network information, including a domain name server (DNS) address as well as a domain name.

- 2020 Cisco and/or its affiliates. All rights reserved. Cisco Public

When using Stateless DHCPv6 to assign IPv6 addresses to host, a DHCPv6 server is used to assign the additional critical network information, however the IPv6 address is assigned using SLAAC.

When implementing Stateful DHCPv6, a DHCPv6 server assigns all network information, including the IPv6 address.

The determination of how hosts obtain they dynamic IPv6 addressing is dependent on flag setting contain within the router advertisement (RA) messages.

In this scenario, the company has grown in size, and the network administrators can no longer assign IP addresses to devices manually. Your job is to configure the R2 router to assign IPv6 addresses on two different subnets connected to router R1.

Note: The routers used with CCNA hands-on labs are Cisco 4221 with Cisco IOS XE Release 16.9.4 (universalk9 image). The switches used in the labs are Cisco Catalyst 2960s with Cisco IOS Release 15.2(2) (lanbasek9 image). Other routers, switches, and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and the output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at the end of the lab for the correct interface identifiers.

Note: Ensure that the routers and switches have been erased and have no startup configurations. If you are unsure contact your instructor.

Required Resources

- 2 Routers (Cisco 4221 with Cisco IOS XE Release 16.9.4 universal image or comparable)
- 2 Switches (Cisco 2960 with Cisco IOS Release 15.2(2) lanbasek9 image or comparable) - **Optional**
- 2 PCs (Windows with a terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

Instructions Part 1: Build the Network and Configure Basic Device Settings

In Part 1, you will set up the network topology and configure basic settings on the PC hosts and switches.

Step 1: Cable the network as shown in the topology.

Attach the devices as shown in the topology diagram and cable as necessary.



Step 2: Configure basic settings for each switch. (Optional)

- Assign a device name to the switch.
- Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands as though they were host names.
- Assign **class** as the privileged EXEC encrypted password.
- Assign **cisco** as the console password and enable login.
- Assign **cisco** as the VTY password and enable login.

Lab - Configure DHCPv6

- f. Encrypt the plaintext passwords.
- g. Shutdown all unused ports

```
Switch>ena
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname S1
S1(config)#no ip domain-lookup
S1(config)#enable secret class
S1(config)#line console 0
S1(config-line)#password cisco
S1(config-line)#login
S1(config-line)#exit
S1(config)#line vty 0 4
S1(config-line)#password cisco
S1(config-line)#login
S1(config-line)#exit
S1(config)#service password-encryption
S1(config)#banner motd # Unauthorized Access is Prohibited! #
S1(config)#interface range f0/1-4,f0/7-24,g0/1-2
S1(config-if-range)#shutdown

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/2, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/3, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/4, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/7, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/8, changed state to administratively down

Switch>ena
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname S2
S2(config)#no ip domain-lookup
S2(config)#enable secret class
S2(config)#line console 0
S2(config-line)#password cisco
S2(config-line)#login
S2(config-line)#exit
S2(config)#line vty 0 4
S2(config-line)#password cisco
S2(config-line)#login
S2(config-line)#exit
S2(config)#service password-encryption
S2(config)#banner motd # Unauthorized Access is Prohibited! #
S2(config)#interface range f0/1-4,f0/7-17,f0/19-24,g0/1-2
S2(config-if-range)#shutdown

%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/2, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/3, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/4, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/7, changed state to administratively down
%LINK-5-CHANGED: Interface FastEthernet0/8, changed state to administratively down
```

- h. Save the running configuration to the startup configuration file.

```
S1#copy running-config startup-config S2#copy running-config startup-config
Destination filename [startup-config]? Destination filename [startup-config]?
Building configuration... Building configuration...
[OK] [OK]
S1# S2#
```

Step 3: Configure basic settings for each router.

- Assign a device name to the router.
- Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands as though they were host names.
- Assign **class** as the privileged EXEC encrypted password.
- Assign **cisco** as the console password and enable login.
- Assign **cisco** as the VTY password and enable login.
- Encrypt the plaintext passwords.
- Create a banner that warns anyone accessing the device that unauthorized access is prohibited.
- Enable IPv6 Routing
- Save the running configuration to the startup configuration file.

```
Router>ena
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R1
R1(config)#no ip domain-lookup
R1(config)#enable secret class
R1(config)#line console 0
R1(config-line)#password cisco
R1(config-line)#login
R1(config-line)#exit
R1(config)#line vty 0 4
R1(config-line)#password cisco
R1(config-line)#login
R1(config-line)#exit
R1(config)#service password-encryption
R1(config)#banner motd # Unauthorized Access is Prohibited! #
R1(config)#ipv6 unicast-routing
R1(config)#exit
R1#
%SYS-5-CONFIG_I: Configured from console by console

R1#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R1#
```

```
Router>ena
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname R2
R2(config)#no ip domain-lookup
R2(config)#enable secret class
R2(config)#line console 0
R2(config-line)#password cisco
R2(config-line)#login
R2(config-line)#exit
R2(config)#line vty 0 4
R2(config-line)#password cisco
R2(config-line)#login
R2(config-line)#exit
R2(config)#service password-encryption
R2(config)#banner motd # Unauthorized Access is Prohibited! #
R2(config)#ipv6 unicast-routing
R2(config)#exit
R2#
%SYS-5-CONFIG_I: Configured from console by console

R2#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R2#
```

Step 4: Configure interfaces and routing for both routers.

- Configure the G0/0/0 and G0/0/1 interfaces on R1 and R2 with the IPv6 addresses specified in the table above.

```
R1(config)#interface g0/0/1
R1(config-if)#ipv6 address fe80::1 link local
^
% Invalid input detected at '^' marker.

R1(config-if)#ipv6 address fe80::1 link-local
R1(config-if)#ipv6 address 2001:db8:acad:1::1/64
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0/1, changed state to up

R1(config-if)#exit
R1(config)#interface g0/0/0
R1(config-if)#ipv6 address fe80::1 link-local
R1(config-if)#ipv6 address 2001:db8:acad:2::1/64
R1(config-if)#no shutdown

R1(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0/0, changed state to up

R1(config-if)#exit
R1(config)#
```

Lab - Configure DHCPv6

```
R2(config)#interface g0/0/1
R2(config-if)#ipv6 address fe88::1 link-local
R2(config-if)#ipv6 address 2001:db8:acad:3::1/64
R2(config-if)#no shutdown

R2(config-if)#
%LINK-S-CHANGED: Interface GigabitEthernet0/0/1, changed state to up

%LINEPROTO-S-UPDOWN: Line protocol on Interface GigabitEthernet0/0/1, changed state to up

R2(config-if)#interface g0/0/0
R2(config-if)#ipv6 address fe88::2 link-local
R2(config-if)#ipv6 address 2001:db8:acad:2::2/64
R2(config-if)#no shutdown

R2(config-if)#
%LINK-S-CHANGED: Interface GigabitEthernet0/0/0, changed state to up

%LINEPROTO-S-UPDOWN: Line protocol on Interface GigabitEthernet0/0/0, changed state to up

R2(config-if)#|
```

- b. Configure a default route on each router pointed to the IP address of G0/0/0 on the other router using the following commands.

```
R1(config)# ipv6 route ::/0 2001:db8:acad:2::2
R2(config)# ipv6 route ::/0 2001:db8:acad:2::1

R1(config)#ipv6 route ::/0 2001:db8:acad:2::2
R1(config)#|

R2(config)#ipv6 route ::/0 2001:db8:acad:2::1
R2(config)#|
```

- c. Verify routing is working by pinging R2's G0/0/1 address from R1.

```
R1#ping 2001:db8:acad:3::1

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 2001:db8:acad:3::1, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/0 ms

R1#|
```

- d. Save the running configuration to the startup configuration file.

<pre>R1#copy running-config startup-config Destination filename [startup-config]? Building configuration... [OK] R1# </pre>	<pre>R2#copy running-config startup-config Destination filename [startup-config]? Building configuration... [OK] R2# </pre>
---	---

Part 2: Verify SLAAC Address Assignment from R1

In Part 2, you will verify that Host PC-A receives an IPv6 address using the SLAAC method.

- a. Power up PC-A and ensure that the NIC is configured for IPv6 automatic configuration.

IPv6 Configuration	
☒ Automatic	☐ Static
IPv6 Address	2001:DB8:ACAD:1:260:2FFF:FE1A:96BD / 64
Link Local Address	FE80::260:2FFF:FE1A:96BD
Default Gateway	FE80::1

- b. After a few moments, the results of the command **ipconfig** should show that PC-A has assigned itself an address from the 2001:db8:1::/64 network.

```
C:\Users\Student> ipconfig
```

Lab - Configure DHCPv6

Windows IP Configuration

Ethernet adapter Ethernet 2:

```
Connection-specific DNS Suffix . :  
IPv6 Address. . . . . : 2001:db8:acad:1:5c43:ee7c:2959:da68  
Temporary IPv6 Address. . . . . : 2001:db8:acad:1:3c64:e4f9:46e1:1f23  
Link-local IPv6 Address . . . . . : fe80::5c43:ee7c:2959:da68%6  
IPv4 Address. . . . . : 169.254.218.104  
Subnet Mask . . . . . : 255.255.0.0  
Default Gateway . . . . . : fe80::1%6
```

```
C:\>ipconfig  
  
FastEthernet0 Connection:(default port)  
  
Connection-specific DNS Suffix...:  
Link-local IPv6 Address.....: FE80::260:2FFF:FE1A:96BD  
IPv6 Address.....: 2001:DB8:ACAD:1:260:2FFF:FE1A:96BD  
IPv4 Address.....: 0.0.0.0  
Subnet Mask.....: 0.0.0.0  
Default Gateway.....: FE80::1  
                        0.0.0.0  
  
Bluetooth Connection:  
  
Connection-specific DNS Suffix...:  
Link-local IPv6 Address.....: ::  
IPv6 Address.....: ::  
IPv4 Address.....: 0.0.0.0  
Subnet Mask.....: 0.0.0.0  
Default Gateway.....: ::  
                        0.0.0.0  
  
C:\>
```

Where did the host-id portion of the address come from?

The host-ID portion of the address come from the EUI-64 process, which expands the device's 48-bit MAC address into a 64-bit interface identifier by inserting FFFE in the middle and flipping the seventh bit.

Part 3: Configure and Verify a DHCPv6 server on R1

In Part 3, you will configure and verify a stateless DHCP server on R1. The objective is to provide PC-A with DNS server and Domain information.

Step 1: Examine the configuration of PC-A in more detail.

- Issue the command `ipconfig /all` on PC-A and take a look at the output.

```
C:\Users\Student> ipconfig /all  
Windows IP Configuration
```

```
Host Name . . . . . : DESKTOP-3FR7RKA  
Primary Dns Suffix . . . . . :  
Node Type . . . . . : Hybrid  
IP Routing Enabled. . . . . : No  
WINS Proxy Enabled. . . . . : No
```

Ethernet adapter Ethernet0:

Lab - Configure DHCPv6

```
Connection-specific DNS Suffix . . : 
Description . . . . . : Intel(R) 852574L Gigabit Network Connection
Physical Address. . . . . : 00-50-56-83-63-6D
IPv6 Address. . . . . : 2001:db8:acad:1:5c43:ee7c:2959:da68(Preferred)
Temporary IPv6 Address. . . . . : 2001:db8:acad:1:3c64:e4f9:46e1:1f23(Preferred)
Link-local IPv6 Address . . . . . : fe80::5c43:ee7c:2959:da68%6(Preferred)
IPv4 Address. . . . . : 169.254.218.104(Preferred)
Subnet Mask . . . . . : 255.255.0.0
Default Gateway . . . . . : fe80::1%6
DHCPv6 IAID . . . . . : 50334761
DHCPv6 Client DUID. . . . . : 00-01-00-01-24-F5-CE-A2-00-50-56-B3-63-6D
DNS Servers . . . . . : fec0:0:0:ffff::1%1
                        fec0:0:0:ffff::2%1
                        fec0:0:0:ffff::3%1

NetBIOS over Tcpip. . . . . : Enabled
```

```
C:\>ipconfig /all

FastEthernet0 Connection:(default port)

    Connection-specific DNS Suffix...: 
    Physical Address. . . . . : 0060.2F1A.96BD
    Link-local IPv6 Address . . . . . : FE80::260:2FFF:FE1A:96BD
    IPv6 Address. . . . . : 2001:DB8:ACAD:1:260:2FFF:FE1A:96BD
    IPv4 Address. . . . . : 0.0.0.0
    Subnet Mask . . . . . : 0.0.0.0
    Default Gateway . . . . . : FE80::1
                                0.0.0.0
    DHCP Servers . . . . . : 0.0.0.0
    DHCPv6 IAID . . . . . : 
    DHCPv6 Client DUID. . . . . : 00-01-00-01-70-DD-56-6C-00-60-2F-1A-96-BD
    DNS Servers . . . . . : ::
                                0.0.0.0

Bluetooth Connection:

    Connection-specific DNS Suffix...: 
    Physical Address. . . . . : 0040.0B63.8698
    Link-local IPv6 Address . . . . . : ::
    IPv6 Address. . . . . : ::
    IPv4 Address. . . . . : 0.0.0.0
    Subnet Mask . . . . . : 0.0.0.0
    Default Gateway . . . . . : ::
                                0.0.0.0
    DHCP Servers . . . . . : 0.0.0.0
    DHCPv6 IAID . . . . . : 
    DHCPv6 Client DUID. . . . . : 00-01-00-01-70-DD-56-6C-00-60-2F-1A-96-BD
    DNS Servers . . . . . : ::
                                0.0.0.0
```

- b. Notice that there is no Primary DNS suffix. Also note that the DNS server addresses provided are “site local anycast” addresses, and not unicast addresses, as would be expected.

Step 2: Configure R1 to provide stateless DHCPv6 for PC-A.

- a. Create an IPv6 DHCP pool on R1 named R1-STATELESS. As a part of that pool, assign the DNS server address as 2001:db8:acad::254 and the domain name as stateless.com.

```
R1(config)# ipv6 dhcp pool R1-STATELESS
R1(config-dhcp)# dns-server 2001:db8:acad::254
R1(config-dhcp)# domain-name STATELESS.com
```


Lab - Configure DHCPv6

- b. Configure the G0/0/1 interface on R1 to provide the OTHER config flag to the R1 LAN, and specify the DHCP pool you just created as the DHCP resource for this interface.

```
R1(config)# interface g0/0/1
```

```
R1(config-if)# ipv6 nd other-config-flag
```

```
R1(config-if)# ipv6 dhcp server R1-STATELESS
```

- c. Save the running configuration to the startup configuration file.

```
R1(config)#ipv6 dhcp pool R1-STATELESS
```

```
R1(config-dhcpv6)#dns-server 2001:db8:acad::254
```

```
R1(config-dhcpv6)#domain-name STATELESS.com
```

```
R1(config-dhcpv6)#exit
```

```
R1(config)#interface g0/0/1
```

```
R1(config-if)#ipv6 nd other-conif-flag
```

```
^  
% Invalid input detected at '^' marker.
```

```
R1(config-if)#ipv6 nd other-conig-flag
```

```
^  
% Invalid input detected at '^' marker.
```

```
R1(config-if)#ipv6 nd other-config-flag
```

```
R1(config-if)#ipv6 dhcp server R1-STATELESS
```

```
R1(config-if)#exit
```

```
R1(config)#exit
```

```
R1#
```

```
%SYS-5-CONFIG_I: Configured from console by console
```

```
R1#copy running-config startup-config
```

```
Destination filename [startup-config]?
```

```
Building configuration...
```

```
[OK]
```

```
R1#
```

- d. Restart PC-A.
- e. Examine the output of **ipconfig /all** and notice the changes.

```
C:\Users\Student> ipconfig /all
```

```
Windows IP Configuration
```

```
Host Name . . . . . : DESKTOP-3FR7RKA  
Primary Dns Suffix . . . . . :  
Node Type . . . . . : Hybrid  
IP Routing Enabled. . . . . : No  
WINS Proxy Enabled. . . . . : No  
DNS Suffix Search List. . . . . : STATELESS.com
```

```
Ethernet adapter Ethernet0:
```

```
Connection-specific DNS Suffix . : STATELESS.com  
Description . . . . . : Intel(R) 82574L Gigabit Network Connection  
Physical Address. . . . . : 00-50-56-83-63-6D  
DHCP Enabled. . . . . : Yes  
Autoconfiguration Enabled . . . . : Yes  
IPv6 Address. . . . . : 2001:db8:acad:1:5c43:ee7c:2959:da68 (Preferred)
```


Lab - Configure DHCPv6

```
Temporary IPv6 Address. . . . . : 2001:db8:acad:1:3c64:e4f9:46e1:1f23(Preferred)
Link-local IPv6 Address . . . . . : fe80::5c43:ee7c:2959:da68%6(Preferred)
IPv4 Address. . . . . : 169.254.218.104(Preferred)
Subnet Mask . . . . . : 255.255.0.0
Default Gateway . . . . . : fe80::1%6
DHCPv6 IAID . . . . . : 50334761
DHCPv6 Client DUID. . . . . : 00-01-00-01-24-F5-CE-A2-00-50-56-B3-63-6D
DNS Servers . . . . . : 2001:db8:acad::254
NetBIOS over Tcpi. . . . . : Enabled Connection-
specific DNS Suffix Search List : STATELESS.com
```

```
C:\>ipconfig /all

FastEthernet0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Physical Address. . . . . : 0060.2F1A.96BD
    Link-local IPv6 Address . . . . . : FE80::260:2FFF:FE1A:96BD
    IPv6 Address. . . . . : 2001:DB8:ACAD:1:260:2FFF:FE1A:96BD
    IPv4 Address. . . . . : 0.0.0.0
    Subnet Mask . . . . . : 0.0.0.0
    Default Gateway . . . . . : FE80::1
                                0.0.0.0
    DHCP Servers . . . . . : 0.0.0.0
    DHCPv6 IAID . . . . . :
    DHCPv6 Client DUID. . . . . : 00-01-00-01-70-DD-56-6C-00-60-2F-1A-96-BD
    DNS Servers . . . . . : ::
                                0.0.0.0

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Physical Address. . . . . : 0040.0B63.8698
    Link-local IPv6 Address . . . . . : ::
    IPv6 Address. . . . . : ::
    IPv4 Address. . . . . : 0.0.0.0
    Subnet Mask . . . . . : 0.0.0.0
    Default Gateway . . . . . : ::
                                0.0.0.0
    DHCP Servers . . . . . : 0.0.0.0
    DHCPv6 IAID . . . . . :
    DHCPv6 Client DUID. . . . . : 00-01-00-01-70-DD-56-6C-00-60-2F-1A-96-BD
    DNS Servers . . . . . : ::
                                0.0.0.0
```

- f. Test connectivity by pinging R2's G0/0/1 interface IP address.

```
C:\>ping 2001:db8:acad:2::1

Pinging 2001:db8:acad:2::1 with 32 bytes of data:

Reply from 2001:DB8:ACAD:2::1: bytes=32 time<1ms TTL=255
Reply from 2001:DB8:ACAD:2::1: bytes=32 time<1ms TTL=255
Reply from 2001:DB8:ACAD:2::1: bytes=32 time<1ms TTL=255
Reply from 2001:DB8:ACAD:2::1: bytes=32 time<1ms TTL=255

Ping statistics for 2001:DB8:ACAD:2::1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\>
```

Part 4: Configure a stateful DHCPv6 server on R1

In Part 4, you will configure R1 to respond to DHCPv6 requests from the LAN on R2.

- Create a DHCPv6 pool on R1 for the 2001:db8:acad:3:aaa::/80 network. This will provide addresses to the LAN connected to interface G0/0/1 on R2. As a part of the pool, set the DNS server to 2001:db8:acad::254, and set the domain name to STATEFUL.com.

```
R1(config)# ipv6 dhcp pool R2-STATEFUL
R1(config-dhcp)# address prefix 2001:db8:acad:3:aaa::/80
R1(config-dhcp)# dns-server 2001:db8:acad::254
R1(config-dhcp)# domain-name STATEFUL.com
```

- Assign the DHCPv6 pool you just created to interface g0/0/0 on R1.

```
R1(config)# interface g0/0/0
R1(config-if)# ipv6 dhcp server R2-STATEFUL
R1(config)#ipv6 dhcp pool R2-STATEFUL
R1(config-dhcpv6)#address prefix 2001:db8:acad:3:aaa::/80
R1(config-dhcpv6)#dns-server 2001:db8:acad::254
R1(config-dhcpv6)#domain-name STATEFUL.com
R1(config-dhcpv6)#exit
R1(config)#interface g0/0/0
R1(config-if)#ipv6 dhcp server R2_STATEFUL
R1(config-if)#
```

Part 5: Configure and verify DHCPv6 relay on R2.

In Part 5, you will configure and verify DHCPv6 relay on R2, allowing PC-B to receive an IPv6 Address.

Step 1: Examine the SLAAC address.

- Power on PC-B.

IPv6 Configuration	
☒ Automatic	☐ Static
IPv6 request successful.	
IPv6 Address	2001:DB8:ACAD:3:201:97FF:FEC6:2465 / 64
Link Local Address	FE80::201:97FF:FEC6:2465
Default Gateway	FE88::1
DNS Server	

- Examine the SLAAC address that is generated.

```
C:\Users\Student> ipconfig /all
Windows IP Configuration
```

```
Host Name . . . . . : DESKTOP-3FR7RKA
Primary Dns Suffix . . . . . :
Node Type . . . . . : Hybrid
IP Routing Enabled. . . . . : No
WINS Proxy Enabled. . . . . : No
```

```
Ethernet adapter Ethernet0:
```

```
Connection-specific DNS Suffix . :
Description . . . . . : Intel(R) 82574L Gigabit Network Connection
Physical Address. . . . . : 00-50-56-B3-7B-06
DHCP Enabled. . . . . : Yes
```

Lab - Configure DHCPv6

```
Autoconfiguration Enabled . . . . : Yes
IPv6 Address. . . . . : 2001:db8:acad:3:a0f3:3d39:f9fb:a020 (Preferred)
Temporary IPv6 Address. . . . . : 2001:db8:acad:3:d4f3:7b16:eeee:b2b5 (Preferred)
Link-local IPv6 Address . . . . . : fe80::a0f3:3d39:f9fb:a020%6 (Preferred)
IPv4 Address. . . . . : 169.254.160.32 (Preferred)
Subnet Mask . . . . . : 255.255.0.0
Default Gateway . . . . . : fe80::1%6
DHCPv6 IAID . . . . . : 50334761
DHCPv6 Client DUID. . . . . : 00-01-00-01-24-F2-08-38-00-50-56-B3-7B-06
DNS Servers . . . . . : fec0:0:0:ffff::1%1
fec0:0:0:ffff::2%1
fec0:0:0:ffff::3%1    NetBIOS over Tcpip. . . . . :
Enabled
```

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig /all

FastEthernet0 Connection: (default port)

    Connection-specific DNS Suffix...:
    Physical Address. . . . . : 0001.97C6.2465
    Link-local IPv6 Address . . . . . : FE80::201:97FF:FEC6:2465
    IPv6 Address. . . . . : 2001:DB8:ACAD:3:201:97FF:FEC6:2465
    IPv4 Address. . . . . : 0.0.0.0
    Subnet Mask . . . . . : 0.0.0.0
    Default Gateway . . . . . : FE88::1
                                0.0.0.0

    DHCP Servers . . . . . : 0.0.0.0
    DHCPv6 IAID . . . . . :
    DHCPv6 Client DUID. . . . . : 00-01-00-01-A8-8C-8B-9A-00-01-97-C6-24-65
    DNS Servers . . . . . : ::
                                0.0.0.0

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Physical Address. . . . . : 0060.4790.21EA
    Link-local IPv6 Address . . . . . : ::
    IPv6 Address. . . . . : ::
    IPv4 Address. . . . . : 0.0.0.0
    Subnet Mask . . . . . : 0.0.0.0
    Default Gateway . . . . . : ::
                                0.0.0.0

    DHCP Servers . . . . . : 0.0.0.0
    DHCPv6 IAID . . . . . :
    DHCPv6 Client DUID. . . . . : 00-01-00-01-A8-8C-8B-9A-00-01-97-C6-24-65
    DNS Servers . . . . . : ::
                                0.0.0.0

C:\>
```

- c. Notice in the output that the prefix used is 2001:db8:acad:3::

Step 2: Configure R2 as a DHCP relay agent for the LAN on G0/0/1.

- a. Configure the **ipv6 dhcp relay** command on R2 interface G0/0/1, specifying the destination address of the G0/0/0 interface on R1. Also configure the **managed-config-flag** command.

```
R2(config)# interface g0/0/1
```

Lab - Configure DHCPv6

```
R2(config-if)# ipv6 nd managed-config-flag R2(config-if)# ipv6 dhcp
relay destination 2001:db8:acad:2::1 g0/0/0
```

```
R2(config)#interface g0/0/1
R2(config-if)#ipv6 nd managed-config-flag
R2(config-if)#ipv6 dhcp relay destination 2001:db8:acad:2::1 g0/0/0
^
% Invalid input detected at '^' marker.
```

```
R2(config-if)#
```

ipv6 dhcp relay command is not working

b. Save your configuration.

```
R2#wr
Building configuration...
[OK]
R2#
```

Step 3: Attempt to acquire an IPv6 address from DHCPv6 on PC-B.

- Restart PC-B.
- Open a command prompt on PC-B and issue the command **ipconfig /all** and examine the output to see the results of the DHCPv6 relay operation.

```
C:\Users\Student> ipconfig /all
Windows IP Configuration
```

```
Host Name . . . . . : DESKTOP-3FR7RKA
Primary Dns Suffix . . . . . :
Node Type . . . . . : Hybrid
IP Routing Enabled. . . . . : No
WINS Proxy Enabled. . . . . : No
DNS Suffix Search List. . . . . : STATEFUL.com
```

Ethernet adapter Ethernet0:

```
Connection-specific DNS Suffix . : STATEFUL.com
Description . . . . . : Intel(R) 852574L Gigabit Network Connection
Physical Address. . . . . : 00-50-56-B3-7B-06
DHCP Enabled. . . . . : Yes
Autoconfiguration Enabled . . . . : Yes
IPv6 Address. . . . . : 2001:db8:acad3:aaaa::7104:8b7d:5402(Preferred)
Lease Obtained. . . . . : Sunday, October 6, 2019 3:27:13 PM
Lease Expires . . . . . : Tuesday, October 8, 2019 3:27:13 PM
Link-local IPv6 Address . . . . . : fe80::a0f3:3d39:f9fb:a020%6(Preferred)
IPv4 Address. . . . . : 169.254.160.32(Preferred)
Subnet Mask . . . . . : 255.255.0.0
Default Gateway . . . . . : fe80::2%6
DHCPv6 IAID . . . . . : 50334761
DHCPv6 Client DUID. . . . . : 00-01-00-01-24-F2-08-38-00-50-56-B3-7B-06
DNS Servers . . . . . : 2001:db8:acad::254
NetBIOS over Tcpip. . . . . : Enabled
Connection-specific DNS Suffix Search List :
STATEFUL.com
```

```
C:\>ipconfig /all

FastEthernet0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Physical Address.....: 0001.97C6.2465
    Link-local IPv6 Address.....: FE80::201:97FF:FEC6:2465
    IPv6 Address.....: 2001:DB8:ACAD:3:201:97FF:FEC6:2465
    IPv4 Address.....: 0.0.0.0
    Subnet Mask.....: 0.0.0.0
    Default Gateway.....: FE88::1
                        0.0.0.0

    DHCP Servers.....: 0.0.0.0
    DHCPv6 IAID.....:
    DHCPv6 Client DUID.....: 00-01-00-01-A8-8C-8B-9A-00-01-97-C6-24-65
    DNS Servers.....: ::
                        0.0.0.0

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Physical Address.....: 0060.4790.21EA
    Link-local IPv6 Address.....: ::
    IPv6 Address.....: ::
    IPv4 Address.....: 0.0.0.0
    Subnet Mask.....: 0.0.0.0
    Default Gateway.....: ::
                        0.0.0.0

    DHCP Servers.....: 0.0.0.0
    DHCPv6 IAID.....:
    DHCPv6 Client DUID.....: 00-01-00-01-A8-8C-8B-9A-00-01-97-C6-24-65
    DNS Servers.....: ::
                        0.0.0.0
```

- c. Test connectivity by pinging R1's G0/0/1 interface IP address.

```
C:\>ping 2001:db8:acad:1::1

Pinging 2001:db8:acad:1::1 with 32 bytes of data:

Reply from 2001:DB8:ACAD:1::1: bytes=32 time=6ms TTL=254
Reply from 2001:DB8:ACAD:1::1: bytes=32 time=3ms TTL=254
Reply from 2001:DB8:ACAD:1::1: bytes=32 time<1ms TTL=254
Reply from 2001:DB8:ACAD:1::1: bytes=32 time<1ms TTL=254

Ping statistics for 2001:DB8:ACAD:1::1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 6ms, Average = 2ms

C:\>
```