FTL Quote SOP

Owner: Jericho Freight	**Effective Date: 08/25/26**
Version: 1.0	**Department: Brokerage**

General Information

Description / Objective	Teach any teammate how to quote a full truck, how every dollar and day is calculated, what the printed ledger means, and how to explain why a whole truck can beat shared LTL once the trailer is full enough.
Assignee	Santiago Rendon

Glossary

1. What FTL is
2. How to open it
3. Customer and previous FTL quotes
4. Route, miles, notes, and valid until
5. Equipment and load
6. Utilization math
7. Transit days and the 600-mile rule
8. All-in pricing ledger math
9. LTL comparison
10. Carbon
11. Generate and FTL-Q file name
12. Output fields and customer value
13. What to say out loud
14. Common mistakes
15. Definitions

1. What FTL is

1.1 Kid picture

FTL means Full Truckload. The customer rents the whole truck, like hiring a whole moving van instead of sharing a bus. Nobody else's boxes get mixed in. That usually means faster, simpler, and better care, and it costs more until the trailer is fairly full.

Use FTL when pallet count is high, freight is heavy, freight is fragile, or the customer hates terminal handling. LTL freight gets touched at terminals. FTL usually goes dock to dock.

2. How to open it

2.1 Click path

Home screen, click FTL. Header should say FTL Quote Builder. Change User must already be filled so your name prints.

3. Customer and previous FTL quotes

3.1 Mode-only memory

Include customer on quote works like other modes. Load Previous Quote here only lists FTL snapshots labeled FTL-Q plus the number. It will not load LTL or Dray.

4. Route, miles, notes, and valid until

4.1 Lane boxes

Origin city, origin ZIP, destination city, destination ZIP. ZIPs are required. Click Calculate Distance. Miles save into a hidden box. Blurring the ZIP fields also tries to refresh miles.

If you type a flat linehaul and later get miles, the app can fill rate per mile as linehaul / miles. If you type rate per mile, it can fill linehaul as rpm x miles. Last box you edited wins.

Valid Until defaults to 7 days from today if you leave it blank. FTL spot prices move faster than LTL menus, so the printed quote says it is valid for that many days.

Notes print on the quote. Use them for temperature, appointments, or 'driver must have a pallet jack.'

5. Equipment and load

5.1 Pick the right trailer

Van (V) is a dry box. Default. About 26 pallet spots and 45,000 lb payload.

Reefer (R) is a fridge on wheels. About 26 spots and 43,500 lb. A pre-cool checkbox appears. Check it to add $75.

Boxtruck (SB) is a smaller city truck. About 12 spots and 10,000 lb.

Flatbed (F), Stepdeck (SD), Hotshot (HS), RGN, and Low-boy (LB) are open decks for freight that does not fit in a box. A tarps box appears. Each tarp adds $50.

Pallet count and total weight (lb) are optional but they unlock utilization and some carbon math. Team drivers checkbox means two drivers sharing the truck so it can keep moving. That halves the drive days in the 600-mile rule.

6. Utilization math

6.1 How full is the truck?

Position utilization percent = pallets / equipment spots x 100. Over-positions is true if pallets are greater than spots. Then you need two trucks or a different idea.

Weight utilization percent = weight / payload x 100. Over-weight is true if you exceed payload. Then you are illegal or you need a heavier setup. Do not quote that as one truck.

Fill percent

position % = pallets / spots x 100

weight % = pounds / payload pounds x 100

Tiny example: van, 20 pallets, 30,000 lb. Position % = 20/26 x 100 = 76.9%. Weight % = 30000/45000 x 100 = 66.7%. The truck is space-full before it is weight-full.

7. Transit days and the 600-mile rule

7.1 Why 600?

One truck driver is allowed about 11 hours of driving in a work day. At about 55 miles an hour, that is roughly 600 miles. The app uses 600 on purpose so every mode tells the same story.

Drive days = miles / (600 x number of drivers). Team uses 2 drivers. The result is rounded to one decimal for the mean.

The printed window is not a hard appointment. It is mean plus and minus a buffer that grows with trip length and equipment type. Reefers and specialty gear get a slightly wider wobble. If this lane has real history in the local database, the app may swap in a history-backed prediction interval instead of the pure mileage guess.

Days on the road

mean days = miles / (600 x drivers)

Tiny example: 1,200 miles, solo van. 1200/600 = 2.0 days. Team would be 1200/1200 = 1.0 day. Always say this is a planning window, not a promise, unless a guaranteed product is sold separately.

8. All-in pricing ledger math

8.1 How the total is built

If you typed a flat linehaul, that number is the linehaul. If not, linehaul = rate per mile x miles. If you typed neither, rate per mile falls back to $2.50.

Fuel surcharge is optional. Check Include fuel surcharge, then enter a percent of linehaul or a dollar amount. Unchecked, or $0, means no fuel line on the quote.

Pre-cool adds $75 only on reefer when checked.

Tarps add $50 times the tarp count, only on open-deck equipment.

All-in total = linehaul + fuel (if included) + extras. Cost per mile = total / miles. Cost per position = total / pallets.

All-in total

linehaul = flat linehaul, or else rpm x miles (rpm default 2.50)

fuel = linehaul x fsc% / 100, or the dollar amount you typed, only if Include fuel surcharge is on

extras = pre-cool 75 (reefer) + tarps x 50 (open deck)

total = linehaul + fuel + extras

Tiny example: $2,000 linehaul, 20% fuel, $75 pre-cool. Fuel = $400. Total = $2,475. At 1,000 miles, cost per mile = $2.475.

9. LTL comparison

9.1 When the checkbox is on

You may type up to three LTL options with a label, a pallet max, and a total. The app builds a table next to this FTL total.

Savings = cheapest LTL total minus FTL total. Positive savings means FTL is cheaper. Breakeven pallets is a rough 'at this many pallets FTL starts winning' using the cheapest LTL per-pallet rate.

Only fill this if you actually have LTL numbers. Fake LTL rows teach the wrong lesson.

10. Carbon

10.1 Footprint

kg CO2e = miles x short tons x 0.162. Short tons = pounds / 2000. If pounds are missing, the app may use pallets x 500 lb. This is an EPA-style truck factor, not a lab measurement. Use it when the customer asks, not as a scare line.

11. Generate and FTL-Q file name

11.1 Print

Generate Quote writes the page and remembers the form for Load Previous Quote. Print Quote names the file FTL-Q plus the number, for example FTL-Q4242.

12. Output fields and customer value

12.1 Walk the PDF

Route block: origin, destination, miles, notes. This is 'where and how far.'

Guaranteed All-In Freight Ledger: every money line plus the total. This is what they pay if the extras you listed happen. Unlisted extras (lumper, extra stop) are not included. Say that out loud.

Equipment Utilization: fill percents. Customers use this to see they are not buying empty air, or that they are overweight.

Delivery window: planning days with a percent confidence (usually 90%). Direct, no terminals is the FTL promise versus LTL's extra handling.

Mode Comparison: only if you entered LTL options. Use it to recommend FTL vs LTL with numbers, not vibes.

Estimated Footprint: CO2. Optional conversation.

Validity days: how long this price is good.

13. What to say out loud

13.1 Simple pitch

You can say: 'This price is for the whole truck, door to door, no sharing. The bottom line includes the extras we checked. The day range is how long the drive should take at about 600 miles a day for one driver.'

14. Common mistakes

14.1 Watch-outs

Typing fuel as $20 instead of 20%. Twenty percent of $2,000 is $400. Twenty dollars is $20.

Quoting 30 pallets on a 26-spot van.

Leaving miles at 0, then presenting cost per mile as if it were real.

Checking LTL comparison with empty totals.

Promising team transit times without checking Team drivers.

Definitions	
FTL	Full Truckload. One customer, whole trailer.
RPM	Rate per mile. Dollars for each mile the truck drives.

Pre-cool	Running the reefer before loading so the box is already cold. $75 in this app.
Team	Two drivers. The truck can move about twice as many miles per day.
HOS	Hours of Service. Federal drive-time rules. Why we use 600 miles a day.
FTL-Q	Print file prefix for this mode.

Reviewed By:	**Date:**
Approved By:	**Date:**
Last Updated By:	**Date / Time:**