

IBM Education Assistance for z/OS V2R1

Item: ENF 70 Events

Element/Component: JES3



Agenda

- Trademarks
- Presentation Objectives
- Overview
- Usage & Invocation
- Migration & Coexistence Considerations
- Appendix

Trademarks

See url http://www.ibm.com/legal/copytrade.shtml for a list of trademarks.

Presentation Objectives

To understand what ENF 70 events are and how to listen for them



Overview

Problem Statement / Need Addressed

- JES3 exits are needed to monitor job level phase changes
 - Affects vendor and customer products

Solution

A new ENF 70 event for JES3 has been added for tracking job status

Benefit / Value

- Reduces the requirement for JES3 exits to track job flow, simplifying migration to new releases
- Also allows programs to monitor job status changes without issuing repetitive SSI 80 calls
- Allows programs to monitor job status changes in a JES-independent way

- Multi-system ENF 70 events are issued when jobs change state
 - -ENF70_SELECT indicates job was selected by a processing phase
 - conversion, execution, job transmitter, etc.
 - –ENF70_DESELECT indicates job was deselected by a processing phase
 - -ENF70_CHANGE indicates job was queued for a new phase
 - old and new phases are identified
 - this event also includes being requeued to a new class or service class queue prior to execution
 - -ENF70_PURGE indicates job was purged
- See next slide for job fields returned, for each type of ENF 70 event mentioned above



 Mapped by IAZENF70 - Includes information to identify the job and its current status:

```
ENF70 ID
                        CL6
                                    Eye catcher 'ENF70 '
                 DS
ENF70 VERSION
                                    Version of mapping
                 DS
                        X
ENF70 LENGTH
                 DS
                        F
                                    Total length of ENF70 data
                                    Length of fixed section
ENF70 FIXED LENGTH DS
                        Н
ENF70 QUALIFIER DS
                                    Qualifier code - defined below
                        XT.1
ENF70 SELECT
                        1
                                        Job was selected
                 EOU
ENF70 DESELECT
                        2
                                       Job was processed
                 EQU
ENF70 CHANGE
                        3
                                       Job queued to new phase
                 EQU
                                       Job was purged
ENF70 PURGE
                 EOU
ENF70 JES NAME
                        CL8
                                    JES2 Member/JES3 MAIN where signal originated
                 DS
ENF70 JESPLEX ID DS
                        XL8
                                    Unique JESPLEX identifier
ENF70 JOBNAME
                 DS
                        CL8
                                    Job name
ENF70 JOBID
                        CL8
                                    Job ID
                 DS
                                    Original Job ID
ENF70 ORG JOBID
                        CL8
                 DS
                        CL8
                                    Original Node
ENF70 ORG NODE
                 DS
ENF70 JOBCLASS
                 DS
                        CL8
                                    Job Class
                        CL8
ENF70 SRVCLASS
                 DS
                                    Service class
ENF70 RDR DATE
                        F
                                    Reader on date
                 DS
ENF70 RDR TIME
                 DS
                        F
                                    Reader on time
ENF70 MAXCC
                 DS
                        XL4
                                    Job completion code
ENF70 QUEUE
                 DS
                        XL1
                                    Current phase job is queued for
ENF70 JESDATA
                        CL16
                                    JES-specific data for job
                 DS
```



• More fields mapped by IAZENF70:

```
ENF70_VEXT DSECT ENF70 variable data extension ENF70_VEXT_EYE DC CL6'ENF70X' Eyecatcher ENF70_VEXT_LENGTH DS H Length of variable extension ENF70_REQDATA DS 0D Beginning of variable data ENF70_VEXT_SIZE0 EQU *-ENF70_VEXT
```

```
REQUEST=Q SELECT or Q DESELECT
ENF70 DEVICE
                   DS
                        CL10
                                     Device name
ENF70 DEVICE TYPE
                        XL1
                                     Device class
ENF70 DTYPE DEV
                   EQU
                        1
                                       Standard device
ENF70 DTYPE JINIT
                   EQU
                       2
                                       JES Initiator
ENF70 DTYPE WINIT
                   EQU
                       3
                                       WLM Initiator
ENF70 DTYPE PHASE
                   EQU
                       4
                                       Select for current phase
ENF70 DESEL FLG1
                   DS
                        XL1
                                     Reserved
ENF70 DESEL REQUE
                       B'10000000' Job to be requeued for execution
                   EQU
ENF70 DEV DATA
                                     JES-specific device data
                   DS
                        XL4
```

```
* REQUEST=Q_CHANGE

ENF70_OLD_QUEUE DS XL1 Phase job moved from

ENF70_OLD_JCLASS DS CL8 Previous job class

ENF70_OLD_SCLASS DS CL8 Previous service class
```



Use ENFREQ macro to listen for ENF 70 events, for example:

```
ENFREQ ACTION=LISTEN, Initiate the ENF70 listener

CODE=ENFPC070, Listen for ENF 70 events

EXIT=(R0), R0 contains address of listener rtn

XSYS=YES,

etc.
```

- When an ENF 70 event is signalled, a parameter list mapped by IAZENF70 is passed to the listener
- See (SA23-1373) MVS Programming: Authorized Assembler Services Reference, Volume 2 (EDT-IXG) for more information on ENFREQ

- By default, JES3 signals ENF 70 events across all systems in a SYSPLEX
- Use the OPTIONS JES3 initialization statement to control the signalling scope of ENF 70 events:
 - ...JOBTRACK=SYSPLEX,... is also the default
 - ...JOBTRACK=JGLOBAL,... ENF 70 events will be signaled only to listeners residing on the JES3 Global
 - ...JOBTRACK=OFF,... ENF 70 event signalling is disabled
- Use
 - *MODIFY, JOBTRACK = SYSPLEX | JGLOBAL | OFF, or
 - *MODIFY,CONFIG

to change signalling scope of ENF 70 events, after JES3 has started

 Use *INQUIRY,OPTIONS to display the value of the JOBTRACK parameter setting currently in effect



Migration & Coexistence Considerations

- Migration: None.
- ENF 70 listeners can exist on back-level mains, but the JES3 Global main must be at V2R1, otherwise the ENF 70 events will not be signalled.

Appendix

See MVS Programming: Authorized Assembler Services Reference,
 Volume 2 (EDT-IXG) – SA23-1373, for more information on ENFREQ on how to listen for ENF 70 events