

Acuity Installation Guide

Sage Software, Inc.

4AIN640-0799

Information in this document is furnished only under a Customer License Agreement or non-disclosure agreement, and may be used or copied only in accordance with the terms of such agreement. The software described in this document is protected by copyright, and may not be copied on any medium except as specifically authorized in the license or non-disclosure agreement.

This document is also protected by copyright, and may not be reproduced or transmitted, in whole or in part, by any means, including photocopying, facsimile transmission, or reduction to any electronic medium or machine-readable form, without the express written consent of Sage Software, Inc.

Copyright 1996-1999 Sage Software, Inc. All rights reserved.

Acuity Financials, Acuity, and Sage Software are trademarks of Sage Software, Inc. Other product names used in this document are trademarks or registered trademarks of their respective owners.

Contents

1 ACUITY REQUIREMENTS

SQL server requirements	2
Windows NT Server overview	2
Microsoft SQL Server 7 overview	2
Microsoft SQL Server 6.5 overview	4
Windows Terminal Server requirements	4
Windows Terminal Server overview	5
File server requirements	6
Local and Network Client requirements	6
Year 2000 compliance	7
Where to go from here	7

2 CREATING ACUITY DATABASES

Microsoft SQL Server 7 requirements	10
Microsoft SQL Server 7 checklist	10
Microsoft SQL Server 6.5 requirements	12
Microsoft SQL Server 6.5 checklist	13
Database creation	14
Database sizing recommendations	17
Establishing a maintenance plan	18
Logging in to Acuity	20

3 ACUITY CLIENT

Installing the Local Client	24
Client requirements	24
Client checklist	24
Installing the Network Client	29
File server requirements	30
File server checklist	30

Client requirements	32
Client checklist	33
Installing on a Windows Terminal Server	35
Windows Terminal Server requirements	35
Windows Terminal Server checklist	36
Installing Acuity using Add/Remove Programs	36
Installing Acuity using the Change User function	38
Removing Acuity	39
Reinstalling the Acuity Client	42
Upgrading the Acuity Client	44

4 UPGRADING THE ACUITY DATABASES

Microsoft SQL Server requirements	48
Microsoft SQL Server checklist	48
Before starting the database upgrade	49
Database upgrade utility installation	49
Running the database upgrade utility	50
Comparing databases	50
Upgrading databases	52
Acuity database upgrade from SQL Server 6.5 to SQL Server 7.0	55

5 UTILITIES AND UPDATES

Third party utilities and program updates	58
Internet Explorer version 5.0	58
Microsoft Windows NT 4.0 Service Pack 5	58
Microsoft SQL Server 6.5 Service Pack 5a	58
Microsoft SQL Server 7.0 Service Pack 1	58
Microsoft Data Access Components 2.1	59
Distributed Component Object Model 95	59
Scripting	59
RegClean	59

6 MODULE ENHANCEMENTS

Global enhancements	62
Version 4.1 user manuals	62

Registry Editor	63
User login	64
Calendar control	65
System Manager	66
System management	66
Reports	69
General Ledger	69
GL Utilities	69
Reports	78
Accounts Payable	80
Maintenance	80
AP Utilities	81
Multicurrency Management	84
Reports	84
Cash Management	85
Reports	85
Purchase Order	86
Maintain blanket purchase orders	86
Inventory Management	86
Inventory calendar	86
Set up purchase product lines	88
Maintain items	89
Inquiries	89
Accounts Receivable	94
AR Utilities	94
Sales Order	99
Maintain blanket sales orders	99

APPENDICES

Appendix A: Installing on Windows NT Clients	102
Administrator installation	102
Appendix B: Client post-installation notes	103
Appendix C: Installing Seagate Crystal Reports Designer	105
Seagate Crystal Reports requirements	105
Seagate Crystal Reports checklist	105
Installing Seagate Crystal Reports for Acuity	106
Appendix D: Copying Acuity databases	109

Microsoft SQL Server 7 requirements	109
Microsoft SQL Server 7 checklist	110
Microsoft SQL Server 6.5 requirements	111
Microsoft SQL Server 6.5 checklist	112
The Database Synchronization Utility	113
Appendix E: Protocol issues	121
Windows 95 and Windows 98 clients	121
Windows NT 4.0 Workstation client	126
Appendix F: Command-line execution	135
Important notes	135
Obtaining the task ID	136
Appendix G: Silent mode installation	155
Creating the script	155
Executing the script	155
Script definition	156

Chapter 1

A C U I T Y Requirements

Welcome to Acuity®. We have striven to bring you a product that is easy to use and rich in features, including flexible reporting abilities through Seagate Crystal Reports™ for Acuity. Acuity is a client / server-based product that takes advantage of the technological innovations available to full 32-bit Windows® 95, Windows® 98, and Windows NT® 4.0 applications. The following sections describe the requirements for installing Acuity:

- SQL server requirements (page 2)
- Windows Terminal Server requirements (page 4)
- File server requirements (page 6)
- Local and Network Client requirements (page 6)
- Year 2000 compliance (page 7)
- Where to go from here (page 7)

SQL server requirements

Acuity has specific server platform requirements. Verify that your server meets the minimum hardware configuration recommendations outlined below. Review the Platform Matrix in the Preinstall Section of our website at www.us.sage.com/acuity/ support for any updates to this information.



Tip

You can download the Service Packs from the Acuity CD or from the Microsoft web site at <ftp://ftp.microsoft.com/softlib/mslfiles>.

- Intel Pentium® II class (350MHz or better recommended) or DEC Alpha class processor
- Minimum of 128MB of RAM (recommendation varies based on user count)
- Windows NT Server 4.0 with Service Pack 5 or better
- Microsoft® SQL Server™ 6.5 with Service Pack 5a or better or Microsoft SQL Server 7.0 with Service Pack 1.
- Minimum of 225MB of available disk space for the Server Install of the Acuity database utilities.
- Minimum of 440MB of available disk space for database creation.

Windows NT Server overview

Configure the Windows NT Server as a dedicated database server. Routable protocols, which include TCP/IP and IPX/SPX (NWLink bindings in NT), are the only supported network protocols for your Acuity software. You can implement TCP/IP as long as IP addresses have been assigned at the client and server. You can use IPX/SPX when the NT server and clients are properly configured or attached to a NetWare server. To use either or both, they must be installed on the client and server under the Network Settings applet in Control Panel. For more information, refer to “IPX Protocol” and “TCP/IP” in the *Windows NT Books Online Index*.

Microsoft SQL Server 7 overview

If you are using the Fixed Memory option, the Microsoft SQL Server 7.0 should be configured with a minimum allocation of 32MB of RAM.

When allocating fixed memory or a memory range, follow Microsoft's rough estimates for dedicated SQL Servers. The figures in the following table are available from the *SQL Server Books Online™* documentation. For detailed information on how SQL Server utilizes memory, view the SQL Server Memory Pool and Enhancing Performance topics.

Machine memory (MB)	SQL Server maximum memory allocation (MB)
128	100
256	216
512	464

For Microsoft SQL Server 7.0, Acuity supports the use of the SQL Server and Windows NT security model.

The following is the supported Microsoft SQL Server 7.0 configuration under which Acuity has been thoroughly tested:

- Character Set - ISO - Code Page 1252
- Sort Order - Dictionary Order, Case Insensitive - ID 52 (Default)
- Sort Order - Dictionary Order, Case Sensitive - ID 51

Minimum values of Microsoft SQL Server Properties include:

- Minimum Server Memory - 8MB
- Default language for user - English
- Allow nested triggers option selected
- Query governor cost of 0
- Y2K support setting between 1950 and 2049
- Minimum concurrent user connections - 15 x <number of client connections>
- Default Connection Options - none of the Attribute values selected

Microsoft SQL Server 6.5 overview

The Microsoft SQL Server 6.5 should be configured with a minimum allocation of 32MB (16384 - 2K pages) of RAM.

Memory recommendations vary, but should follow Microsoft's rough estimates for dedicated SQL Servers. The following figures are available from the *SQL Server Books Online™* documentation.

Machine memory (MB)	SQL Server memory allocation (MB)
128	100
256	216
512	464

For Microsoft SQL Server 6.5, Acuity requires the use of SQL Server's Standard Security model.

The following is the supported Microsoft SQL Server configuration (under which Acuity has been thoroughly tested):

- Character Set - ISO 8859-1 (Default)
- Sort Order - Dictionary Order, Case Insensitive - ID 52 (Default)
- Sort Order - Dictionary Order, Case Sensitive - ID 51
- Standard Security

Minimum values of Microsoft SQL Server Configuration/Options include:

- Locks - 10,000 or more depending on number of users
- Open Objects - 10,000 or more depending on the number of users
- User Connections - 15 x <number of client connections>

Windows Terminal Server requirements

- Dual Intel Pentium class or higher or DEC Alpha class processor
- Minimum of 128MB of RAM plus an additional 64MB for each typical user

- Minimum of 400MB of available disk space
- SCSI hard drives (caching array recommended)

Windows Terminal Server overview

Windows Terminal Server allows for multiple user sessions to run concurrently on a shared server. You can use one NT user account to establish multiple Windows Terminal sessions from the same terminal or different terminals. You cannot use an NT user account more than once to establish a Terminal session and run Acuity. Shared objects in the running table (ROT) on the Windows Terminal Server cause this limitation. You can have more than one user running Acuity on a Windows Terminal Server; however, the users must have different NT user accounts. Acuity does not detect multiple instances of itself under the same NT user account. A terminal session can remain open if you do not log off. It is possible to reconnect to an open session or establish a new session. If you establish a new session under the same NT user account, and an old session is still open and running Acuity, attempting to run Acuity on the newly established session fails.

The following recommendations are available from the *Windows NT® Server Terminal Server Edition, version 4.0* documentation.

Purchasing a multiprocessor system allows you to add capacity as your number of users grows. Processor and memory requirements scale linearly (up to four processors). For example, you can support double the number of users on a multiprocessor-capable Pentium system by doubling the number of processors and doubling the amount of memory.

The bus architecture in single and multiprocessor systems affects system performance. For best performance, use a higher-performance bus, such as EISA, MCA, or PCI.

Although the Remote Desktop Protocol (RDP) used with Terminal Server causes negligible network load, a high-performance network interface (NIC) is recommended. This is particularly important if many disparate users require access to Acuity.

If a multiport asynchronous communications adapter is installed to support dial-in users, use an intelligent (microprocessor-based) adapter to reduce interrupt overhead.

File server requirements

Acuity supports a network installation of the client software. From the workstation, you can access the client software using either a UNC (Universal Naming Convention) designation or a mapped drive letter. Acuity does not require specific operating systems, but we do recommend the following minimum specifications for an Acuity network file server:

- Pentium II processor (dual is preferred)
- Minimum of 64MB of RAM for Windows NT
- 350MB of available disk space
- Available share point or shared volume
- 10Mb/s network connection
- SCSI hard drives

Because of performance considerations, we strongly recommend against employing the SQL Server as the file server for Acuity programs.

Local and Network Client requirements

As of the publication of this guide, Acuity supports the Microsoft Windows 95, Microsoft Windows 98, and Microsoft Windows NT Workstation operating systems at the client. For updates to this information, review the Platform Matrix in the Preinstall Section of our website at www.us.sage.com/acuity/support.

We require the following minimum hardware specifications for running Acuity:

- Pentium II class or better processor
- Minimum of 64MB of RAM (128MB or more recommended)
- SVGA Monitor and Video Drivers (800x600 resolution)
- 325MB of available disk space for a local client installation
- 50MB of available disk space for a network client installation
- Windows 95, Windows 98, or Windows NT 4.0

- DCOM95 for machines with a Windows 95 operating system
- A default print device

Acuity has been tested on the supported network communications mechanisms outlined below. Refer to “Appendix E: Protocol issues” on page 121 for more information.

SQL Net-Library	Network Protocol
Named Pipes	TCP /IP
Multi-Protocol	TCP /IP
TCP /IP Sockets	TCP /IP
NWLink IPX /SPX	IPX /SPX

Year 2000 compliance

You can view documentation regarding year 2000 compliance for Acuity on the home page of Sage Software’s web site at <http://www.us.sage.com>

Where to go from here

- For a new Acuity installation, review chapter 2, “Creating Acuity Databases” and chapter 3, “Acuity Client.”
- If you are upgrading, review chapter 4, “Upgrading the Acuity Databases” and review “Upgrading the Acuity Client” on page 44.
- To move or recreate Acuity databases, refer to “Appendix D: Copying Acuity databases” on page 109.
- For a new installation of the Seagate Crystal Report Designer version 6.0, refer to “Appendix C: Installing Seagate Crystal Reports Designer” on page 105.

- For a new installation or upgrade to FRx version 5.51, refer to the *FRx Installation Guide*, which you can obtain from the FRx folder on the Acuity third party CD.
- To install Acuity Web Reports, refer to the *Acuity Web Reports Installation Guide*.

For general questions or problems, refer to the Support section of our website at www.us.sage.com. Search for issues in our knowledgebase at www.us.sage.com/support. You can contact Acuity Customer Support Services by phone in the U.S. at (800) 944-5481 or for our international customers at (949) 788-5387.

Chapter 2

CREATING **Acuity Databases**

This chapter covers the installation of the Acuity database on the SQL Server. We encourage you to use the installation checklists on the following pages to aid you in completing these instructions. Follow these instructions carefully. Prior SQL Server 7.0 Database Administration training and experience is required.

- Microsoft SQL Server 7 requirements (page 10)
- Microsoft SQL Server 7 checklist (page 10)
- Microsoft SQL Server 6.5 requirements (page 12)
- Microsoft SQL Server 6.5 checklist (page 13)
- Database creation (page 14)

Microsoft SQL Server 7 requirements

Before beginning the installation or upgrade process on SQL Server 7.0, verify that your server meets the following requirements:

- Minimum of 225MB of available disk space for the Server install of the Acuity database utilities.
- Minimum of 440MB available hard disk space for a database creation.
- The tempdb size must be 1 / 3 of the application database or 100MB, whichever is larger. We recommend that you select **Automatically grow file** and **Unrestricted filegrowth** for both the database and transaction log. In the database Options, select **Select into/bulk copy**. We also recommend that you select **Truncate log on checkpoint**.
- For Microsoft SQL Server 7.0, you must have applied Service Pack 1. You can download the SQL Service Pack 1 from the Acuity CD or from the Microsoft Web site at <ftp://ftp.microsoft.com/softlib/mslfiles>. You can find instructions for applying the patches in the `Readme.txt` file.
- The Microsoft SQL Server service must be started and running before execution of the Acuity Database Creation Utility or Acuity Database Upgrade Utility.
- Your Master database in Microsoft SQL Server should have at least 50% free space. We recommend that you select **Automatically grow file** and **Unrestricted filegrowth** for both the database and transaction log. In the database Options, select **Truncate log on checkpoint**.

Microsoft SQL Server 7 checklist

Before you install or upgrade Acuity on SQL Server 7.0, use the checklist to verify that you have completed all required preliminary steps. If the answer to any of these questions is No, do not continue. Make the appropriate changes, then continue working through the checklist.

- ❑ **Is your server's operating system Windows NT Server version 4.0?**
This is the only server platform supported.
- ❑ **Have you applied Service Pack 5 for Windows NT Server 4.0?**
Service Pack 5 contains the required updates for the proper operation of Acuity.
- ❑ **Have you installed Microsoft SQL Server 7.0?**
Microsoft SQL Server 7.0 must be installed and running prior to creation of the Acuity databases.
- ❑ **Have you applied Service Pack 1 for Microsoft SQL Server 7.0?**
Service Pack 1 contains the required updates for the proper operation of Acuity.
- ❑ **Is your server processor an Intel Pentium or Digital Alpha with a minimum of 128MB of RAM?**
Your Windows NT Server should have 128MB of RAM.
- ❑ **Do you have at least 440MB of free hard disk space?**
The minimum required space for creation of the Acuity databases and devices is 440MB.
- ❑ **If you are using the Dynamic Memory option, do you have at least 8MB of RAM allocated within SQL Server?**
When using Dynamic Memory, Microsoft SQL Server 7.0 should be configured with a minimum allocation of 8MB of RAM.
- ❑ **Is your tempdb for Microsoft SQL Server configured for the larger of either 1/3 of the application database or 100MB?**
The tempdb database must be configured to 1/3 of the application database size or 100MB (whichever is larger).
- ❑ **Have you backed up your master database and other existing databases?**
In the case of a Microsoft SQL Server failure, you may have to restore the databases from a backup.
- ❑ **Is your character set ISO - Code Page 1252?**
Acuity only supports this SQL Server 7.0 default character set.
- ❑ **Is your SQL Server's Sort Order ID 51 or 52?**
Verify this value using the *sp_configure* stored procedure.
- ❑ The Default language for user Server Setting must be English.

- ❑ Select **Allow nested triggers**.
- ❑ Verify the Query governor cost limit value is set to 0.
- ❑ The Y2K support setting should be between 1950 and 2049.
- ❑ Set the minimum number of concurrent user connections to 15 x <number of client connections>.
- ❑ None of the attribute values should be selected for the Default Connection Options.

Microsoft SQL Server 6.5 requirements

Before beginning the installation or upgrade process on SQL Server 6.5, verify that your server meets the following requirements:

- Minimum of 225MB of available disk space for the Server install of the Acuity database utilities.
- Minimum of 440MB available hard disk space for database creation.
- The tempdb size must be 1/3 of the application database or 100MB, whichever is larger. We recommend creation under a device other than the default master device.
- For Microsoft SQL Server 6.5, you must have applied Service Pack 5a. You can download the SQL Service Pack 5a from the Acuity CD or from the Microsoft Web site at <ftp://ftp.microsoft.com/softlib/mslfiles>. For the Intel service pack, select `65sp4x86.exe`. For the Alpha service pack, select `65sp4alp.exe`. You can find instructions for applying the patches in the `Readme.txt` file.
- The Microsoft SQL Server service must be started and running before execution of the Acuity Database Creation Utility or Acuity Database Upgrade Utility.
- Your Master database in Microsoft SQL Server should have at least 50% free space.

Microsoft SQL Server 6.5 checklist

Before you install or upgrade Acuity on your server, use the checklist to verify that you have completed all required preliminary steps. If the answer to any of these questions is No, do not continue. Make the appropriate changes, then continue working through the checklist.

- ☐ **Is your server's operating system Windows NT Server version 4.0?**
This is the only server platform supported.
- ☐ **Have you applied Service Pack 5 for Windows NT Server 4.0?**
Service Pack 5 contains the required updates for the proper operation of Acuity.
- ☐ **Have you installed Microsoft SQL Server 6.5?**
Microsoft SQL Server 6.5 must be installed and running prior to creation of the Acuity databases.
- ☐ **Have you applied Service Pack 5a for Microsoft SQL Server 6.5?**
Service Pack 5a contains the required updates for the proper operation of Acuity.
- ☐ **Is your server processor an Intel Pentium or Digital Alpha with a minimum of 128MB of RAM?**
Your Windows NT Server should have 128MB of RAM with a minimum of 32MB configured for Microsoft SQL Server.
- ☐ **Do you have at least 440MB of free hard disk space?**
The minimum required space for creation of the Acuity databases and devices is 440MB.
- ☐ **Is your tempdb for Microsoft SQL Server configured for the larger of either 1/3 of the application database or 100MB?**
The tempdb database must be configured to 1/3 of the application database size or 100MB (whichever is larger).
- ☐ **Have you backed up your master database and other existing databases?**
In the case of a Microsoft SQL Server failure, you may have to restore the databases from a backup.


- ❑ **Is your character set ISO 8859-1?**
Acuity only supports this SQL Server default character set.
- ❑ **Is your new SQL Server's Sort Order ID 51 or 52?**
Verify this value using the *sp_configure* stored procedure.

Database creation


This section discusses the creation of the Acuity databases on a SQL Server. To begin the database creation process, you must install the Acuity Database Utilities. If you are using a DEC Alpha server, you must perform the database creation from a Windows 95, Windows 98, or Windows NT client that can attach to the SQL Server.

- 1 You must log into the Windows NT Server using the Administrator account. At this time, you should remove any previous database creation utilities, service packs, and so on, by selecting **Start | Programs | Acuity | Uninstall** <program reference>.
- 2 Begin the Acuity Database Utilities installation by inserting the Acuity CD into your CD-ROM drive. The following window appears.

! WARNING
Installation of the Database Utilities may require a system reboot.




- 3 Select **Server Install** from the Setup menu. The installation program creates the folders, if they do not already exist, and copies the software from the CD to the destination folder.
- 4 Upon completion of the Database Utilities installation, you are prompted to run the Database Creation Utility. You will not be asked to start the Database Creation Utility if you must restart your server. If you select **No** at the prompt, you can start the Database Creation Utility by selecting **Start | Programs | Acuity Financials | Acuity Database Creation Utility**.
- 5 The licensing window appears first. Review and accept the license agreement, specify the number of Acuity licenses needed, and select **OK**.
- 6 The login window appears. Specify the database server on which to create the databases and the password for the system administrator (SA) login of that server. You cannot proceed until you have provided valid login information.
- 7 The Database Creation Utility then verifies the default settings for many of the required server parameters on your SQL Server. If any of the parameters do not meet the minimum required configuration values for Acuity, a window similar to the following appears.




- 8 The Database Configuration window indicates the server parameters that must be updated, their current minimum values, and their recommended values. The Database Creation Utility

does not allow you to continue until the server configuration meets the minimum requirements. To obtain the recommended values for a given number of users, change the number of concurrent Acuity users, and select **Refresh**. Select **Apply** to update the server parameters automatically. The following window confirms your selections.



✓ Tip
Remember to verify the information on both the System Database and Company Database tab pages.


- 9 Select **Yes** to continue. The following window prompts you for information concerning the database set to create.



✓ Tip
We recommend a minimum size of 600MB for the application (company) database when creating a database for use in a production environment.

- 10 You enter the database name, size, Microsoft SQL Server device name (file), and the path in which to create this device. To place the database on an existing SQL Server 6.5 device, select **Data Device** and **Log Device**, and select the device you want to use. The device sizes listed are the minimum sizes in which you can create the Acuity databases.

- 11 Select **Proceed** to start the database creation. The following window prompts you to select your regional setting. You can select **Load Acuity demo data** to install the test data included with Acuity. We recommend that you load the demo data for testing and comparison purposes.



Database creation is a lengthy process and can take up to one hour depending on the server configuration. A display of the progress shows the current operations being performed.

Database sizing recommendations

If you are running Acuity on SQL Server 7.0, you can define growth parameters to automatically expand your database. Refer to *SQL Server Books Online* in the section, “Expanding the database” for more information on dynamic resizing in SQL Server 7.0.

If you do not define growth parameters when you create the database, or if you are running Acuity on SQL Server 6.5, you cannot size the Acuity databases any less than the sizes specified in the Database Creation Utility. However, you can increase these sizes according to the following recommendations:



TIP
Databases must be sized in 1MB increments.

System Database	5MB for every security group
Application Database	25MB for every 5,000 General Ledger transactions
Log Size	20% to 30% of the database size

These recommendations are based on the assumptions that follow. We also recommend that you have an excess of space. If you determine 1MB for the system database and 5MB for the application database to be enough, then size the databases accordingly.

System database

The sizing recommendations for the system database assume the following:

- You will add a number of users when you add a security group.
- When you add a security group, that group is being used in the definition of customizations.
- You will add a number of companies.

Application Database

The sizing information for this database assumes you have all subsidiary modules, and you must include an allocation of space for entities, such as vendors, customers, and so on, which have no direct impact on General Ledger transactions.


Establishing a maintenance plan

Once your databases are created, you can create a maintenance plan. If you choose to do so, the Database Maintenance Wizard appears. This utility allows you to create a basic maintenance plan for the databases you created. We strongly recommend that you establish a maintenance plan to ensure the consistency of your databases and to provide for the proper backup of your critical financial data.

If, at this time, you elect to not create a maintenance plan, select **Exit** to complete the database creation process.

You can start the Database Maintenance Wizard after the Acuity databases have been created to establish a maintenance and backup plan. To start the Database Maintenance Wizard, select **Run** from the Windows Start menu, then enter

C:\AcuityDB\DBInstall\CreateDB /M. The following window appears.



The following outlines the information in this utility. We recommended that you schedule these activities for times during which there is little or no activity occurring against the Acuity databases.

■ **System and Application Databases**

Specify the Acuity system database that contains system and user information, and the application database that contains the financial information.

■ **Maintenance Options**

Select the Data Validation option to schedule the DBCC CHECKDB and DBCC CHECKCATALOG Database Consistency Checker commands. CHECKDB reports on data and index page consistency, while CHECKCATALOG reports on consistency of the system tables.

The Data Optimization option rebuilds the table indexes using the free space percent value as the inverse of the index fillfactor. This option also updates the index statistics used in the compilation of stored procedures.

■ **Perform Scheduled Backups To**

Select this field to specify the folder in which to create the backup files. The folder that you select should not be on the same drive as your database. The folder specified should be one to which the

server always has access. The file names of the backups are generated at run time as the database name with a current date (YYYYMMDD) extension.

■ **Plan Frequency**

Configure how often, on which days, and at what time the scheduled maintenance is to automatically occur.

■ **Generate Report To**

Enter the path to which the results of the maintenance activities will be created. A valid path is **required** in this field.

■ **E-Mail To**

Select a previously established SQL Server Operator to whom completion messages should be sent. For more information on how to create SQL Server Operators see the *Microsoft SQL Server Online Help* topic, “Creating an Operator.”

When you have completed the desired maintenance plan, select **Apply** to have the Wizard schedule your maintenance plan. The maintenance plan takes effect according to the schedule that you configured. It will only execute if the SQL Executive service is running concurrently with the SQL Server service. Information about the scheduled plan can then be viewed, modified, or run within the Enterprise Manager | Scheduled Tasks function.

Logging in to Acuity

You can now login to Acuity with the user ID “admin” with no password. Both this user ID and the “sotaadmin” user ID have been created within the SQL Server. Do not modify passwords and permissions in SQL Server for these or any other Acuity users before reviewing the *System Manager Guide* (with updates contained in this guide) and the Online Help for more information on creating and maintaining users.

If you installed the demo data, seven demonstration companies exist for your use. These are CAD, COA, CON, DKS, SGE, SLS, and SOA. The Systems of America (SOA) company contains a fairly extensive amount of data in all of the Acuity modules that you can use for testing or viewing. The Consolidation Company (CON) has been created as the sample company in which the Advanced Consolidations module can be utilized.

You have completed the Acuity database creation and can now proceed to the Acuity Client installation procedures discussed in chapter 3.

Chapter 3

Acuity Client

The following chapter guides you through the process of installing, removing, reinstalling, and upgrading the Acuity Client software.

- Installing the Local Client (page 24)
- Installing the Network Client (page 29)
- Installing on a Windows Terminal Server (page 35)
- Removing Acuity (page 39)
- Reinstalling the Acuity Client (page 42)
- Upgrading the Acuity Client (page 44)

Installing the Local Client

The local installation of the Acuity Client allows you to store and execute the Acuity programs on your client machine. This installation method reduces network traffic when starting Acuity.

If you are installing on a Windows NT Workstation client or Windows 95/Windows 98 clients with profiles enabled, review the information in “Appendix A: Installing on Windows NT Clients” on page 102.

If you want to perform the centralized network installation, refer to “Installing the Network Client” on page 29.

Client requirements

Before beginning the software installation, verify that your client machine meets the following criteria:

- Pentium II class or better processor
- Minimum of 64MB of RAM (128MB or more recommended)
- SVGA Monitor and Video Drivers (800x600 resolution)
- 400MB of available disk space for a local client installation
- 50MB of available disk space for a network client installation
- Windows 95, Windows 98, or Windows NT 4.0
- DCOM95 for machines with a Windows 95 operating system
- A default print device

Client checklist

Before you install, reinstall, or upgrade Acuity on your machine, review the following checklist to verify that you have completed all the required preliminary steps. If the answer to any of these questions is No, do not continue. Make the appropriate changes, then continue working through this checklist.

- ☐ **Is your processor an Intel Pentium II or better with a minimum of 64MB of RAM?**

Your machine should have a minimum of 64MB of RAM.

- ☐ **Is your machine's operating system Windows NT 4.0, Windows 95, or Windows 98?**

These are the only operating systems supported.

- ☐ **If your machine's operating system is Windows 95, did you install DCOM95?**

This is required for a successful client installation on Windows 95.

- ☐ **Do you have at least 400MB of available hard disk space on your local drive?**

This is the required hard disk space for local installation of the Acuity client.

- ☐ **Do you have at least 50MB of available hard disk space on your local drive?**

This is the required hard disk space for a network installation of the Acuity client.

- ☐ **Have you shut down all other software applications?**

An installation error may occur if other applications are running while attempting an Acuity installation.

- ☐ **Have you defined a default printer?**

Seagate Crystal Reports, Acuity's reporting engine, requires a default printer to function properly.

You are now ready to install, reinstall, or upgrade the Acuity Client software.


Client installation




WARNING
Before installing, reinstalling, or upgrading the Acuity Client on a Windows NT Workstation or Windows NT Server running SQL Server, shut down all SQL Server services.

- 1 To begin the Acuity Client installation, place the Acuity CD into your CD-ROM drive. The following window appears.

Tip
If you want to install Seagate Crystal Reports for Acuity, you must do so prior to installing the Acuity client.




- 2 Select **Client Install** to begin the installation process. The following window appears.




- 3 Select **Browse** to optionally change the destination directory.
- 4 Select **Next** to continue.


- 5 You are prompted to select the Acuity modules that you want to install. The window also displays the amount of required and available space on your destination drive. If you do not have enough available space, you can change the target directory by selecting **Browse**. You can also view the available disk space on alternate drives by selecting **Disk Space**.




- 6 Select the check box next to each module's name that you want to install.
- 7 When you are done making your selections, select **Next**. Setup creates a Folder for Acuity. You can create the Folder using a different name or you can select an existing Folder. Select **Next** to continue.



- 8 You are prompted to specify the name of the Microsoft SQL Server. See your System Administrator for the name of the Microsoft SQL Server on which the Acuity databases have been created.



- 9 After you specify the default SQL Server, select **Next** to continue. Acuity copies the requested Acuity components to your selected target directory. The following window appears after a successful installation.



- 10 If database names have been modified from the default of `acuity_sys` and `acuity_app`, or if you need to verify connectivity to the server, select
Start | Programs | Acuity Financials | Registry Editor.

Installing the Network Client



TIP

If you move your network installation, you must reinstall your network clients.

You can also install the Acuity version 4.1 Client to a network share point for easy administration. This feature allows you to run the Acuity programs, reports, and Help files from a central location. A simple workstation setup program is provided to install only those components required to run Acuity. This installation method is recommended only for fast network connections.

If you are installing on a Windows NT Workstation Client or Windows 95/Windows 98 with profiles enabled, review the information in “Appendix A: Installing on Windows NT Clients” on page 102.

If you would like to perform the local installation, refer to “Installing the Local Client” on page 24.

File server requirements

Before beginning the software installation, verify that your file server meets the following criteria:

- Pentium II or better processor (dual is preferred)
- Minimum of 64MB of RAM for Windows NT
- 400MB of available disk space
- An available share point or shared volume

Because of performance considerations, we strongly recommend against employing the SQL Server as the file server for Acuity programs.

File server checklist


Before you install or reinstall Acuity on your file server, review the checklist to verify that you have completed all the required preliminary steps. If the answer to any of these questions is No, do not continue. Make the appropriate changes, then continue working through this checklist.

- ☐ **Does your file server meet the specified requirements?**
Refer to “File server requirements” above and on page 6 for the recommended file server requirements.
- ☐ **Do you have at least 400MB of available hard disk space on the network hard drive?**
This is the amount of hard disk space required for installation of the Acuity components.
- ☐ **Have you defined a common share point or shared volume?**
This is required to install and access the Acuity programs in the network installation.


You are now ready to install, reinstall, or upgrade the Acuity Client software.

Copying the Acuity Client

- 1 To begin the copy process, insert the Acuity CD into your CD-ROM drive.
- 2 Select the Windows **Start** button, then select **Run**, and enter **D:\Client\Setup.exe /a**. Change this path to the drive letter associated with your CD-ROM drive.



- 3 Select the destination share point or volume using either a UNC or drive letter. The Acuity installation program automatically creates a folder name "Acuity" in the location specified.



- 4 When selecting a UNC, the installation program cannot determine the amount of available disk space. Verify that the minimum is available and continue.

- 5 Upon successful completion of the program copy process, the following window appears.



You are now ready to begin the client installation.

Client requirements

Before beginning the software installation, verify that your client machine meets the following criteria:

- Pentium II class or better processor
- Minimum of 64MB of RAM (128MB or more recommended)
- SVGA Monitor and Video Drivers (800x600 resolution)
- 50MB of available disk space for a network client installation
- Windows 95, Windows 98, or Windows NT 4.0
- A default print device
- Access is enabled to the share point in which the Acuity programs have been copied

Client checklist

Before you install, reinstall, or upgrade Acuity on your client machine, review the checklist to verify that you have completed all the required preliminary steps. If the answer to any of these questions is No, do not continue. Make the appropriate changes, then continue working through the rest of this checklist.

- ☐ **Is your processor an Intel Pentium II or better with a minimum of 64MB of RAM?**

Your machine should have a minimum of 64MB of RAM.

- ☐ **Is your machine's operating system Windows NT 4.0, Windows 95, or Windows 98?**

These are the only operating systems supported.

- ☐ **Do you have at least 50MB of available hard disk space on your local drive?**

This is the required hard disk space for a network installation of the Acuity client.

- ☐ **Have you shut down all other software applications?**

An installation error may occur if other applications are running while attempting an Acuity installation.

- ☐ **Have you defined a default printer?**

Seagate Crystal Reports, Acuity's reporting engine, requires a default printer to function properly.


You are now ready to install, reinstall, or upgrade the Acuity Client software.

Client installation from a share point




WARNING
Before installing, reinstalling, or upgrading the Acuity Client on a Windows NT Workstation or Windows NT Server running SQL Server, shut down all SQL Server services.

- 1 At the share point or volume in which you copied the Acuity programs, run the **\Acuity\WksClient\Setup.exe** program. The following window appears.




- 2 Select **Browse** to optionally change the destination directory.
- 3 You are prompted to specify the name of the Microsoft SQL Server. See your System Administrator for the name of the Microsoft SQL Server on which the Acuity databases have been created.



- 4 After you specify the SQL Server, select **Next** to continue. You are then prompted to specify the default database. After you specify the default database, select **Next** to continue. Acuity then copies

the Acuity components to your selected target directory. The following window appears after a successful installation.



- 5 If database names have been modified from the default of `acuity_sys` and `acuity_app`, or if connectivity to the server needs to be verified, select **Start | Programs | Acuity Financials | Registry Editor**.

Installing on a Windows Terminal Server



TIP

Review the Windows Terminal Server documentation and requirements for information on installing and configuring your client machines.

Rather than installing Acuity on a server, then on several machines, you can install Acuity on a dedicated Windows Terminal Server and connect to it from other machines. Use either of these methods to install Acuity for multiuser access.

- Use **Add/Remove Programs** in **Control Panel**
- Use the **change user** command at the command prompt before and after installing Acuity

Windows Terminal Server requirements

- Dual Intel Pentium class or higher or DEC Alpha class processor
- Minimum of 128MB of RAM plus an additional 64MB for each typical user

- Minimum of 400MB of available disk space
- SCSI hard drives (caching array recommended)

Windows Terminal Server checklist



TIP

Deselecting Show Startup Logo in the Acuity Registry Editor reduces network traffic when starting Acuity in Windows Terminal Server.

- ☐ **Is your server processor a Dual Intel Pentium class or Digital Alpha class with a minimum of 128MB of RAM?**
Your Windows Terminal Server should have 128MB of RAM.
- ☐ **Does your server have an additional 64MB of RAM for each typical user?**
In addition to the required 128MB of base RAM, your Windows Terminal Server should have an additional 64MB of RAM allocated for each concurrent user.
- ☐ **Do you have at least 400MB of free hard disk space?**
The minimum required space for creation of the Acuity client components is 400MB.
- ☐ **Have you shut down all other software applications?**
An installation error may occur if other applications are running while attempting an Acuity installation.

You are now ready to install Acuity on a Windows Terminal Server using Add / Remove Programs or using Change User.

Installing Acuity using Add/Remove Programs


- 1 Log on at the Windows Terminal Server as the local Administrator.
- 2 Close all other applications.
- 3 Select **Start | Settings | Control Panel | Add/Remove Programs**. The following window appears.



- 4 Select **Install**. The following window appears.



- 5 Insert the Acuity CD and select **Next**. The following window appears.



- 6 In the **Run Installation Program** dialog box, select **Browse** to locate the Acuity database installation, then select **Next**.
- 7 In the **Change User Option** dialog box, select **All users begin with common application settings**, then select **Next**.
- 8 Install Acuity on a local Windows NT file system (NTFS)-formatted drive.
- 9 In the **Finish Admin Install** dialog box, select **Finish**.



WARNING

Use caution when selecting Use Windows NT Authentication. Selecting this option selects it for all other users who connect after this setting is saved.

You are now ready to connect to Acuity. Review the Windows Terminal Server documentation for information on connecting to, disconnecting from, and logging off of a Windows Terminal Server session.

If you establish a new session under the same NT user account, and an old session is still open and running Acuity, attempting to run Acuity on the newly established session will fail.

Installing Acuity using the Change User function

- 1 Log on to the Windows Terminal Server as the local Administrator.
- 2 Close all other applications.
- 3 Select **Start | Programs | Command Prompt**.

- 4 At the DOS command prompt, type **change user/install**. (To see whether execute mode is enabled and .ini file mapping is on, you can type **change user/query**.)
- 5 Install Acuity on a local Windows NT file system (NTFS)-formatted drive.
- 6 When the installation is complete, type **change user/execute** at the command prompt.



WARNING
Use caution when selecting Use Windows NT Authentication. Selecting this option selects it for all other users who connect after this setting is saved.


You are now ready to connect to Acuity. Review the Windows Terminal Server documentation for information on connecting to, disconnecting from, and logging off of a Windows Terminal Server session.

If you establish a new session under the same NT user account, and an old session is still open and running Acuity, attempting to run Acuity on the newly established session will fail.


Removing Acuity

You can remove the Acuity Client components from the client machine by following these steps. If you want to remove or upgrade an Acuity version prior to 3.0, refer to “Upgrading the Acuity Client” on page 44.

- 1 To remove the Acuity Client components, you can select **Uninstall Acuity** from the **Start** menu, or you can remove it using the client removal feature on the CD or the workstation setup. To do this, place the Acuity CD into your CD-ROM drive. The following setup window appears.




- 2 Select **Client Install**. The following window appears.




- 3 Select **Remove Acuity Financials**.
- 4 A message appears prompting you to verify that you want to completely remove Acuity and all of its components. Select **Yes**

to remove the Client files from your system. After a successful uninstall, the following window appears.



- 5 Select **OK**. Acuity then returns you to the beginning of the installation process. Refer to “Installing the Local Client” on page 24 or “Installing the Network Client” on page 29 for instructions on the installation process.




Reinstalling the Acuity Client


This section reviews the procedures required to reinstall the Acuity version 4.1 Client. It replaces the upgrade procedure used with previous versions.

! WARNING
Before installing, reinstalling, or upgrading the Acuity Client on a Windows NT Workstation or Windows NT Server running SQL Server, shut down all SQL Server services.


- 1 To begin the Acuity Client installation, place the Acuity CD into your CD-ROM drive. The following window appears.




- 2 Select **Client Install** to begin the installation process. The following window appears.



- 3 Select **Reinstall Acuity**, then select **Next**.
- 4 Select the modules you want to reinstall, then select **Next**.



- 5 A message appears, prompting you to determine whether you want to remove all of the existing Acuity programs from your system. Select **Yes** to continue the reinstallation process. The following window appears after a successful reinstallation.



Upgrading the Acuity Client

Follow the steps below for each client machine on which Acuity versions prior to 4.0 have been installed. These instructions assume that installation has been completed according to the default parameters. If the defaults have not been followed, then adjust these instructions accordingly.

- 1 To upgrade to Acuity version 4.1, you must disable the Preload utility if it was previously loaded. Do this by removing the Acuity Preload shortcut from your Startup group and restarting your workstation.
- 2 Uninstall Acuity and Seagate Crystal Reports by selecting the Windows **Start** button, then selecting **Settings | Control Panel**. In Control Panel, select **Add/Remove Programs**. From the list of items, select the **Acuity Financials** components or version extension, then select **Add/Remove**. Repeat these steps for Seagate Crystal Reports to remove prior versions of the Seagate Crystal Reports designer. We recommend that you delete the



WARNING


Deleting the Acuity directory also deletes modified reports, Help files, and programs.

**TIP**

The Acuity version 2.50 CD is required to remove Seagate Crystal Reports.

remaining Acuity and CRW folders as well. If the Recycle Bin is enabled on your system, empty the bin before proceeding with your new installation. Even though the programs may no longer appear in your directory, they reside in the Recycle Bin.

- To clean your System Registry of all Acuity components, select the **regclean.exe** program in the /Support/Regclean folder located on the Acuity CD. The Microsoft RegClean window displays, notifying you that the utility is checking your registry for errors. If the system finds errors, select **Fix Errors** to continue the process.



- When RegClean is complete, select **Exit**.
- 3 At this time, you can begin the client installation found in “Installing the Local Client” on page 24, “Installing the Network Client” on page 29, or “Installing on a Windows Terminal Server” on page 35.

Chapter 4

UPGRADING THE **Acuity Databases**

This chapter discusses upgrading your existing databases to Acuity version 4.1. With this version you can generate upgrade scripts by comparing your existing database to another database. Refer to “Database creation” on page 14 for instructions on how to create new databases.

- Microsoft SQL Server requirements (page 48)
- Microsoft SQL Server checklist (page 48)
- Before starting the database upgrade (page 49)
- Database upgrade utility installation (page 49)
- Running the database upgrade utility (page 50)
- Comparing databases (page 50)
- Upgrading databases (page 52)
- Acuity database upgrade from SQL Server 6.5 to SQL Server 7.0 (page 55)

Microsoft SQL Server requirements

Before beginning the installation or upgrade process, verify that your server meets the following requirements:

- The tempdb size must be 1/3 of the application database or 100MB, whichever is larger. We recommend creation under a device other than the default master device.
- The Microsoft SQL Server must be started and running before you execute the Acuity Database Upgrade Utility.
- 80 MB of data space available in the existing Acuity Application database.
- 20 MB of data space available in the existing Acuity System database.

Microsoft SQL Server checklist

Before you upgrade Acuity on your server, use the checklist to verify that you have completed all the required preliminary steps. If the answer to any of these questions is No, do not continue. Make the appropriate corrections, then continue working through the checklist.

- ☐ **Is your tempdb for Microsoft SQL Server configured for at least 1/3 of the application database or 100MB?**
To upgrade the Acuity databases, your tempdb database must be 1/3 the size of the application database or 100MB, whichever is larger.
- ☐ **Have you performed Data Base Consistency Checks?**
Perform a DBCC CheckDB and DBCC NewAlloc against the databases you plan to upgrade, and review the error log or results for possible page allocation problems.
- ☐ **Have you backed up your master and other existing databases?**
In the case of a Microsoft SQL Server failure, you may need to restore the databases from backup. Your backups should be archived in case of an upgrade failure realized in the future.

- ❑ Your server must have 80MB of data space available in the existing Acuity Application database.
- ❑ Your server must have 20MB of data space available in the existing Acuity System database.

Before starting the database upgrade

Due to the critical nature of your business's financial information you must post any unposted batches and create a backup of the existing Acuity databases prior to attempting the database upgrade. In each module, review Post XX Batches, where XX is the module name. Review General Ledger as the final module to ensure that no batches remain open or unposted. Then, run the Database Consistency Checker, or, if you have configured the Acuity Database Maintenance Wizard, run the equivalent SQLMaint functions, and review the error log.

Database upgrade utility installation



WARNING

Upgrade forward only. Reinstalling a previous version may involve reformatting your hard drive, reinstalling your operating system, and reinstalling Acuity.

Upgrade the server first when upgrading both the client and the server. Otherwise, you may have to reinstall the client with the previous version if the server upgrade is unsuccessful.

To begin the database upgrade process, install the Database Utilities. If you are using a DEC Alpha server, you must perform the database upgrade from a Windows 95, Windows 98, or Windows NT client that can connect to the SQL Server. When you are upgrading the database, there should be no other activity on the Windows NT Server or the Microsoft SQL Server.

You must log into the Windows NT Server as the Administrator. Begin the Database Utilities installation by inserting the Acuity CD into the CD-ROM drive and selecting **Server Install**. Refer to "Database creation" on page 14 for information on installing the Acuity Database Utilities.

The installation program creates the AcuityDB folder and copies the software from the CD to the destination folder.

Running the database upgrade utility



Tip

The database upgrade can take from one to twelve hours, depending on the amount of data and speed of the server.

- 1 To begin the Database Upgrade Utility, select the Windows **Start** button. Then select **Programs | Acuity Financials | Acuity Database Upgrade Utility**.
- 2 Specify the correct database server and the password for the system administrator (SA) login on that server. You cannot proceed until you have provided valid login information.
- 3 Once you have successfully logged in to the server, start the upgrade process by selecting menu options outlined in the sections below.

Comparing databases

Once you have started the Database Upgrade Utility you can compare databases by selecting **Tools | Compare Databases**.

Database Upgrade Utility

☒ Compare with pre-processed Acuity Database information

System Database 1: Application Database 1:

System Database 2: Application Database 2:

Compare with Version:

☐ Generate Database Upgrade Script

This optional utility can create a custom upgrade script to upgrade your modified version of the Acuity databases. You can also use this utility to review the database schema changes present between two database sets or review changes from one version to another.

You establish the options for database comparison and perform these comparisons using one of the following methods:

- The first method is to compare your database against the precompiled information that ships with the Database Upgrade Utility. This is the fastest way to compare your current database with the shipped version. This is the default method of the upgrade utility.
- The second method is to compare two databases. This option is most useful when you are interested in modifications that have been made between two previously created database sets. To compare two databases, deselect **Compare with pre-processed Acuity Database information**. This allows you to select a second Acuity database.
- The final option is to have the comparison generate a database upgrade script by selecting **Generate Database Upgrade Script**. Once the comparison is complete, an upgrade script is created and can be run at a later time to upgrade the databases specified in the System and Application Database fields. The files created reside in the **AcuityDB\DBUpgrade\<version number>** folder and are named **usc_appl.sql** for the application database and **usc_sys.sql** for the system database.




WARNING

Any customized stored procedures or triggers must be recompiled after the database upgrade process.

Once you select the options you desire, select **Proceed** to begin the comparison process.

During the compare process, a window displays the comparison progress of each table. When the compare process is complete, the main window populates with the results of the comparison. The left pane displays the database and table where differences occurred, and the right pane displays the specific column attributes that have changed. To output a report of the database differences, select **Reports | Schema Changes**.




Upgrading databases


TIP
You must post all batches in all Acuity modules and companies to proceed with the database upgrade.

In addition to comparing databases and applying a generated script, you can perform a direct, one-step database upgrade by selecting **Tools | Upgrade Existing Databases**.

- 1 Use the following window to select the databases to upgrade.



- 2 Select the target databases to upgrade in the System and Application Database fields. If no schema changes have been made to this database, select **Use pre-generated Acuity Database Upgrade script**. This option performs the standard database upgrade. If you have made any schema modifications, they will be lost along with any data they contain. If you are unsure whether this database contains any modifications, run the Compare Database option or deselect **Use pre-generated Acuity Database Upgrade script**.



⚠ WARNING
The Main and Sub-Segment combination cannot exceed 15 characters.

- 3 Changes to the General Ledger Chart of Accounts structure were made in version 3.0. You must select how you want these changes to affect your General Ledger accounts.

The following window appears, allowing you to make these changes. You can combine your Main account segment with any defined Sub-Segments. If you do not combine these segments, the upgrade process changes all Sub-Segment types to Validated segments. In this case, the Database Upgrade Utility adds all current Sub-Segment values as Validated values in General Ledger. Make any necessary changes, and select **OK** to continue.

The general ledger account structure has been enhanced in Acuity Financials version 3.0. A general ledger account is now comprised of a Natural account segment and optional Validated account segments. The Natural account segment replaces the Main segment in earlier versions.

You can choose to combine the Main and Sub segments in your current account structure into the Natural account segment or you can choose to transfer only the Main segment into the Natural account segment.


The current account structure for each of your companies is shown below. Please indicate the desired upgrade option for each company.

(M) - Main; (S) - Sub.


	Company	Current GL Account Structure	Combine Main and Sub(s)
1	COA	(M) Main - Division - Department - Region	☒
2	SJC	(M) Main Segment	☒
3	SOA	(M) Main - Division - Department - Region	☒

OK Cancel

- 4 Upon completion of the database upgrade, the Database Upgrade Utility displays a log of the operations that occurred. If you want to save a report of the operations, select **Reports | Schema Changes**. The report is saved to the AcuityDB\DBUpgrade\StrtChng.txt file. To view the report, select **Yes** at the following prompt.



- 5 Once you create your databases, you can choose to create a maintenance plan. The Database Maintenance Wizard appears after the database upgrade window closes. Review “Establishing a maintenance plan” on page 18 for more information.



- 6 Review the DBError.log file generated by the upgrade process. This is saved in the AcuityDB\DBUpgrade folder. It contains information about the upgrade and any errors encountered in the process.

Acuity database upgrade from SQL Server 6.5 to SQL Server 7.0



TIP

The Acuity database upgrade from SQL Server 6.5 to SQL Server 7.0 is only supported in Acuity version 4.1 or higher.

In addition to upgrading Acuity databases from previous versions of Acuity, you can also upgrade Acuity databases from SQL Server 6.5 to SQL Server 7.0.

- 1 You must upgrade the databases from your previous version of Acuity to version 4.1 in SQL Server 6.5. Refer to “Upgrading databases” on page 52.
- 2 To upgrade your databases from Microsoft SQL Server 6.5, follow the instructions found in *SQL Server Books Online* for SQL Server 7.0 in the section, “Upgrading from an Earlier Version of SQL Server.” Of the two methods detailed (Direct Pipeline and Tape Drive), we recommend upgrading using the Direct Pipeline method. Follow the instructions found in *SQL Server Books Online* in the section, “How to perform a version upgrade using a direct pipeline (SQL Server Upgrade Wizard).” Be sure to include both the Acuity system and Acuity application databases when using the SQL Server Upgrade Wizard.
- 3 After successfully upgrading the Acuity databases from Microsoft SQL Server 6.5 to SQL Server 7.0, install the Acuity SQL Server 7.0 patch, located on the Acuity 4.1 CD in the \Patches\SQL Server 7.0 folder. Once installed, apply the patch to the Acuity databases. Failure to apply this patch will result in an error when you try to log in to the Acuity databases using the Acuity client.

Chapter 5

Utilities and Updates

This chapter discusses the following utilities and updates that accompany your Acuity version 4.1 CD:

- Third party utilities and program updates (page 58)

Third party utilities and program updates

A number of third party utilities and program updates have been included for your convenience with your Acuity software. These utilities and updates are located on the Acuity CD. Refer to the software manufacturer if you encounter any problems applying these updates.

Internet Explorer version 5.0

Internet Explorer version 5.0 is the required client for use in accessing the Web Reports module included with Acuity. This component has been included for your convenience. You can also download the Internet Explorer 5.0 software from Microsoft's web site at <http://www.microsoft.com>.

Microsoft Windows NT 4.0 Service Pack 5

Windows NT 4.0 Service Pack 5 is the minimum NT service pack required for operation of the Acuity software. This update has been included for your convenience and should be applied to both NT clients and servers. You can also download Windows NT Service Pack 4 from Microsoft's web site at <ftp://ftp.microsoft.com/softlib/mslfiles>.

Microsoft SQL Server 6.5 Service Pack 5a

Microsoft SQL Server 6.5 Service Pack 5a must be applied to SQL Server 6.5. The Acuity Database Creation Utility requires this update to properly create your databases. This update has been included for your convenience and can also be downloaded from Microsoft's web site at <ftp://ftp.microsoft.com/softlib/mslfiles>.

Microsoft SQL Server 7.0 Service Pack 1

Microsoft SQL Server 7.0 Service Pack 1 must be applied to SQL Server 7.0. The Acuity Database Creation Utility requires this update to properly create your databases. This update has been included for

your convenience and can also be downloaded from Microsoft's web site at <ftp://ftp.microsoft.com/softlib/mslfiles>.

Microsoft Data Access Components 2.1

Microsoft Data Access Components 2.1 is automatically installed during the Acuity Client installation. You can also install MDAC 2.1 directly from the Acuity CD. The MDAC installation contains the core components (ADO, OLE DB, and ODBC) and additional OLE DB providers and ODBC drivers for various data stores. Use these components to integrate information from a variety of both relational (SQL) and non relational sources.

Distributed Component Object Model 95



TIP
Windows NT Service Pack 4 includes the DCOM update for Windows NT machines.

DCOM 95 (Distributed Component Object Model) is the COM update for Windows 95 and is required if you install the Microsoft scripting components. The Acuity client installation automatically installs the portions of the DCOM 95 update required by Acuity. This update has been included for your convenience and can also be downloaded from Microsoft's web site at <ftp://ftp.microsoft.com/softlib/mslfiles>.

Scripting

The scripting components support the Acuity Customizer module. The Acuity client installation automatically installs the portions of the scripting components required for Customizer. These components have been included for your convenience and can also be downloaded from Microsoft's web site at <ftp://ftp.microsoft.com/softlib/mslfiles>.

RegClean

Use the RegClean utility to properly remove program references when uninstalling Acuity client versions prior to 4.0. This utility has been included for your convenience and can also be downloaded from Microsoft's web site <ftp://ftp.microsoft.com/softlib/mslfiles>.

Chapter 6

MODULE Enhancements

Refer to the following sections for information on enhancements made to the Acuity modules for version 4.1.

- Global enhancements (page 62)
- System Manager (page 66)
- General Ledger (page 69)
- Accounts Payable (page 80)
- Accounts Receivable (page 94)
- Multicurrency Management (page 84)
- Cash Management (page 85)
- Purchase Order (page 86)
- Inventory Management (page 86)
- Sales Order (page 99)

Global enhancements


To create a more user-friendly working environment, several enhancements have been made that effect Acuity across all Acuity modules.

Version 4.1 user manuals

The Acuity user manuals are included as Adobe Acrobat (.pdf) files on the Acuity User Guides CD. Use these manuals with the Online Help to quickly master Acuity.

These manuals require Acrobat Reader for viewing. You can install Acrobat Reader version 4.0 from the Acuity third party CD or from Adobe's website at <http://www.adobe.com>

Place the Acuity CD into your CD-ROM drive. From the list of manuals that appears, select the manual you would like to view.



Registry Editor




WARNING

Use caution when selecting Use Windows NT Authentication in a Windows Terminal Server or MetaFrame session. Selecting this option selects it for all other users who connect after this setting is saved.

The Registry Editor window has been enhanced to include a Use Windows NT Authentication checkbox. If you are running Acuity on SQL Server 7.0, you can use this option to connect directly to Acuity using Windows NT Authentication, rather than through the standard SQL Server security. This eliminates the need for a separate SQL Server user name and password.

You can also select Show Startup Logo to view the Acuity logo while logging in to Acuity.



User login

The user login window has been enhanced to include a Use Windows NT Authentication checkbox. If you are running Acuity on SQL Server 7.0, you can use this option to connect directly to Acuity using the domain or NT logins you have configured within SQL Server 7.0. This eliminates the need to enter user and password information to access Acuity. If you want to disable this option after it has been set, you can change the setting in the Acuity Registry Editor.



WARNING

Use caution when selecting Use Windows NT Authentication in a Windows Terminal Server or MetaFrame session. Selecting this option selects it for all other users who connect after this setting is saved.


You can also change the server and database directly from the login window and save the new connection as the default. This eliminates the need to run the Acuity Registry Editor to change the connection information.

Calendar control

The calendar control on date fields in Acuity has been enhanced to resemble a drop-down box. Select the drop-down arrow on the date field and use one of the following methods to change the date:

- To scroll through the months, use the right or left arrow.
- To change the month without scrolling, left click on the month, and select the desired month from the menu that displays.
- To scroll through the years, left click on the year. Select either the up or down arrow to scroll through the years.

Once you reach the desired month and year, select the day to update the date field. If your business date and system date differ, select the date at the bottom of the calendar to change to the computer's system date.



System Manager

This section discusses enhancements that have been made to Acuity System Manager in version 4.1.

System management

Managing your system includes knowing who can use Acuity and how to protect your financial data. With integration into the SQL Server 7.0 environment, system administrators can now manage Acuity user much more effectively through the user of the Application Roles function.

Acuity provides a SQL Server 7.0 Application Role called Acuity AppRole. When used, this Application Role assumes responsibility for granting permissions to objects in the database for the user.

This functionality has been integrated into Maintain Users and Maintain Site. Review “Maintain users” on page 66 and “Maintain site” on page 68 for more detailed information.

Maintain users



TIP

If you select **Use Acuity AppRole**, you can select **Allow Read Access** to permit the user to have read-only access to the Acuity database.

If you are running Acuity on Microsoft SQL Server 7.0, properly configure the SQL Server logins before using Maintain Users. Acuity allows the addition of users or groups only after they have been granted login rights to SQL Server. Once added, they are available for selection from the User ID Navigator to allow users access into the Acuity databases. For more information on creating SQL Server users, review *SQL Server Books Online* under the section, “Using the Create Login Wizard.”

If you are accessing the Acuity databases on a SQL Server 7.0 server, you can select Use Acuity AppRole and Allow Read Access after selecting to enable AppRoles in Maintain Site.

Selecting Use Acuity AppRole for the user allows the administrator to revoke object permissions on all Acuity database objects for that user and allow the application role to manage these permissions instead.

The Acuity Application Role allows a user to perform normal processing against the data while in Acuity; however, this user has no rights to access the data from any other application outside of Acuity.

After selecting **Use Acuity AppRole**, you can grant the user permissions to only view the data by selecting **Allow Read Access**. When selected, the user can select data from the Acuity database but cannot modify any of this data.

Maintain Users

User: admin
Name: admin
Default Security Group: public
Use Acuity AppRole: ☒
Allow Read Access: ☒
Company: SOA
Group: Super2
Systems of America
Super2
OK
Undo

	Company	Group	Description
1			

admin SOA 5/8/98

Maintain site



Tip

You must view the License Agreement before accepting the agreement and entering the number of licenses.

The Register Modules task in previous versions of Acuity has been enhanced to become Maintain Site. With Maintain Site, not only can you register modules and enter demographic and address information, you can also identify the number of Acuity licenses your company requires. If you are accessing the Acuity databases on a SQL Server 7.0 server, you can select **Use AppRole** on the new Security tab page and set a password for this AppRole.

Application roles allow the ability in SQL Server 7.0 to supersede a user's database permissions. Acuity creates an application role named Acuity AppRole that allows Acuity users to perform normal processing against the data while in Acuity; however, this user has no rights or has read-only rights when accessing the data from any application other than Acuity.

The 'Maintain Site' dialog box is shown with the 'Security' tab selected. The 'Registered Name' field contains 'ABC Company'. The 'AppRole' section is active, showing a checked 'Use AppRole' checkbox. Below it, the 'AppRole' field contains 'AcuityAppRole', and the 'Role Password' and 'Role Password Confirm' fields are empty. The status bar at the bottom shows 'admin SOA 5/8/98'.

The 'Maintain Site' dialog box is shown with the 'License' tab selected. The 'Registered Name' field contains 'ABC Company'. The 'Licensing' section contains the text: 'You must purchase the required licenses prior to using Sage Acuity Application from any other computer. For complete terms and conditions governing the use of this product, please see the license agreements.' Below this, there is a checked checkbox for 'I agree that:' and a statement: 'I have read and agree to be bound by the license agreements for this product.' The 'Number of Licenses' field is set to '10'. The 'OK' and 'Cancel' buttons are at the bottom right. The status bar at the bottom shows 'admin SOA 5/8/98'.

Business Date

You can change the business date for a company in Change Business Date. You might want to do this, for example, if you need to enter data in a future date. For instance, in the month of March, you could change the business date to a date in April, enter the data, and then change the business date back to a date in March.

If you selected to use the same business date for all modules in User Preferences, only one business date appears. Otherwise, a list of modules and their respective business dates appears.

Reports

The following report has been removed from System Manager in version 4.1.

Installed Modules Report

The Installed Modules Report no longer exists in Acuity.

General Ledger

This section discusses enhancements that have been made to Acuity General Ledger in version 4.1.

GL Utilities

The General Ledger Import utility allows you to transfer information from an existing general ledger system to the Acuity General Ledger module. The following section explains the tasks that have been added or modified for importing general ledger data.

Current Period Budget record

The Current Period Budget record updates the *tglBudget* table.

Each General Ledger account must be represented by one record and each import file must be represented by one budget period (target period).

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
1	Acct_No	Account Number	Varchar(100)	1	100	✓	Must exist in <i>tglAccount</i> .
2	Acct_Desc	Account Description	Varchar(40)	101	40		
3	Fisc_Year	Fiscal Year	Char(5)	141	5		
4	Fisc_Per	Fiscal Period	SmallInt	146	5		
5	Bdgt_Type	Budget Type	Char(15)	151	15		
6	Home_Curr	Home Currency ID	Char(3)	166	3		
7	Cur_Bdgt_F	Financial Budget	Int	169	16	✓	
8	Cur_Bdgt_S	Statistical Budget	Int	185	18		For future use.
9	YTD_Bdgt_F	Financial YTD Budget	Int	203	16		
10	YTD_Bdgt_S	Statistical YTD Budget	Int	219	18		For future use.
11	Comp_ID	Company ID	Char(3)	237	3		Case sensitive.

All Period Budgets - Financial record

The All Period Budgets - Financial record updates the *tglBudget* table.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
1	Acct_No	Account Number	Varchar(100)	1	100	✓	Must exist in <i>tglAccount</i> .
2	Acct_Desc	Account Description	Varchar(40)	101	40		
3	Fisc_Year	Fiscal Year	Char(5)	141	5		
4	Bdgt_Type	Budget Type	Char(15)	146	15		
5	Home_Curr	Home Currency ID	Char(3)	161	3		
6	Pn_Bdgt_F	Period n Financial Budget (1-n)	Int	164	16	✓	You can have one field for each period and you must have the same number of fields as periods in a fiscal year. For example, if fiscal year 1999 is defined in Set Up Fiscal Periods as having 12 periods, then the import files must contain 12 fields even though data may not be present in each field.
7	YTD_Bdgt_F	Financial YTD Budget	Int	180	16		Immediately following the fields for the individual periods, one field must contain the net sum of the preceding period fields.
8	Comp_ID	Company ID	Char(3)	196	3		Case sensitive.

Transactions record

The Transactions record updates the *tcBatchLog*, *tglBatch*, *tglOptions*, *tglNaturalAcct*, *tglAcctRefUsage*, *tglJournalLog*, *tglJournalHdr*, and *tglJournalDetl* tables.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
1	Acct_No	Account Number	Varchar(100)	1	100	✓	Must exist in <i>tglAccount</i> .
2	Acct_Desc	Account Description	Varchar(40)	101	40		
3	Fisc_Year	Fiscal Year	Char(5)	141	5		
4	Fisc_Per	Fiscal Period	SmallInt	146	5		
5	Post_Date	Posting Date	DateTime	151	8		yyyymmdd
6	Src_Jrnl	Source Journal ID	Char(2)	159	2		
7	Jrnl_No	Source Journal Number	Int	161	10		Acuity automatically enters a number if blank. However, you can enter a number that does not already exist in Acuity or the current import file.
8	Seq_No	Sequence Number	Int	171	9		Acuity automatically enters the sequence number in the order the records exist in the import file. You can manually enter sequence numbers, starting with 1 and increment accordingly.
9	App_Code	Application Code	Char(3)	180	3		
10	Post_Cmnt	Posting Comment	Varchar(40)	183	40		
11	Home_Curr	Home Currency ID	Char(3)	223	3	✓	Home Currency is only required if you have Multicurrency Management.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
12	Post_Amt_H	Posting Amount - Home Currency	Dec(15,3)	226	16	✓	Posting Amount Home Currency is only required if you have Multicurrency Management. If you enter a posting amount currency, the decimal is required and takes one of the 16 allocated spaces. You can have a maximum of three digits past the decimal. For example, the largest decimal number for a fixed length or delimited file is 999999999999.999. Do not use a comma for separating by thousands.
13	Exch_Rate	Currency Exchange Rate	Dec(15,3)	242	16	✓	The Currency Exchange Rate is only required if you have Multicurrency Management. If you enter a posting amount currency, the decimal is required and takes one of the 16 allocated spaces. You can have a maximum of three digits past the decimal. For example, the largest decimal number for a fixed length or delimited file is 999999999999.999. Do not use a comma for separating by thousands.
14	Nat_Curr	Currency ID	Char(3)	258	3	✓	Must be a valid currency.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
15	Post_Amt_N	Posting Amount - Natural Currency	Dec(15,3)	261	16	✓	If you enter a posting amount currency, the decimal is required and takes one of the 16 allocated spaces. You can have a maximum of three digits past the decimal. For example, the largest decimal number for a fixed length or delimited file is 99999999999.999. Do not use a comma for separating by thousands.
16	Post_Qty	Statistical Posting Quantity	Dec(15,3)	277	16		If you enter a posting quantity, the decimal is required and takes one of the 16 allocated spaces. You can have a maximum of three digits past the decimal. For example, the largest decimal number for a fixed length or delimited file is 99999999999.999. Do not use a comma for separating by thousands.
17	Ref_Code	Account Reference Code	Char(20)	293	20		Must exist in <i>tglAcctRef</i> .
18	Acct_Sign	Account Orientation	Char(1)	313	1		C = Credit D = Debit
19	Comp_ID	Company ID	Char(3)	314	3	✓	The company ID is case sensitive.

Batch Header Record

This record signals the import program to start a new batch.



TIP

You can only have one batch header/footer record per import file.

The batch header record must be in the first line in the import file and the batch footer record must be the last line of the import file. The journal headers and footers are used to nest journal records together. The records for a particular journal must be listed between its journal headers and footers.

The batch header record is required. The format is batch header record, journal header record, transaction records, journal footer record, and batch footer record.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
1	HDR_ID	Header Indicator	Char(4)	1	4	✓	Signals start of a new batch. =@HDR
2	HDR_Type	Header type	Char(5)	5	5	✓	=BATCH
3	HDR_Date	Header Date (business date)	DateTime	10	8	✓	Used as batch posting date.
4	HDR_Cmnt	Header Comment	Char(40)	18	40	✓	Used as batch comment.

Batch Footer Record

This record signals the import program to end the current batch. A batch footer record is received prior to starting another batch.



Tip

You can only have one batch header/footer record per import file.

The batch header record must be in the first line in the import file and the batch footer record must be the last line of the import file. The journal headers and footers are used to nest journal records together. The records for a particular journal must be listed between its journal headers and footers.

The batch footer record is required. The format is batch header record, journal header record, transaction records, journal footer record, and batch footer record

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
1	FTR_ID	Footer Indicator	Char(4)	1	4	✓	Signals the end of the batch record. =@END
2	FTR_Type	Footer Type	Char(5)	5	5	✓	=BATCH

Journal Header Record

Once a batch header record is received, this record signals the import program to start a new journal. You may have multiple unnested journals per import file.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
1	HDR_ID	Header Indicator	Char(4)	1	4	✓	Signals the start of a new journal. =@HDR
2	HDR_Type	Header type	Char(7)	5	7	✓	=Journal
3	HDR_Code	Header Journal Code	Char(2)	12	2	✓	Must be a valid journal code in Set Up Journals and is required. However, if all of the transactions are using the same journal code, this field can be blank and the journal code can be specified in the target area in GL Import.
4	HDR_Fin	Header Financial Flag	Char(1)	14	1	✓	0 = No 1 = Yes Although this is a required field, it can be blank if all of the transactions are the same. The financial flag can be set in the target area in GL Import.

Journal Footer Record

This record signals the import program to end the current journal. A journal footer record is received prior to starting another journal.


No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
1	FTR_ID	Footer Indicator	Char(4)	1	4	✓	Signals end of journal record. =@END
2	FTR_Type	Footer Type	Char(5)	5	7	✓	=Journal

Reports

The following reports have been enhanced in version 4.1.

GL Transactions Report

The Extended Comments option has been added to the Options tab page. You can select this option to include additional posting comments on the report when printing the Detail format.



You can select Extended Comments to view additional posting comments when printing in Detail format.

GL Activity Report

The Recap format and the Extended Comments option have been added to the Options tab page.

Select the Recap format to print the account number, account description, debit amount, credit amount, and net change amount for the selected period(s) on the report.


When printing in detail, you can select Extended Comments to print additional posting comments on the report.

The screenshot shows the 'GL Activity Report' window with the 'Options' tab selected. The 'Format' section has three radio buttons: 'Recap' (selected and circled), 'Summary', and 'Detail'. The 'Report Type' section has a 'Multicurrency' checkbox. The 'Include' section has two checkboxes: 'Posting Comments' (checked) and 'Extended Comments' (checked and circled). The 'Message' section is a text area with several empty lines. The status bar at the bottom shows 'admin SOA 5/8/98'.

Select Recap to print a single line per account without accounting period subtotals.

GL Journal Report

The Posting Comments and Extended Comments options have been added to the Options tab page. You can include posting comments and /or extended posting comments on the report.



Select Extended Comments to print additional posting comments on the report.

Accounts Payable

This section discusses enhancements that have been made to Acuity Accounts Payable in version 4.1.

Maintenance

The following enhancements have been made to the Accounts Payable Maintenance tasks.

Maintain vendors



TIP

You must select Automatic Vendor Numbering in Setup AP Options to enable Next Number.

If you have Project Accounting installed, Next Number assigns a vendor number that is unique across all companies.

AP Utilities

The Accounts Payable Import utility allows you to transfer information from an existing accounts payable system to the Acuity Accounts Payable module. The following section explains the tasks that have been modified for importing accounts payable data.

Vendor address record layout

The the City, CountryID, and StateID fields are now required fields if you enter a value for PostalCode. The fields for Fax, FaxExt, Phone, and PhoneExt have been removed. You can enter this information in the Vendor Contact record.

The vendor address record is allowed in a vendor import file and a vendor address import file. It is a *required* record in the vendor import file, and the file may contain 'N' vendor address records for every vendor record. A valid vendor address record inserts into *tapVendAddr* and updates *tcAddress*.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
1	RecordTypeID	<i>System maintained</i>	Char('R')	1	1	✓	
2	CurrID	<i>System maintained</i>	Char(3)	2	3	✓	Set value to home currency if you do not have Multicurrency Management. <i>tmcCurrency.IsUsed = 1</i> <i>tapOptions.UseMultiCurr = 1</i> (<> Home CurrID).
3	FOBID	<i>System maintained</i>	Char(15)	5	15		Used to look up <i>tcIFOB.FOBKey</i> for the current company.
4	LanguageID	<i>System maintained</i>	LongInt	20	4	✓	Validate with <i>tcLanguage.LanguageID</i> .
5	AddrLine1	Street Addr	VarChar(40)	24	40		
6	AddrLine2	Street Addr	VarChar(40)	64	40		
7	AddrLine3	Street Addr	VarChar(40)	104	40		
8	AddrLine4	Street Addr	VarChar(40)	144	40		
9	AddrLine5	Street Addr	VarChar(40)	184	40		
10	AddrName	Street Addr	VarChar(40)	224	40	✓	Must match VendName on first record when included in Vendor import.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
11	City	City	Char(20)	264	20	✓ *	
12	CountryID	<i>System maintained</i>	Char(3)	284	3	✓ *	Validate with <i>tsmCountry</i> .
13	PostalCode	Postal Code	Char(9)	287	9		If CountryID is null, validate as per the <i>tsmCountry.PostalCode Mask</i> for the country (<i>tsmCompany.CountryID</i>) of the current company. If CountryID is not null, validate as per the <i>tsmCountry.PostalCode Mask</i> for the CountryID. The spaces between characters in PostalCodeMask, if present, should be ignored.
14	StateID	<i>System maintained</i>	Char(3)	296	3	✓ *	Validate with <i>tsmState</i> .
15	ShipMethID	<i>System maintained</i>	Char(15)	299	15		Used to look up <i>tsiShipMethod.ShipMethKey</i> for the current company.
16	VendAddrID	<i>System maintained</i>	Char(15)	314	15	✓	Used to look up <i>tapVendAddr.AddrKey</i> . Used to create new address. Set to VendID for first Addr record in a vendor import.
17	VendID	<i>System maintained</i>	Char(12)	329	12	✓	Used to look up <i>tapVendor.VendKey</i> for the current company.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
18	CurrExchSchdID	<i>System maintained</i>	Char(15)	341	15		Used to look up <i>tmcCurrExchSchd.CurrExchSchdKey</i> . Global CurrExchSchdID is searched first. If not found, company specific is searched.
19	STaxSchdID	<i>System maintained</i>	Char(15)	356	15		Used to look up <i>tciSTaxSchedule.STaxSchdKey</i> . Required if <i>tapOptions.TrackSTaxOnPurch = 1</i> .

* These fields are required if a valid Postal Code is provided.

Multicurrency Management

This section discusses enhancements that have been made to Acuity Multicurrency Management in version 4.1.

Reports

The following enhancements have been made to the Multicurrency Management Report tasks.

Revaluation registers

The Post Date has been added to the heading of the AP, AR, and GL Revaluation Registers.

Multicurrency AP Revaluation Register						
Batch: MCPR-0000020		Journal No: MC-73		Post Date: 4/30/98		Hold Reason:
Vendor	Voucher	Voucher Date	Due Date	Voucher Balance	Voucher Balance USD	

Cash Management

This section discusses enhancements that have been made to Acuity Cash Management in version 4.1.

Reports

The following enhancements have been made to the Cash Management Report tasks.

Cash flow projection reports

The SO and PO options have been rearranged in Daily Cash Flow Projection and Periodic Cash Flow Projection.

The screenshot shows the 'Periodic Cash Flow Projection' dialog box. It has a title bar with standard window controls. Below the title bar is a toolbar with icons for file operations and help. The main area is divided into several sections: 'Setting' (a dropdown menu currently set to 'None'), 'Print Report Settings' (a checkbox), 'Main' and 'Options' tabs (the 'Options' tab is selected), 'Format' (radio buttons for 'Summary', 'Detail', and 'Consolidated View'), 'Include' (checkbox for 'Future Cash Flows' and a 'Projection Categories...' button), 'AR Options' (a 'Calculate By' dropdown set to 'Due Date' and checkboxes for 'Assume Discounts Taken', 'Include Unapplied Transactions', and 'Include Pending Transactions'), 'AP Options' (a 'Calculate By' dropdown set to 'Due Date' and checkboxes for 'Assume Discounts Taken', 'Include Unapplied Transactions', and 'Include Pending Transactions'), 'SO Options' (checkbox for 'Include Open Sales Orders' and a 'Calculate By' dropdown), and 'PO Options' (checkbox for 'Include Open Purchase Orders' and a 'Calculate By' dropdown). The 'SO Options' and 'PO Options' sections are circled in red. At the bottom is a 'Message' area with a text box and a status bar showing 'admin CAD 5/8/98'.

Import Reconciliation Edit List

The Batch ID has been added to the Import Reconciliation Edit List.

Cash Management	
Import Reconciliation Edit List	
Summary	
BatchID: CMRE-0000026	Account Number 8112-4653-383-01
Import Totals	
Records Read	16

Purchase Order

This section discusses enhancements that have been made to Acuity Purchase Order in version 4.1.

Maintain blanket purchase orders


You cannot generate purchase orders from blanket purchase orders that are on hold.

Inventory Management

This section discusses enhancements that have been made to Acuity Inventory Management in version 4.1.

Inventory calendar

A Copy From button has been added that displays the Copy From window that you can use to add a new calendar year.



A new window was added to make it easy to define a new inventory calendar by either copying an existing calendar or using an Acuity defined scheme of monthly, 13 four week periods, or weekly.

Set up purchase product lines

The miscellaneous default fields - Allow Vendor Back Orders and Addl Cost Alloc Basis - have been removed from the task and the remaining fields were rearranged.

NEW LAYOUT

The 'Set Up Purchase Product Lines' dialog box features a title bar with standard window controls. Below the title bar is a toolbar with icons for save, delete, undo, redo, and help. The main area is divided into several sections: 'Purchase Product Line' and 'Description' both set to 'Components'; 'Replenishment Defaults' with fields for Buyer (Surfington), Season Start (Jan), and Season End (Feb); 'Item Defaults' with fields for Item Type (Finished Good) and Match Tolerance (ten); 'Inventory Defaults' with fields for Demand Formula (Demand A), Safety Stock Formula (Safety B), and Lead Time Formula (Lead C); and a 'Department' field set to 20. At the bottom, there are navigation buttons and a status bar showing 'admin SQA 5/8/98'.

OLD LAYOUT

The 'Set Up Purchase Product Lines' dialog box features a title bar with standard window controls. Below the title bar is a toolbar with icons for save, delete, undo, redo, and help. The main area is divided into several sections: 'Purchase Product Line' and 'Description' both set to 'Cables'; 'Allow Vendor Back Orders' checked; 'Addl Cost Alloc Basis' set to 'Amount'; 'Department' field; 'Replenishment Defaults' with fields for Buyer (Moncursor), Season Start, and Season End; 'Item Defaults' with fields for Item Type (Finished Good) and Match Tolerance (ten); 'Inventory Defaults' with fields for Demand Formula (Demand B), Safety Stock Formula (Safety A), and Lead Time Formula (Lead B). At the bottom, there are navigation buttons and a status bar showing 'admin SQA 1/8/99'.

Maintain items

A new Include On Packing List check box was added to the Sales & Purchasing tab page. If selected the item is printed on the Sales Order packing list. This field is checked (prints on packing list) for inventory type items such as, finished goods, raw material, assembled kit, and build-to-order kit, and not checked for non-inventory type items such as, miscellaneous, expense, service, or comment only.

The screenshot shows the 'Maintain Item' window with the 'Sales & Purchasing' tab selected. The 'Item' field is '1.44 Floppy'. The 'Short Description' is '1.44 MB Floppy Drive' and the 'Long Description' is 'TEAC 1.44MB 3.5 Floppy Drive'. The 'Sales' section includes fields for Product Line (Sys), Commission Class (Hardware), Target Margin (16.00), Price Sequence (0), Product Price Group (Price Group 1), Restocking Rate (200.000000), Minimum Sales Quantity (1.000), and Mandatory Sales Multiple (0). The 'Purchases' section includes Purchase Prod Line (Components), PO Match Tolerance (ten), and Period Usage Order Limit (0). The 'Options' section has several checkboxes: Returns Allowed (checked), Allow Drop Ship (unchecked), Internal Delivery Required (unchecked), Allow Cost Override (unchecked), Allow Price Override (unchecked), Receipt Required (checked), Allow Decimal Quantities (unchecked), Subject To Trade Discount (unchecked), and Include On Packing List (checked). The 'Include On Packing List' checkbox is circled in red. The bottom status bar shows 'Super SOA 6/22/99'.

Inquiries

Some fields have been rearranged in the following inquiry tasks to provide consistency:

- Inventory Status
- Bin / Lot / Serial
- Lot Transaction
- Serial Transaction

These tasks now display the warehouse first, followed by the item, and look similar to the task below.

Serial Transaction

Warehouse

Rialto

Item

Exchange Server

Serial No

A11552346

Status

Not Available

Expiration Date

Remaining Qty

Transactions

	Warehouse	Tran Date	Tran Type	Tran Qty	UOM	Vend/Cus
	Rialto	03/09/98	PU	1.000000000	Each	
	Rialto	03/09/98	SA	1.000000000	Each	

Super

SOA

6/16/99

60

Inventory transaction

If you access this task from the Inquiry menu, the Item field is enabled, and you can enter or select an item. You must select **Refresh** to populate the grid. If you access this inquiry from another task or select an item with the **Select...** button the grid automatically populates.

Setting: [None] Select ...

Item: 1.44 Floppy 1.44 MB Floppy Drive

Stock UOM: Each

Warehouse	Tran No	Tran Date	Post Date	Tran Type	Tran Qty
Rialto	0000000056-PU	05/23/98	05/23/98	IM Purchase	100.0
Rialto	0000000020-SA	05/22/98	05/22/98	IM Sale	-80.0
Rialto	0000000020-SA	05/22/98	05/22/98	IM Sale	-18.0
Rialto	0000000033-PU	05/01/98	05/22/98	IM Purchase	130.0
Rialto	0000000011-SR	05/23/98	05/29/98	IM Sale Return	3.0
Rialto	0000000021-IS	05/23/98	05/29/98	Issue	-5.0
Rialto	0000000075-PU	06/01/98	06/01/98	IM Purchase	32.0
Rialto	0000000010-KC	03/02/99	03/02/99	Kit Assembly Component	-1.0
Rialto	0000000014-SH	03/03/99	03/12/99	SH-Shipment	-1.0
Rialto	0000000054-SH	11/23/98	11/27/98	SH-Shipment	-5.0

admin SQA 5/8/98

Item history

If you access this task from the Inquiry menu, the Item field is enabled, and you can enter or select an item. You must select **Refresh** to populate the grid. If you access this inquiry from another task or select an item with the **Select...** button the grid automatically populates.

Setting: (None) [Select...]

Inquiry:

Item: 1.44 Floppy [Search] 1.44 MB Floppy Drive

Stock: Each

Total Quantity for Inquiry:

Receipts	16262	Adjustments	-5
Usage	11017	Transfers	0
Hits	16		

Year/Period	Warehouse	Qty Rcvd	Usage	Qty Adjusted	Qty Transferred	Hits	Co
1998/01	Rialto	5000.000	0.000	0.000	0.000	0	
1998/03	Rialto	0.000	1000.000	0.000	0.000	1	
1998/04	Rialto	0.000	999.000	0.000	0.000	1	
1998/05	Rialto	230.000	1162.000	-5.000	0.000	3	
1998/06	Rialto	32.000	978.000	0.000	0.000	1	
1998/07	Rialto	11000.000	0.000	0.000	0.000	0	
1998/08	Rialto	0.000	979.000	0.000	0.000	1	

admin SOA 5/8/98 [User Icon]

Purchase product line inquiry

If you access this task from the Inquiry menu, the Purchase Product Line field is enabled, and you can enter or select a purchase product line. You must select **Refresh** to populate the grid. If you access this inquiry from another task or select an item with the **Select...** button the grid automatically populates.

Warehouse	Period/Year	Cost Rcvd	Qty Rcvd	Weight Rcvd	Vol Rcvd
Rialto	1/1998	542500.000	33500.000	0.000	0.000
Rialto	3/1998	12250.000	25010.000	0.000	0.000
Rialto	6/1998	15000.000	5000.000	0.000	0.000
Rialto	7/1998	480000.000	19000.000	0.000	0.000
Rialto	9/1998	87125.000	8500.000	0.000	0.000
Rialto	11/1998	96750.000	8450.000	0.000	0.000
Rialto	12/1998	-160000.000	-4000.000	0.000	0.000
Vernon	4/1998	56225.000	287.000	0.000	0.000
Vernon	5/1998	51245.000	144.000	0.000	0.000

Inventory status

The Replenishment Position field and a ... (More) button were added. Select the ... (More) button to display the Replenishment Position window.

Warehouse: Rialto Rialto Warehouse

Item: 1.44 Floppy 1.44 MB Floppy Drive

Total Quantity On Hand: 5,263.000 Each

Total Quantity Available: 5,110.000 Each

Replenishment Position: 5,110.000 Each ...

Inventory Status

☐ Show Serials

Lot No	Expiration Date	Bin	Preference	Qty On Hand
6544886	01/01/00	11		956.000
98060822		1		51.000
98060822		10H		100.000
Lot123usebin11	01/01/00	11		4156.000

admin SOA 6/1/98

Accounts Receivable

This section discusses enhancements that have been made to Acuity Accounts Receivable in version 4.1.

AR Utilities

The Accounts Receivable Import utility allows you to transfer information from an existing accounts receivable system to the Acuity Accounts Receivable module. The following section explains the tasks that have been modified for importing accounts receivable data.

Customer address record layout

The the City, CountryID, and StateID fields are now required fields if you enter a value for PostalCode. The fields for Fax, FaxExt, Phone, and PhoneExt have been removed. You can enter this information in the Customer Contact record.

The customer address record is allowed in a customer import file and a customer address import file. It is a *required* record in the customer import file and can contain 'N' customer address records for every customer record. A valid customer address record inserts into *tarCustAddr* and updates the *tcAddress* table.

You must have one default bill to address, ship to address, and primary address in the customer import file. This does not necessarily mean that there is one record layout for each. The same record layout could be used for multiple default address types.

Depending on the value for the *DfltBilToAddrInd*, *DfltShipToAddrInd*, and *PrimaryAddrInd*, *tarCustomer* would be updated.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
1	RecordTypeID	<i>System maintained</i>	Char('R')	1	1	✓	
2	DfltBillToAddrInd	Default Bill To Address	SmallInt	2	1	✓	0 = No 1 = Yes If this address is used as the default BillToAddress for the customer, set to Yes.
3	DfltShipToAddrInd	Default Ship To Address	SmallInt	3	1	✓	0 = No 1 = Yes If this address is used as the default ShipToAddress for the customer, set to Yes.
4	PrimaryAddrInd	Street Address	SmallInt	4	1	✓	0 = No 1 = Yes If this address is used as the default primary address for the customer, set to Yes.

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
5	CurrID	Currency	Char(3)	5	3	✓	Validate with <i>tmcCurrency.CurrID</i> . Must be <i>tmcCurrency.IsUsed</i> = 1. <i>tarOptions.UseMultiCurr</i> = 1 (<> Home CurrID).
6	CustAddrID	Address	Char(15)	8	15	✓	Combination of CustKey and CustAddrID should be unique.
7	CustID	Customer	Char(12)	23	12	✓	Used to look up <i>tarCustomer.CustKey</i> for the current company.
8	FOBID	F.O.B.	Char(15)	35	15		Must be validated against <i>tcifOB</i> for the current company to retrieve the FOBKey.
9	InvFormID	Invoice Form	Char(15)	50	15		Used to look up <i>tcibusinessForm.BusinessFormKey</i> and populate <i>tarCustAddr.InvFormKey</i> . Must be <i>tcibusinessForm.BusinessFormType</i> = 2.
10	InvMsg	Invoice Message	VarChar(100)	65	100		
11	LanguageID	Language	LongInt	165	4	✓	Validate with <i>tcilanguage.LanguageID</i> .
12	PmtTermsID	Payment Terms	Char(15)	169	15		Used to look up <i>tcipaymentTerms.PmtTermsKey</i> .

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
13	PrintOrderAck	Print Order Acknowledgment	SmallInt	184	1	✓	0 = No 1 = Yes
14	ShipMethID	Ship Via	Char(15)	185	15		Used to look up <i>tcShipMethod.ShipMethKey</i> for the current company.
15	SalesTerritoryID	Territory	Char(15)	200	15		Used to look up <i>tarSalesTerritory.SalesTerritoryKey</i> for the current company.
16	ShipZoneID	<i>System maintained</i>	Char(15)	215	15		Used to look up <i>tcShipZone.ShipZoneKey</i> for the current company.
17	SperID	Salesperson	Char(12)	230	12		Used to look up <i>tarSalesperson.SperKey</i> for the current company. <i>tarSalesperson.Status</i> must be equal to 1 and <i>tarOptions.UseSPer</i> must be equal to 1.
18	AddrLine1	Street Address	VarChar(40)	242	40		
19	AddrLine2	Street Address	VarChar(40)	282	40		
20	AddrLine3	Street Address	VarChar(40)	322	40		
21	AddrLine4	Street Address	VarChar(40)	362	40		
22	AddrLine5	Street Address	VarChar(40)	402	40		
23	AddrName	Name	VarChar(40)	442	40		
24	City	City	Char(20)	482	20	✓ *	
25	CountryID	Country	Char(3)	502	3	✓ *	Validate with <i>tsmCountry</i> .
26	PostalCode	Postal Code	Char(9)	505	9		Validate with <i>tsmPostalCode</i> .
27	StateID	State	Char(3)	514	3	✓ *	Validate with <i>tsmState</i> .

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
28	CommPlanID	Commission Plan	Char(15)	517	15		Used to look up <i>tarCommPlan.CommPlanKey</i> for the current company.
29	STaxSchdID	Sales Tax Schedule	Char(15)	532	15		Used to look up <i>tcisTaxSchedule.STaxSchdKey</i> . If not entered, then default from the Customer Class Sales Tax Schedule.
30	WhseID	Closest Warehouse	Char(6)	547	6		Used to look up <i>timWarehouse.WhseKey</i> for the current company and populate <i>tarCustAddr.WhseKey</i> . It cannot be a transit warehouse (<i>timWarehouse.Transit</i> = 0).
31	SOAckFormID	Acknowledgment Form	Char(15)	553	15		Used to look up <i>tcisBusinessForm.BusinessFormKey</i> for the current company and populate <i>tarCustAddr.SOAckFormKey</i> . The form type (<i>tcisBusinessForm.BusinessFormType</i>) must be 8 (SO Acknowledgment).
32	ShipLblFormID	Shipping Label Form	Char(15)	568	15		Used to look up <i>tcisBusinessForm.BusinessFormKey</i> for the current company and populate <i>tarCustAddr.ShipLabelFormKey</i> . The form type (<i>tcisBusinessForm.BusinessFormType</i>) must be 4 (Customer Label).

No.	Field Name	Description	Data Type	Start	Width	Req'd	Restrictions
33	ShipComplete	Ship Complete	SmallInt	583	1		0 = No (default) 1 = Yes
34	ShipDays	Ship Days	SmallInt	584	5		Default = 3
35	AllowInvtSubst	Allow Inventory Substitutions	SmallInt	589	1	✓	0 = No 1 = Yes
36	CustPriceGroupID	<i>System maintained</i>	Char(15)	590	15		Used to look up <i>timCustPriceGroup.CustPriceGroupKey</i> for the current company.
37	PackListFormID	Packing List Form	Char(15)	605	15		Used to look up <i>tcBusinessForm.BusinessFormKey</i> and populate <i>tarCustAddr.PackListFormKey</i> . Must be <i>tcBusinessForm.BusinessFormType</i> = 15.

* These fields are required if a valid Postal Code is provided.

Sales Order

This section discusses enhancements that have been made to Acuity Sales Order in version 4.1.

Maintain blanket sales orders

You cannot generate sales orders from blanket sales orders that are on hold.

Appendices

The following appendices contain additional information regarding the installation of Acuity.

- Appendix A: Installing on Windows NT Clients (page 102)
- Appendix B: Client post-installation notes (page 103)
- Appendix C: Installing Seagate Crystal Reports Designer (page 105)
- Appendix D: Copying Acuity databases (page 109)
- Appendix E: Protocol issues (page 121)
- Appendix F: Command-line execution (page 135)
- Appendix G: Silent mode installation (page 155)

Appendix A: Installing on Windows NT Clients



Tip

Before installing the Acuity Client on an NT workstation or NT Server running SQL Server, shut down all SQL Server services, including SQL Server, SQL Executive, and DTC.

Windows NT 4.0 provides a secure client environment for running Acuity, but requires some additional installation steps if multiple users will access Acuity while logged on to this machine as an individual. You may encounter problems because individual profiles are created for each user with a valid local login. In addition, if policies are being implemented for users, then those policies must correspond to the rights as detailed by the procedure below.

Administrator installation

- 1 Login to the client machine as Local Administrator.
- 2 Follow the instructions found under “Installing the Local Client” on page 24 or “Installing the Network Client” on page 29.
- 3 Select the Windows **Start** button, then select **Run**.
- 4 Enter **regedt32** and select **OK**.
- 5 In the Registry Editor window, select **HKEY_LOCAL_MACHINE on local machine \ Software \ State Of The Art**.
- 6 Select **Security | Permissions** from the menu bar and select **Everyone**.
- 7 Select **Replace Permissions on Existing Subkeys**.
- 8 Change the Type of Access to **Full Control**, or add specific groups or users that should have access to Acuity, and select **OK**.
- 9 Select **Yes** when prompted to begin the permissions replacement for this key.
- 10 Exit the Registry Editor when the process is complete.

Appendix B: Client post-installation notes



WARNING

Selecting new values for any of the fields or options in the Acuity Registry Editor in a terminal server session affects all users connecting to Acuity through that Windows Terminal Server.

Upon completion of the Acuity client installation, the Acuity program group is added to your Start menu. This program group includes the following icons:

- **Acuity Financials** - Use this icon to start Acuity.
- **Registry Editor** - Use the Registry Editor to direct your Acuity client to another SQL Server or set of Acuity databases. Select or enter the server name in the Acuity Database Server field, then select **Refresh** to list the valid Acuity databases on that server. You can also select **Refresh** to find the SQL Servers in your domain. Select Use Windows NT Authentication when employing domain or NT users in Acuity, and select Show Startup Logo to view the splash screen when starting Acuity.
- **System Inspector** - Use the System Inspector as a client troubleshooting tool.
- **Uninstall Acuity Financials** – Use this icon to uninstall the Acuity client.

The Acuity folder contains all components of Acuity, which includes all the programs, Help, and reports available for each module and task.

The Acuity client installation automatically adds 32-bit ODBC and SQL Server communications components. In addition, two User Data Source Names (DSN) are added to ODBC. These are acuity-app and acuity-sys, which contain vital information used in accessing the SQL Server where the Acuity databases have been created. Do not modify these manually. Instead, use the Acuity Registry Editor mentioned above.

Appendix C: Installing Seagate Crystal Reports Designer

During installation of the Acuity client, the Seagate Crystal Reports version 7.0 runtime engine is also installed. This provides you with the ability to print and preview reports in Acuity. If you want to modify or create reports, install the Seagate Crystal Reports Designer. This component accompanies your Acuity software, but you must install it separately. It has been included with a local installation license. Contact Seagate Software to purchase a network license.

Follow the steps below to complete the installation of Seagate Crystal Reports.

Seagate Crystal Reports requirements

Before beginning the software installation, verify that your client machine meets the following criteria:

- 100MB of available disk space
- No other software applications are running
- A CD-ROM drive or access to a CD-ROM drive share point is available
- A default print device is established

Seagate Crystal Reports checklist

Before you install Seagate Crystal Reports for Acuity on your client machine, review the checklist to verify that you have completed all the required preliminary steps. If the answer to any of these questions is No, do not continue. Make the appropriate changes, then continue working through this checklist.

- ☐ **Do you have at least 100MB of available hard disk space on your local drive?**
This is the required hard disk space for installation of Seagate Crystal Reports.

- ❑ **Have you shut down all other software applications?**
An installation error may occur if other applications are running while attempting a Seagate Crystal Reports installation.
- ❑ **Have you defined a default printer?**
Seagate Crystal Reports requires a default printer to function properly.


Installing Seagate Crystal Reports for Acuity

You are now ready to install Seagate Crystal Reports for Acuity.


- 1 Insert the Acuity third party CD into your CD-ROM drive.
- 2 Select **Crystal Reports Installation**. The following window appears.



- 3 Select **Install (Win 32)**. The Welcome window displays. Select **Next**.
- 4 View and accept the License Agreement. The following window displays.



- 5 Select **Typical** to install the most common components, or select **Custom** to manually select the components you want to install. Select an installation directory and select **Next**. The following window displays.



- 6 Select the Program Group, then select **Next** to begin the Seagate Crystal Reports for Acuity installation.

Appendix D: Copying Acuity databases

The procedures discussed in this appendix explain how to correctly move or copy the Acuity databases and synchronize Acuity users. The operations detailed imply and require a certain knowledge of SQL Server and systems functions. The operations are, therefore, beyond the general scope of Acuity Support. If you are not familiar with these operations, defer the procedure to a knowledgeable professional.

Microsoft SQL Server 7 requirements

Before beginning the installation or upgrade process on SQL Server 7, verify that your server meets the following requirements:

- Minimum of 225MB of available disk space for the Server install of the Acuity database utilities.
- Minimum of 440MB available hard disk space for database creation.
- The tempdb size must be 1/3 of the application database or 100MB, whichever is larger. We recommend that you select **Automatically grow file** and **Unrestricted filegrowth** for both the database and transaction log. In the database Options, select **Select into/bulk copy**. We also recommend that you select **Truncate log on checkpoint**.
- For Microsoft SQL Server 7.0, you must have applied Service Pack 1. You can download the SQL Service Pack 1 from the Acuity CD or from the Microsoft Web site at <ftp://ftp.microsoft.com/softlib/mslfiles>. You can find instructions for applying the patches in the `Readme.txt` file.
- The Microsoft SQL Server service must be started and running before execution of the Acuity Database Creation Utility or Acuity Database Upgrade Utility.
- Your Master database in Microsoft SQL Server should have at least 50% free space. We recommend that you select **Automatically grow file** and **Unrestricted filegrowth** for both

the database and transaction log. In the database Options, select **Truncate log on checkpoint**.

Microsoft SQL Server 7 checklist

Before you install or upgrade Acuity on SQL Server 7, use the checklist to verify that you have completed all required preliminary steps. If the answer to any of these questions is No, do not continue. Make the appropriate changes, then continue working through the checklist.

- ☐ **Is your server's operating system Windows NT Server version 4.0?**
This is the only server platform supported.
- ☐ **Have you applied Service Pack 5 for Windows NT Server 4.0?**
Service Pack 5 contains the required updates for the proper operation of Acuity.
- ☐ **Have you installed Microsoft SQL Server 7.0?**
Microsoft SQL Server 7.0 must be installed and running prior to creation of the Acuity databases.
- ☐ **Have you applied Service Pack 1 for Microsoft SQL Server 7.0?**
Service Pack 1 contains the required updates for the proper operation of Acuity.
- ☐ **Is your server processor an Intel Pentium or Digital Alpha with a minimum of 128MB of RAM?**
Your Windows NT Server should have 128MB of RAM.
- ☐ **Do you have at least 440MB of free hard disk space?**
The minimum required space for creation of the Acuity databases and devices is 440MB.
- ☐ **If you are using the Dynamic Memory option, do you have at least 8MB of RAM allocated within SQL Server?**
When using Dynamic Memory, Microsoft SQL Server 7.0 should be configured with a minimum allocation of 8MB of RAM.
- ☐ **Is your tempdb for Microsoft SQL Server configured for the larger of either 1/3 of the application database or 100MB?**
The tempdb database must be configured to 1/3 of the application database size or 100MB (whichever is larger).

- ☐ **Have you backed up your master database and other existing databases?**
In the case of a Microsoft SQL Server failure, you may have to restore the databases from a backup.
- ☐ **Is your character set ISO - Code Page 1252?**
Acuity only supports this SQL Server 7.0 default character set.
- ☐ **Is your SQL Server's Sort Order ID 51 or 52?**
Verify this value using the *sp_configure* stored procedure.
- ☐ The Default language for user Server Setting must be English.
- ☐ Select **Allow nested triggers**.
- ☐ Verify the Query governor cost limit value is set to 0.
- ☐ The Y2K support setting should be between 1950 and 2049.
- ☐ Set the minimum number of concurrent user connections to 15 x <number of client connections>.
- ☐ None of the attribute values should be selected for the Default Connection Options.

Microsoft SQL Server 6.5 requirements

Before beginning the installation or upgrade process on SQL Server 6.5, verify that your server meets the following requirements:

- Minimum of 225MB of available disk space for the Server install of the Acuity database utilities.
- Minimum of 440MB available hard disk space for database creation.
- The tempdb size must be 1/3 of the application database or 100MB, whichever is larger. We recommend creation under a device other than the default master device.
- For Microsoft SQL Server 6.5, you must have applied Service Pack 5a. You can download the SQL Service Pack 5a from the Acuity CD or from the Microsoft Web site at <ftp://ftp.microsoft.com/softlib/mslfiles>. For the Intel service pack, select 65sp4x86.exe. For the Alpha service pack, select 65sp4alp.exe. You can find instructions for applying the patches in the Readme.txt file.

- The Microsoft SQL Server service must be started and running before execution of the Acuity Database Creation Utility or Acuity Database Upgrade Utility.
- Your Master database in Microsoft SQL Server should have at least 50% free space.

Microsoft SQL Server 6.5 checklist

Before you install or upgrade Acuity on your server, use the checklist to verify that you have completed all required preliminary steps. If the answer to any of these questions is No, do not continue. Make the appropriate changes, then continue working through the checklist.

- ☐ **Is your server's operating system Windows NT Server version 4.0?**
This is the only server platform supported.
- ☐ **Have you applied Service Pack 5 for Windows NT Server 4.0?**
Service Pack 5 contains the required updates for the proper operation of Acuity.
- ☐ **Have you installed Microsoft SQL Server 6.5?**
Microsoft SQL Server 6.5 must be installed and running prior to creation of the Acuity databases.
- ☐ **Have you applied Service Pack 5a for Microsoft SQL Server 6.5?**
Service Pack 5a contains the required updates for the proper operation of Acuity.
- ☐ **Is your server processor an Intel Pentium or Digital Alpha with a minimum of 128MB of RAM?**
Your Windows NT Server should have 128MB of RAM with a minimum of 32MB configured for Microsoft SQL Server.
- ☐ **Do you have at least 440MB of free hard disk space?**
The minimum required space for creation of the Acuity databases and devices is 440MB.
- ☐ **Is your tempdb for Microsoft SQL Server configured for the larger of either 1/3 of the application database or 100MB?**
The tempdb database must be configured to 1/3 of the application database size or 100MB (whichever is larger).

- ❑ **Have you backed up your master database and other existing databases?**

In the case of a Microsoft SQL Server failure, you may have to restore the databases from a backup.

- ❑ **Is your character set ISO 8859-1?**

Acuity only supports this SQL Server default character set.


- ❑ **Is your new SQL Server's Sort Order ID 51 or 52?**

Verify this value using the *sp_configure* stored procedure.

The Database Synchronization Utility

This utility is an essential part of moving or copying Acuity databases. With the Database Synchronization Utility, you can synchronize Acuity and Acuity Projects users on a new SQL Server. You can also correct modified Acuity or Acuity Projects internal database name references if you rename these databases.

To use the Database Synchronization Utility, install the Acuity Financials Database Utilities. Select **Start | Programs | Acuity Financials | Acuity Financials Database Synchronization Utility** to start the utility. Complete the login information, including the SA password. The following window appears.



Select the appropriate System, Application, and Project Accounting Databases that you want to synchronize.

Select **Synchronize Acuity Financials users on a new SQL Server** to add users created in Acuity to the new SQL Server. When you create these, the passwords for these logins are set to null (blank) and permissions are reset for all objects. This option also recreates the

“admin” and “sotaadmin” users if they no longer exist. This is necessary when the Acuity databases are copied to the new SQL Server.

Select **Check Acuity Financials database name references** to reset the internal name references that Acuity uses to refer to the other databases in the set. This is necessary when databases are renamed or copied to another server.

Single-user unique set on same SQL Server 6.5 or SQL Server 7.0 server

To create a second unique database set using the same server with access granted to the “admin” user ID only, follow the steps below. This scenario does not allow a password or password change in either database set for the admin user.

- 1 Select **Start | Programs | Acuity Financials | Acuity Financials Database Creation Utility** on the machine on which the Acuity Database Utilities were installed.
- 2 Within the Database Creation Utility, specify device and database names different from those previously created.

Multi-user duplicate set on same SQL Server 6.5 server

To create a second duplicate database set using the same server with access granted to multiple users, follow the steps below. This scenario does not allow a password change in either database set for these users. In addition, users created in one database set will have access only to that database set’s information. For the user to also have access to data in the other database set, the user must be created in the additional set. No password is allowed for this user in either set.

- 1 Using ISQL or the Enterprise Manager Query Tool, execute the ***sp_coalesce_fragments*** system stored procedure against both the system and application databases.
- 2 Also using ISQL or the Enterprise Manager Query Tool, execute the ***sp_help_revdatabase*** system stored procedure against both

the system and application databases. For each query, be sure to save the script shown in the query results to a file.

- 3 Using the **DISK INIT** function in ISQL, or the **Manage Devices** function in Enterprise Manager, create new database devices corresponding to the device formats currently used for the system and application databases. The device fragment sizes and orders must match (see the LOAD statement in *SQL Server Books Online*), but the names must not.
- 4 Modify the *sp_help_revdatabase* script to reflect the new device (created in step 3) and database names. In ISQL or the Enterprise Manager Query Tool, load, then execute this script in the query window.
- 5 Using the **Enterprise Manager | Tools | Database Backup/Restore** function, create a new backup device to a local or mapped hard drive or tape, making sure there is enough disk space.
- 6 Select the new device and set the **Initialize Device** option.
- 7 Select the production Acuity application database, then select **Backup Now**.
- 8 Remove the **Initialize Device** option, then select the Acuity system database, and select **Backup Now**.
- 9 Select the **Restore** tab, then **From Device**, and select the device created in step 5.
- 10 Select the new application database created in step 1, then the application database backup in the Backup Information grid and select **Restore Now**.
- 11 Repeat steps 9 and 10 for the system database.
- 12 Select **Start | Programs | Acuity Financials | Acuity Financials Database Synchronization Utility** on the machine on which the Acuity Database Utilities were installed.
- 13 Login and specify the new databases created, then select the **Check Acuity Financials Database Name Reference** option only, and select **Proceed**.

Multi-user duplicate set on same SQL Server 7.0 server

To create a second duplicate database set using the same server with access granted to multiple users, follow the steps below. This scenario does not allow a password change in either database set for SQL Server users. This does not apply to Windows NT users when using the Use Windows NT Authentication option.

- 1 Using **Enterprise Manager | Action | New Database**, create a new database representing the Acuity application database. Specify the same file sizes for the database and transaction log as those shown in the production database.
- 2 Start **Tools | Backup Database**, and select the production Acuity application database and select **Database - complete**.
- 3 Add a new backup destination device to a local or mapped hard drive or tape, making sure there is enough disk space to accommodate the data size.
- 4 On the Options tab page, select **Overwrite existing media**, then select **Verify backup upon completion**.
- 5 Also on the Options tab page, select **Initialize and label media**, assign the proper name and description, then select **OK** to begin the backup process.
- 6 Repeat steps 1 through 4 for the production Acuity system database.
- 7 Start **Tools | Restore Database**, and select the destination application database in the **Restore as database** field.
- 8 Select **From device**, then select the device created in step 3.
- 9 Select **Database - complete**. On the Options tab page, select **Force restore over existing database**, then select **OK** to begin restoration of the database.
- 10 Repeat steps 7 through 9 for the destination system database.

- 11 Select **Start | Programs | Acuity Financials | Acuity Financials Database Synchronization Utility** at the machine on which the the Acuity Database Utilities were installed.
- 12 Login and specify the new databases created, then select **Check Acuity Financials Database Name Reference** only, and select **Proceed**.

Multi-user duplicate set on separate SQL Server 6.5 server

To create a second duplicate database set using a different server with access granted to multiple users, follow the steps below. This scenario allows passwords and password changes for all users. Users created in one database set on one server will have access only to that database set's information. For a user to also have access to data in the other database set on the other server, the user must be created in that set. The SQL Server on which the databases originate is referred to as server 1. The destination SQL Server is referred to as server 2. On server 1, use ISQL or the Enterprise Manager Query Tool, execute the ***sp_coalesce_fragments*** system stored procedure against both the system and application databases.

- 1 On server 1, also using ISQL or the Enterprise Manager Query Tool, execute the ***sp_help_revdatabase*** system stored procedure against both the system and application databases. For each query, be sure to save the script shown in the query results to a file.
- 2 On server 1, use the **Enterprise Manager | Tools | Database Backup/Restore** function to create a new backup device to a local sharepoint or common mapped hard drive or tape, making sure there is enough space.
- 3 On server 1, use **Enterprise Manager | Tools | Database Backup/Restore** to create a new backup device to a local sharepoint, making sure there is enough space.
- 4 On server 1, select the production Acuity application database, then select **Backup Now**.
- 5 On server 1, remove the **Initialize Device** option, then select the Acuity system database, and select **Backup Now**.

- 6 On server 2, use the **DISK INIT** function in ISQL, or the **Manage Devices** function in Enterprise Manager and create new database devices corresponding to the device formats currently used for the system and application databases. The device fragment sizes and orders must match (see the LOAD statement in *SQL Server Books Online*), but the names must not.
- 7 Modify the *sp_help_revdatabase* script to reflect the new device (created in step 3) and database names. On server 2, use ISQL or the Enterprise Manager Query Tool and load then execute this script in the query window.
- 8 On server 2, start **Enterprise Manager | Tools | Database Backup/Restore**. Load the tape on which the databases have been backed up in preparation to restore them. If the backup was created on disk, then move these files to your local hard drive and create a backup device corresponding to the same name created for the device in step 2.
- 9 On server 2, select the **Restore** tab, then **From Device**, and select the tape device or backup device created in step 8.
- 10 On server 2, select the new application database created in step 6, then the application database backup in the Backup Information grid, and select **Restore Now**.
- 11 Repeat steps 9 and 10 for the system database.
- 12 Select **Start | Programs | Acuity Financials | Acuity Financials Database Synchronization Utility** on the machine on which the Acuity Database Utilities were installed.
- 13 Login and specify the new databases created, select both **Synchronize Acuity Financials User** and **Check Acuity Financials Database Name Reference**. Select **Proceed**.

Multi-user duplicate set on separate SQL Server 7.0 server

To create a second duplicate database set using a different server with access granted to multiple users, follow the steps below. This scenario allows passwords and password changes for all users. The SQL Server on which the databases originate is referred to as the production server. The destination SQL Server is referred to as the

destination server. If all users created are Windows NT users and the new SQL Server does not connect to the same domain, these users will no longer have login abilities into Acuity. New Windows NT or SQL Server users will have to be created.

- 1 At the production server, start **Tools | Backup Database**. Select the Acuity application database and **Database - complete**.
- 2 At the production server, add a new backup destination device to a local or mapped hard drive or tape, making sure there is enough disk space to accommodate the data size.
- 3 At the production server, select **Overwrite existing media**, then select **Verify backup upon completion** on the Options tab page.
- 4 Also on the Options tab page, select **Initialize and label media**. Assign the proper name and description, then select **OK** to begin the backup process.
- 5 At the production server, repeat steps 1 through 4 for the Acuity system database.
- 6 At the destination server, using **Enterprise Manager | Action | new Database**, create two new databases representing the Acuity application and system databases. Specify the same file sizes for the database and transaction log as those shown for the Acuity databases on server 1.
- 7 At the destination server, start **Tools | Restore Database** and select the destination application database in the **Restore as database** field.
- 8 At the destination server, select **From device**. Load the tape on which the databases have been backed up or select the device on the drive on which the production application database has backed up.
- 9 At the destination server, select **Database - complete**. On the Options tab page, select **Force restore over existing database**, then select **OK** to begin restoration of the database.
- 10 At the destination server, repeat steps 7 through 9 for the destination system database.

- 11 Select **Start | Programs | Acuity Financials | Acuity Financials Database Synchronization Utility** at the machine on which the Acuity Database Utilities were installed.
- 12 Login to the destination server and specify the new databases created. Select **Synchronize Acuity Financials users on a new SQL Server** and **Check Acuity Financials Database Name Reference**, then select **Proceed**.

Connecting the Client

All the server configurations listed require a change to the pointers Acuity uses to find the server and clients. You can generally perform these changes by following the steps detailed below.

- 1 Start the Client Configuration Utility within ODBC and add any required advanced information for the new server. Refer to “Appendix E: Protocol issues” on page 121 for detailed instructions.
- 2 Select **Start | Programs | Acuity Financials | Registry Editor**.
- 3 Enter the correct server name then select **Refresh**.
- 4 Select the appropriate database set in the **System Database Name** and **Application Database Name** options.
- 5 Start the Acuity client. At the login window, select **Advanced Options** to verify or change the server and databases to which the client is connecting.

Appendix E: Protocol issues

Microsoft is aware of issues within the 1.0 TCP/IP Winsock library for Windows 95. For TCP/IP networks we recommend using the Windows NT Workstation operating system at the client, implementing either the Named Pipes or Multi-Protocol IPC mechanism, or applying the Winsock Service Pack from Microsoft. It is our general experience that TCP/IP Sockets performs best over most networks. Review the Preinstall Section | Protocol Matrix pages on our website at www.us.sage.com/acuity/support for any updated information.

The InterProcess Communications mechanisms supported by Acuity are as follows.

Windows 95 and Windows 98 clients

Named Pipes over TCP/IP

You must be able to ping the SQL Server at a command prompt from the client machine. In addition, you must be able to connect to the SQL Server using the acuity-app and acuity-sys ODBC Data Source Name (DSN). A general rule for connecting using Named Pipes is that you must be logged in to the domain on which the SQL Server resides or have an open pipe into a resource at the SQL Server. A pipe can be opened to the IPC\$ sharepoint on the server using the net view command-line utility. Connecting to any other shared resource using the browse or mapping features in **Windows Explorer** or the **Network Neighborhood** applet serves the same purpose.

SQL SERVER 7.0

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 7.0 | Server Network Utility**.
- 2 Select **Add**.
- 3 Enter the pipe name in the **Pipe name** field, or accept the default by selecting **OK**.

- 4 The SQL Server Server Network Utility returns you to the General tab page. Select **OK**.
- 5 Stop, then restart the SQL Server Service.

SQL SERVER 6.5

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 6.5 | SQL Setup**.
- 2 In SQL Setup, continue through the Welcome and Installed windows to the Options window.
- 3 Select **Change Network Support**, then select **Continue**.
- 4 Select **Named Pipes**, then select **OK** and continue through the remaining fields.
- 5 Stop, then restart the SQL Server service.

CLIENT (INCLUDING WINDOWS TERMINAL SERVER)

- 1 Remove the NetBEUI protocol from the client system, or remove this network protocol from the server.
- 2 From the Windows **Start** button, select **Settings | Control Panel | 32-bit ODBC**.
- 3 Select the acuity-app or acuity-sys DSN and select **Configure**. If no acuity Data Source Names appear in the list, refer to chapter 3 for installation instructions.
- 4 Verify the correct server name is entered, select **Next** and select **Client Configuration**.
- 5 In the Client Configuration section on the Advanced tab, enter the server name or the Server alias.
- 6 Select **Named Pipes** for the DLL Name from the drop-down list or select it from the list of Network libraries.
- 7 Select **Add/Modify**, then select **Done** or select **OK**.
- 8 Enter a valid Acuity user ID and password, or **SA** as the Login ID with the appropriate password.

- 9 Select **Next** to verify connectivity. Once this has been established, select **Cancel**. If the connection fails, refer the issue to your IS professional or Microsoft, this is beyond the scope of Acuity Support.
- 10 Logon with the Acuity registry editor or client application.

Disadvantages to this configuration include the fact that all protocols except TCP/IP may have to be removed from the client system if the protocol bindings are not modified. The TCP/IP network protocol should be the first protocol bound to the Network Interface Card (NIC) within the Control Panel | Network | Bindings window.

Multi-protocol over TCP/IP (port 1434)

You must be able to ping the SQL Server at a command prompt from the client machine. In addition, you must be able to connect to the SQL Server using the acuity-app and acuity-sys ODBC Data Source Name (DSN). A general rule for connecting using Multi-Protocol is that you must be logged in to the domain on which the SQL Server resides, or have an open pipe into a resource at the SQL Server. A pipe can be opened to the IPC\$ sharepoint on the server using the net view command-line utility. Connecting to any other shared resource using the browse or mapping features in **Windows Explorer** or the **Network Neighborhood** applet serve the same purpose.

SQL SERVER 7.0

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 7.0 | Server Network Utility**.
- 2 Select **Add**.
- 3 Enter a server alias. If you want the alias and the computer name to be different, change the name in the Computer Name field.
- 4 Select **OK**. The SQL Server Server Network Utility returns you to the General tab page. Select **OK**.
- 5 Stop, then restart the SQL Server Service.

SQL SERVER 6.5

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 6.5 | SQL Setup**.
- 2 In SQL Setup, continue through the Welcome and Installed windows to the Options window.
- 3 Select **Change Network Support**, then select **Continue**.
- 4 Select **Multi-Protocol**, then select **OK** to continue.
- 5 Although it is not required, you can select to encrypt Multi-Protocol communications at the encryption window.
- 6 From the Windows **Start** button, select **Run** and enter **REGEDT32** in the Open: field.
- 7 Navigate to the **HKEY_LOCAL_MACHINE\Software\Microsoft\MSSQLSERVER\MSSQLSERVER\RPCNetlib** registry key.
- 8 Select **Edit | Add Value** and enter **RPCprotocols** with a data type of **REG_MULTI_SZ**.
- 9 For the Data value, enter **ncacn_ip_tcp,1434**.
- 10 Stop, then restart the SQL Server service.



WARNING

This text is case-sensitive, and there is no space before or after the comma.

CLIENT (INCLUDING WINDOWS TERMINAL SERVER)

- 1 From the Windows **Start** button, select **Settings | Control Panel | 32-bit ODBC**.
- 2 Select the acuity-app or acuity-sys DSN and select **Configure**. If no acuity Data Source Names appear in the list, refer to chapter 3 for installation instructions.
- 3 Verify the correct server name is entered, select **Next** and select **Client Configuration**.
- 4 In the Client Configuration section on the Advanced tab, enter the server name or the Server alias.
- 5 Select **Multi-Protocol** for the DLL Name from the drop-down list or select it from the list of Network libraries.
- 6 In the Connection String or Additional parameters field, enter **ncacn_ip_tcp:<server ip address>[1434]**.



WARNING

This text is case-sensitive, and there is no space between the :, the ip address, and the [,

- 7 Select **Add/Modify**, then select **Done**.
- 8 Enter a valid Acuity user ID and password, or **SA** as the Login ID with the appropriate password.
- 9 Select **Next** to verify connectivity. Once this has been established, select **Cancel**.
- 10 Logon with the Acuity registry editor or client application.

IPX/SPX over IPX/SPX protocol

The NWLink IPX/SPX protocol must be installed at both the server and client. In addition, you must be able to connect to the SQL Server using the acuity-app and acuity-sys ODBC Data Source Name (DSN).

SQL SERVER 7.0

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 7.0 | Server Network Utility**.
- 2 Select **Add**.
- 3 Enter a server alias.
- 4 You can specify connection parameters by service name or network address. If you select **Service Name**, enter the name of the service. If you select **Network Address**, enter the Address, Port, and Network information for your network.
- 5 Select **OK**. The SQL Server Server Network Utility returns you to the General tab page. Select **OK**.
- 6 Stop, then restart the SQL Server Service.

SQL SERVER 6.5

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 6.5 | SQL Setup**.
- 2 In SQL Setup continue through the Welcome and Installed windows to the Options window.
- 3 Select **Change Network Support**, then select **Continue**.
- 4 Select **NWLink IPX/SPX**, then select **OK** to continue.
- 5 Stop, then restart the SQL Server service.

CLIENT (INCLUDING WINDOWS TERMINAL SERVER)

- 1 From the Windows **Start**, button, select **Settings | Control Panel | 32-bit ODBC**.
- 2 Select the acuity-app or acuity-sys DSN and select **Configure**. If no Acuity Data Source Names appear in the list, refer to chapter 3 for installation instructions.
- 3 Verify the correct server name is entered. Select **Next** and select **Client Configuration**.
- 4 In the Client Configuration section on the Advanced tab, enter the server name or the Server alias.
- 5 Select **NWLink IPX/SPX** for the DLL Name from the drop-down list or select it from the list of Network libraries.
- 6 Select **Add/Modify**, then select **Done**.
- 7 Enter a valid Acuity user ID and password, or **SA** as the Login ID with the appropriate password.
- 8 Select **Next** to verify connectivity. Once this has been established, select **Cancel**.
- 9 Logon with the Acuity registry editor or client application.

Unless a NetWare server resides on the network, the clients may encounter problems in the naming service and therefore may not find the SQL Server. The NWLink IPX/SPX IPC mechanism is specific to the IPX/SPX protocol.

Windows NT 4.0 Workstation client

Named Pipes over TCP/IP

You must be able to ping the SQL Server at a command prompt from the client machine. In addition, you must be able to connect to the SQL Server using the acuity_app and acuity_sys ODBC Data Source Name (DSN). A general rule for connecting using Named Pipes is that you must be logged in to the domain in which the SQL Server resides, or have an open pipe into a resource at the SQL Server. A pipe can be opened to the IPC\$ sharepoint on the server using the net view command-line utility. Connecting to any other shared resource

using the browse or mapping features in **Windows Explorer** or the **Network Neighborhood** applet serves the same purpose.

SQL SERVER 7.0

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 7.0 | Server Network Utility**.
- 2 Select **Add**.
- 3 Enter the pipe name in the **Pipe name** field, or accept the default by selecting **OK**.
- 4 The SQL Server Server Network Utility returns you to the General tab page. Select **OK**.
- 5 Stop, then restart the SQL Server Service.

SQL SERVER 6.5

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 6.5 | SQL Setup**.
- 2 In SQL Setup, continue through the Welcome and Installed windows to the Options window.
- 3 Select **Change Network Support**, then select **Continue**.
- 4 Select **Named Pipes** then select **OK**, and continue through the remaining windows.
- 5 Stop, then restart the SQL Server service.

CLIENT (INCLUDING WINDOWS TERMINAL SERVER)

- 1 Remove the NetBEUI protocol from the client system, or specify the TCP/IP protocol as the first in the Workstation binding order.
- 2 From the Windows **Start** button, select **Settings | Control Panel | 32-bit ODBC**.
- 3 Select the acuity_app or acuity_sys DSN, and select **Configure**. If no acuity Data Source Names appear in the list, refer to chapter 3 for installation instructions.
- 4 Verify that the correct server name is entered. Select **Next**, and select **Client Configuration**.

- 5 In the Client Configuration section on the Advanced tab, enter the server name or the Server alias.
- 6 Select **Named Pipes** for the DLL Name from the drop-down list or select it from the list of Network libraries.
- 7 Select **Add/Modify**, then select **Done** or select **OK**.
- 8 Enter a valid Acuity user ID and password or **SA** as the Login ID with the appropriate password.
- 9 Select **Next** to verify connectivity. Once verified, select **Cancel**.
- 10 Logon with the Acuity registry editor or client application.

Disadvantages to this configuration include the fact that all protocols except TCP/IP may have to be removed from the client system if the protocol bindings are not modified. The TCP/IP network protocol should be the first protocol bound to the Network Interface Card (NIC) within the Control Panel | Network | Bindings window.

Multi-Protocol over TCP/IP (port 1434)

You must be able to ping the SQL Server at a command prompt from the client machine. In addition, you must be able to connect to the SQL Server using the acuity_app and acuity_sys ODBC Data Source Name (DSN). A general rule for connecting using Multi-Protocol is that you must be logged in to the domain in which the SQL Server resides, or have an open pipe into a resource at the SQL Server. A pipe can be opened to the IPC\$ sharepoint on the server using the net view command-line utility. Connecting to any other shared resource using the browse or mapping features in **Windows Explorer** or the **Network Neighborhood** applet serves the same purpose.

SQL SERVER 7.0

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 7.0 | Server Network Utility**.
- 2 Select **Add**.
- 3 Enter a server alias. If you want the alias and the computer name to be different, change the name in the Computer Name field.
- 4 Select **OK**. The SQL Server Server Network Utility returns you to the General tab page. Select **OK**.
- 5 Stop, then restart the SQL Server Service.

SQL SERVER 6.5

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 6.5 | SQL Setup**.
- 2 In SQL Setup, continue through the Welcome and Installed windows to the Options window.
- 3 Select **Change Network Support**, then select **Continue**.
- 4 Select **Multi-Protocol**, then select **OK** to continue.
- 5 Although it is not required, you may select to encrypt Multi-Protocol communications at the encryption window.
- 6 From the Windows **Start** button, select **Run**, and enter **REGEDT32** in the Open: field.
- 7 Navigate to the **HKEY_LOCAL_MACHINE\Software\Microsoft\MSSQLSERVER\MSSQLSERVER\RPCNetlib** registry key.
- 8 Select **Edit | Add Value**, and enter **RPCprotocols** with a data type of **REG_MULTI_SZ**.
- 9 For the Data value, enter **ncacn_ip_tcp,1434**.
- 10 Stop, then restart the SQL Server service.



WARNING

This text is case-sensitive, and there is no space before or after the comma.

CLIENT (INCLUDING WINDOWS TERMINAL SERVER)

- 1 From the Windows **Start** button, select **Settings | Control Panel | 32-bit ODBC**.
- 2 Select the acuity_app or acuity_sys DSN, and select **Configure**. If no acuity Data Source Names appear in the list, refer to chapter 3 for installation instructions.
- 3 Verify the correct server name is entered. Select **Next**, and select **Client Configuration**.
- 4 In the Client Configuration section on the Advanced tab, enter the server name or the Server alias.
- 5 Select **Multi-Protocol** for the DLL Name from the drop-down list or select it from the list of Network libraries.
- 6 In the Connection String or Additional parameters field enter **ncacn_ip_tcp:<server ip address>[1434]**.
- 7 Select **Add/Modify**, then select **Done**.
- 8 Enter a valid Acuity user ID and password or **SA** as the Login ID with the appropriate password.
- 9 Select **Next** to verify connectivity. Once verified, select **Cancel**.
- 10 Logon with the Acuity registry editor or client application.



WARNING

This text is case-sensitive, and there is no space between the :, the ip address, and the [.

IPX/SPX over IPX/SPX protocol

The NWLink IPX/SPX protocol must be installed at both the server and client. In addition, you must be able to connect to the SQL Server using the acuity_app and acuity_sys ODBC Data Source Name (DSN).

SQL SERVER 7.0

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 7.0 | Server Network Utility**.
- 2 Select **Add**.

- 3 Enter a server alias.
- 4 You can specify connection parameters by service name or network address. If you select **Service Name**, enter the name of the service. If you select **Network Address**, enter the Address, Port, and Network information for your network.
- 5 Select **OK**. The SQL Server Server Network Utility returns you to the General tab page. Select **OK**.
- 6 Stop, then restart the SQL Server Service.

SQL SERVER 6.5

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 6.5 | SQL Setup**.
- 2 In SQL Setup, continue through the Welcome and Installed windows to the Options window.
- 3 Select **Change Network Support**, then select **Continue**.
- 4 Select **NWLink IPX/SPX**, then select **OK** to continue.
- 5 Stop, then restart the SQL Server service.

CLIENT (INCLUDING WINDOWS TERMINAL SERVER)

- 1 From the Windows **Start** button, select **Settings | Control Panel | 32-bit ODBC**.
- 2 Select the acuity_app or acuity_sys DSN and select **Configure**. If no Acuity Data Source Names appear in the list, refer to chapter 3 for installation instructions.
- 3 Verify the correct server name is entered. Select **Next**, and select **Client Configuration**.
- 4 In the Client Configuration section on the Advanced tab, enter the server name or the Server alias.
- 5 Select **NWLink IPX/SPX** for the DLL Name from the drop-down list or select it from the list of Network libraries.
- 6 Select **Add/Modify**, then select **Done**.
- 7 Enter a valid Acuity user ID and password or **SA** as the Login ID with the appropriate password.

- 8 Select **Next** to verify connectivity. Once verified, select **Cancel**.
- 9 Logon with the Acuity registry editor or client application.

Unless a NetWare server resides on the network, the clients may encounter problems in the naming service and, therefore, may not find the SQL Server. The NWLink IPX/SPX IPC mechanism is specific to the IPX/SPX protocol.

TCP/IP sockets over TCP/IP protocol

You must be able to ping the SQL Server at a command prompt from the client machine. In addition, you must be able to connect to the SQL Server using the acuity-app and acuity-sys ODBC Data Source Name (DSN).

SQL SERVER 7.0

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 7.0 | Server Network Utility**.
- 2 Select **Add**.
- 3 Enter a server alias. If you want the server alias and the computer name to be different, change the name in the Computer Name field.
- 4 Select **OK**. The SQL Server Server Network Utility returns you to the General tab page. Select **OK**.
- 5 Stop, then restart the SQL Server Service.

SQL SERVER 6.5

- 1 From the Windows **Start** button, select **Programs | Microsoft SQL Server 6.5 | SQL Setup**.
- 2 In SQL Setup, continue through the Welcome and Installed windows to the Options window.
- 3 Select **Change Network Support**, then select **Continue**.
- 4 Select **TCP/IP Sockets**, then select **OK** and continue through the remaining window (note the port number if this is changed).
- 5 Stop, then restart the SQL Server service.

CLIENT (INCLUDING WINDOWS TERMINAL SERVER)

- 1 From the Windows **Start** button, select **Settings | Control Panel | 32-bit ODBC**.
- 2 Select the acuity-app or acuity-sys DSN and select **Configure**. If no Acuity Data Source Names appear in the list, refer to chapter 3 for installation instructions.
- 3 Verify the correct server name is entered. Select **Next**, and select **Client Configuration**.
- 4 In the Client Configuration section on the Advanced tab enter the server name or the Server alias.
- 5 Select **TCP/IP Sockets** for the DLL Name from the drop-down list or select it from the list of Network libraries.
- 6 Enter <server ip address>,<port #> in the Connection String field.
- 7 Select **Add/Modify**, then select **Done**.
- 8 Enter a valid Acuity user ID and password, or SA as the Login ID with the appropriate password.
- 9 Select **Next** to verify connectivity. Once this has been established, select **Cancel**.
- 10 Logon with the Acuity registry editor or client application.



WARNING

This text is case-sensitive, and there is no space before or after the comma.

This IPC mechanism is specific to the TCP/IP protocol. Although it is not required, the connection string specifying the IP address and port number are recommended in the case that the IP name resolution service is not operating or available.

Appendix F: Command-line execution

Acuity tasks with an EXE extension support direct execution from a command prompt or shortcut. This method must include the program name and the /t switch, which is followed by the task ID parameter.

FOR EXAMPLE:

C:> \Acuity\sm\smzma001 /t 16842757

Programs can generally be found within the module's folder in the Acuity folder. For instance, System Manager (SM) programs can be found in the Acuity\SM folder where the Acuity client is installed.

Important notes

Acuity tasks launched through shortcuts behave just like every other Acuity task. The Acuity LaunchPad has been modified to support shortcuts and does not display unless specifically launched.

If you launch a task from a shortcut, and it is the first Acuity task to run on that machine, you are prompted with the login window. After a successful login, only the task invoked appears. The Acuity LaunchPad does not. Subsequent executions of shortcuts in this session do not launch the login window. This limits you to working in only the company specified during the original login. If it is necessary for you to work within multiple companies in one session, start the Acuity LaunchPad.

If you launched an Acuity task from a shortcut, and the LaunchPad is not running, a subsequent execution of the Acuity LaunchPad does not invoke the login window.

If the Acuity LaunchPad is running, a shortcut execution launches the task in the company currently specified in the LaunchPad.

If the Acuity LaunchPad is shut down all Acuity tasks, including tasks started with a shortcut, are ordered to shut down.

Obtaining the task ID

In ISQL you can use the following query against the Acuity system database to obtain the task IDs for a given module. Changing the like filter allows you to obtain these by module. The following query example lists the tasks associated with the System Manager module:

```
SELECT tsmTask.TaskID, tsmTask.TaskOleProgID,  
tsmMenu.MenuTitle  
  
FROM tsmTask, tsmMenu  
  
WHERE UPPER(TaskOleProgID) like 'SM%'  
  
AND tsmTask.TaskID = tsmMenu.TaskID  
  
ORDER BY MenuTitle  
  
or  
  
SELECT SUBSTRING(tsmTaskStrDef.TaskLongName,1,2)  
"Module",  
RTRIM(SUBSTRING(tsmTaskStrDef.TaskLongName,4,40))  
"Menu Item",  
LOWER(SUBSTRING(tsmTask.TaskOleProgID,1,16))"Progra  
m Name", tsmTask.TaskID "Task ID"  
  
FROM tsmTask, tsmMenu, tsmTaskStrDef  
  
WHERE tsmTask.TaskID = tsmMenu.TaskID  
  
AND tsmTask.TaskID = tsmTaskStrDef.TaskID  
  
ORDER BY tsmTaskStrDef.TaskLongName
```

You can also use the following list of menu titles, program names, and task IDs to identify the tasks against which you want to create shortcuts.

Menu Item	Program Name	Task ID
Accounts Payable		
1099 Activity Report	APZRP001	67698703
1099 Beginning Balances	APZDN001	67502240
1099 Box Setup	APZMC001	67174405

Menu Item	Program Name	Task ID
1099 Corrections	APZDM001	67502210
1099 Form Printing	APZRQ001	67698704
Age Vendor Accounts	APZDG001	67502160
Aged Payables	APZRF001	67698693
Aged Payables Report (MC)	APZRF001	67698709
Analysis Report	APZRL001	67698714
Apply Payments and Memos Process	APZDJ001	67502130
Cash Requirements Report	APZRH001	67698695
Custom Field Value Setup	CIZMD001	67174407
Edit Voucher 1099 Data	APZDL001	67502220
Import Data	APZUX001	67960862
Manual Check Process	APZDJ001	67502120
Options List	APZRU001	67698707
Options Setup	APZSA001	67174403
Payment History Report	APZRT001	67108892
Post AP Batches	CIZUF001	67502140
Print Checks	APZRA001	67502110
Process Period End	APZPA001	67502170
Purchase Activity Report	APZRK001	67698699
Purge AP Data	APZDH001	67502150
Recalculate History	APZTM001	67960863
Recurring Voucher List	APZRS001	67698706
Recurring Voucher Maintenance	APZMD001	67174402
Reverse Import	CIZUX001	67960843
Set Up Payment Method	APZMF001	67174408
Vendor 1099 History Report	APZRN001	67698715
Vendor Class List	APZRR001	67698705
Vendor Class Maintenance	APZMB001	67174404

Menu Item	Program Name	Task ID
Vendor Class Purch History Report	APZIB001	67305479
Vendor List	APZRB001	67698689
Vendor Maintenance	APZMA001	67174401
Vendor Payment Inquiry by Vendor	APZIE001	67305480
Vendor Payment Process	APZDJ001	67502100
Vendor Payment History Report	APZRM001	67698700
Vendor Purchase Analysis Report	APZRI001	67698696
Vendor Purchase History Report	APZIB001	67305478
Vendor Status Inquiry	APZIH001	67305477
Vendor Trial Balance Report	APZRG001	67698712
Vendor Trial Balance Report (MC)	APZRG001	67698713
View / Edit Vouchers	APZDA001	67502190
Voucher Inquiry by Vendor	APZIC001	67305475
Voucher Process	APZDJ001	67502090
Accounts Receivable		
Age Customer Accounts	ARZTJ001	84279496
Aged Receivables Report	ARZRF001	84479240
Aged Receivables Report (MC)	ARZRF001	84479244
Analysis Report	ARZRN001	84479293
Apply Payments and Memos Batch	ARZTL001	84220270
Cash Expectations Report	ARZRK001	84475907
Cash Receipts Batch	ARZTL001	84220260
Commission Batch	ARZTL001	84220280
Commission Class List	ARZLE001	84604778
Commission Class Maintenance	ARZME001	83887079
Commission Plan List	ARZLF001	84604780
Commission Plan Maintenance	ARZMH001	83957624
Commission Report	ARZRP001	84479295

Menu Item	Program Name	Task ID
Custom Field Maintenance	CIZMD001	83951620
Customer Class History Inquiry	ARZTR001	84082950
Customer Class List	ARZLA001	84604774
Customer Class Maintenance	ARZMB001	83887078
Customer History Inquiry	ARZTR001	84082940
Customer List	ARZRA001	84479264
Customer Maintenance	ARZMA001	83952612
Customer Payment Activity	ARZRJ001	84479292
Customer Sales Analysis Report	ARZRL001	84479269
Customer Statements	ARZRE001	84479259
Customer Status Inquiry	ARZQA001	84082790
Customer Trial Balance Report	ARZRG001	84479249
Customer Trial Balance Report (MC)	ARZRG001	84479254
Finance Charge Batch	ARZTL001	84220290
Import Data	ARZUX001	84220780
Invoice Batch	ARZTL001	84220780
Invoice Print - Multiple Batches	ARZTC001	84280227
Invoice Reprint	ARZTC001	84280297
Invoice Summary Inquiry by Customer	ARZQD001	84082890
Options List	ARZLC001	84604440
Options Maintenance	ARZMG001	83951917
Payment Summary Inquiry by Customer	ARZTT001	84082910
Post Batches	CIZUF001	84738248
Process Period End	ARZPA001	84672517
Purge AR Data	ARZDL001	84342629
Recalculate History	ARZTM001	84738252
Recurring Invoice List	ARZLB001	84604776
Recurring Invoice Maintenance	ARZMC001	83951676

Menu Item	Program Name	Task ID
Reverse Import	CIZUX001	84738269
Sales Activity Report	ARZRI001	84475906
Sales Territory List	ARZLG001	84604775
Sales Territory Maintenance	ARZMF001	83952614
Salesperson History Inquiry	ARZTU001	84082930
Salesperson List	ARZLD001	84604779
Salesperson Maintenance	ARZMD001	83957623
Salesperson Sales Analysis Report	ARZRM001	84479274
View / Edit Invoices	ARZDA003	84279346
Advanced Allocations		
Options List	AAZLA001	403308554
Process Advanced Allocations	AAZAA001	403046401
Set Up Options	AAZSA001	402718721
Advanced Consolidations		
Consolidations List	ACZLA001	420085790
Delete Consolidation Data by Company	ACZUF001	420282573
Delete Consolidation Data by Period	ACZUG001	420282574
Elimination Group List	ACZLC001	420085962
Import Subsidiary Data	ACZUA001	420282569
Maintain Consolidations	ACZMA001	419495956
Maintain Elimination Groups	ACZMC001	419496138
Maintain Rollups	ACZMB001	419496137
Options List	ACZLS001	420085770
Process Advanced Consolidations	ACZAA001	419954698
Rollup List	ACZLB001	420085961
Set Up Options	ACZSA001	419495937
Cash Management		
AP Check Conversion	CMZPD001	151847012

Menu Item	Program Name	Task ID
Bank Account History Inquiry	CMZQD001	151191554
Bank Account Inquiry	CMZQB001	151191553
Bank Account Status Inquiry	CMZQC001	151191555
Bank Account Trans Summary Inquiry	CMZQE001	151192100
Bank Activity Report	CMZRD001	151585068
Bank Statement Inquiry	CMZQF001	151192000
Bank Transaction Batch	CMZTL001	151323720
Cash Trend Analysis Report	CMZRE001	151585118
Daily Cash Balance Report	CMZRB001	151584918
Daily Cash Flow Projection	CMZRC001	151584968
Deposit Generation Batch	CMZTL001	151323710
Future Cash Flow List	CMZLE001	151650307
Future Cash Flow Maintenance	CMZME001	151060482
Options List	CMZLD001	151650306
Options Setup	CMZSA001	151060481
Periodic Cash Flow Projection	CMZRA001	151584868
Post CM Batches	CIZUF001	151388360
Process Period End	CMZPA001	151781476
Purge CM Data	CMZPB001	151388310
Reconciliation Batch	CMZTL001	151323700
Common Information		
Bank Account List	CIZLV001	34144262
Bank Account Maintenance	CIZMV001	33620068
Bank List	CIZLA001	34209942
Bank Setup	CIZMA001	33620168
Business Form Setup	CIZMO001	33619979
Business Form List	CIZLO001	34210132
Comment Maintenance (EXE)	CIZND001	33620000

Menu Item	Program Name	Task ID
Comments List	CIZLI001	34210172
Company Tax Code List	CIZLM001	34210182
Country and State Setup	CIZMK001	33619976
FOB ID Maintenance	CIZNG001	33620218
FOB List	CIZOG001	34210192
Item History Report	CIZRB001	34144258
Item List	IMZRL001	34209793
Maintain Company Tax Information	CIZNF001	33627168
Maintain Non-Stock Item Classes	IMZMI001	33619988
Maintain Non-Stock Items	IMZMR001	33619970
Memos List	CIZLQ001	34210152
Non-Stock Item Class List	IMZLI001	34210142
Options List	CIZLB001	34210122
Options Setup	CIZSA001	33619980
Payment Terms List	CIZLH001	34209832
Payment Terms Setup	CIZMH001	33619974
Postal Code Setup	CIZML001	33619977
Processing Cycle List	CIZLK001	34210112
Processing Cycle Setup	CIZMI001	33619975
Purge Item History	CIZTB001	33947650
Purge Sales Tax History	CIZTC001	33947651
Reason Code List	CIZLJ001	34210102
Reason Code Setup	CIZMJ001	33619985
Sales Tax Class List	CIZLE001	34209802
Sales Tax Class Setup	CIZME001	33619971
Sales Tax Code List	CIZLF001	34209812
Sales Tax Code Setup	CIZMF001	33619972
Sales Tax Recalculate History	CIZTM001	34406900

Menu Item	Program Name	Task ID
Sales Tax Report - AP	CIZRD001	34144259
Sales Tax Report - AR	CIZRD001	34144278
Sales Tax Schedule List	CIZLG001	34209822
Sales Tax Schedule Setup	CIZMG001	33619983
Shipping Method List	CIZLN001	34210092
Shipping Method Setup	CIZMN001	33619981
Tender Type List	CIZLX001	34209992
Tender Type Setup	CIZMX001	33620118
Units of Measure List	CIZLL001	34210162
Unit of Measure Setup	CIZMM001	33619978
Customizer		
Export Form Customizations	CZEXPORT	386269185
Form Customizations List	CZZRA001	386531338
Import Form Customizations	CZIMPORT	386269186
Manage Form Customizations	CZMANAGE	386269187
General Ledger		
Account Categories List	GLZLG001	50994030
Account Group List	GLZRR001	50994030
Account Group Setup	GLZMD001	50403224
Account History Inquiry	GLZIE001	50530276
Account List	GLZRB001	50929482
Account Maintenance	GLZMA001	50399184
Account Segment Setup	GLZME001	50403234
Account Segment Value List	GLZRS001	50995198
Account Shortcuts List	GLZLO001	50988018
Account Structure List	GLZRU001	50995218
Account Structure Setup (Menu)	GLZMI001	50403274
Activity Report	GLZRG002	50929697

Menu Item	Program Name	Task ID
Allocation Journal List	GLZRX001	50994048
Allocation Maintenance	GLZDA001	50401194
Allocation Process	GLZDH001	50663408
Analysis	GLZRI001	50928512
Budget and History Report	GLZRD001	50928522
Budget Revision Maintenance	GLZDG001	50663398
Create Accounts	GLZUE001	51183696
Custom Field Value Setup	CIZMD001	50397224
Delete Accounts	GLZUG001	51183736
Export AC Data	GLZUH001	51183746
Export Data	GLZDD001	51183636
Financial Reports	GLZRF001	50928517
Financial Report Group List	GLZRZ001	50994060
Financial Report Group Maintenance	GLZMM001	50399185
Financial Reports List	GLZRY001	50994059
Financial Report Maintenance	GLZML001	50399422
Fiscal Year List	GLZRQ001	50995178
Fiscal Year Maintenance	GLZMC001	50403214
General Ledger Worksheet	GLZRC001	50929502
Import Data	GLZRA001	51183646
Journals List	GLZRT001	50995208
Journal Maintenance	GLZMF001	50399407
Journal Report	GLZRH001	50928537
Journal Transaction Process	GLZDH001	50397194
Maintain Account Shortcuts	GLZMO001	50398194
Maintain Budgets	GLZMT001	50398244
Maintain Natural Accounts	GLZMP001	50398204
Maintain Reference Codes	GLZMS001	50398224

Menu Item	Program Name	Task ID
Maintain Reference Groups	GLZMR001	50398214
Natural Account List	GLZLP001	50988028
Options List	GLZRP001	50995168
Options Setup	GLZMB001	50403204
Post GL Batches	CIZUF001	50724874
Process Period End	GLZPA001	51125090
Purge GL Data	GLZTD001	51192656
Recurring Journal List	GLZRW001	50994049
Recurring Journal Maintenance	GLZDB001	50401204
Reference Code List	GLZLS001	50988048
Reference Group List	GLZLR001	50988038
Renumber Accounts	GLZUF001	51183726
Reverse Import	CIZUX001	51184850
Set Up Account Categories	GLZMQ001	50399186
Target Company List	GLZRK001	50995228
Target Company Maintenance	GLZMN001	50400184
Transaction Report	GLZRG001	50921479
Transactions Inquiry	GLZIA001	50533266
Trial Balance Report	GLZRE001	50929522
Inventory Management		
Bin Labels	IMZRT001	118030526
Bins List	IMZLN001	118096002
Buyer List	IMZLB001	185205886
Buyer Maintenance	IMZMA001	117506348
Calculate Projected Demand	IMZDD001	117833798
Calculate Replenishment Parameters	IMZDD002	117833808
Commodity Codes List	IMZLO001	118095922
Cost Inquiry	IMZQA001	117637130

Menu Item	Program Name	Task ID
Cost Tier Adjustment Batch	IMZDH001	117833778
Customer Group Pricing List	IMZLU005	118096092
Customer Item CPL	IMZLU004	118096082
Customer Item List	IMZLV001	118096142
Customer PPG CPL	IMZLU009	118096112
Customer Price Group Maintenance	IMZMU003	117506278
Customer Price Group Pricing	IMZMU005	117506308
Customer Price Group List	IMZLU002	118096052
Demand Adjustment	IMZDD006	117833848
Demand Formulas List	IMZLC001	118095912
Freight Class List	IMZLP001	118095932
Global Inventory Change	IMZUD002	117834058
Global Item Change	IMZUD001	117834048
Import	IMZUA001	118292490
Inventory Analysis Report	IMZRG001	118030386
Inventory Cost Report	IMZRE001	118030406
Inventory List	IMZLT001	118095982
Inventory Performance List	IMZRN001	118030476
Inventory Ranks List	IMZLH001	118095962
Inventory Status Inquiry	IMZQK001	117637280
Inventory Transaction Inquiry	IMZQF001	117637210
Inventory Transaction Report	IMZRM001	118030446
Item Classes List	IMZLI001	118095952
Item History Inquiry	IMZQE001	117637190
Item List	IMZLR001	118096022
Landed Costs List	IMZLQ001	118095942
Lead Time Exception Report	IMZRP001	118030486
Lead Time Formulas Lists	IMZLE001	118095902

Menu Item	Program Name	Task ID
Lot Serial Adjustment	IMZUB001	117833888
Lot Serial History Report	IMZRI001	118030496
Lot Summary Inquiry	IMZQG001	117637150
Low Cost Report	IMZRO001	118030436
Maintain Contract Pricing	IMZMU004	117506328
Maintain Customer Items	IMZMV001	117506338
Maintain Inventory	IMZMT001	117506238
Maintain Item Classes	IMZMI001	117506138
Maintain Items	IMZMR001	117516178
Maintain Price Sheet	IMZMU001	117506298
Maintain Vendor Item	IMZMG001	117506258
Move Stock	IMZDF001	117833838
Negative On-Hand Qty Report	IMZRH001	118030456
On Hand Lot/Serial Report	IMZRJ001	118030426
Options List	IMZLM001	118096072
Past Period Valuation Report	IMZRF001	118030396
PI Batch	IMZDH001	117833758
Post IM Batches	CIZUF001	117833988
PPL History Inquiry	IMZQC001	117637180
Price Inquiry	IMZQB001	117637170
Price Sheet List	IMZLU001	118096042
Print Suggested Orders	IMZDD003	117834038
Process Period End	IMZDI001	117833908
Process Replenishment Orders	IMZDD007	117833998
Product Group Pricing List	IMZLU008	118096102
Product Price Group Maintenance	IMZMU002	117506288
Product Price Group Pricing	IMZMU005	117506318
Product Price Group List	IMZLU007	118096062

Menu Item	Program Name	Task ID
Purchase Product Line List	IMZLJ001	118096012
Purge Data	IMZUC001	118292500
Safety Stock Formula Lists	IMZLD001	118095882
Sales Product Lines List	IMZLF001	118095892
Serial Summary Inquiry	IMZQH001	117637140
Set Up Bins	IMZMN001	117506268
Set Up Commodity Codes	IMZMO001	117506108
Set Up Demand Formula	IMZMC001	117506098
Set Up Freight Class	IMZMP001	117506118
Set Up Inventory Ranks	IMZMH001	117506088
Set Up Landed Cost	IMZMQ001	117506128
Set Up Lead Time Formula	IMZME001	117506078
Set Up Purchase Product Line	IMZMJ001	117506158
Set Up Safety Stock Formula	IMZMD001	117506058
Set Up Sales Product Line	IMZMF001	117506068
Set Up Warehouses	IMZMK001	117506168
Setup Custom Field Values	CIZMD001	117506358
Setup Options	IMZMM001	117506148
Special Order Source Report	IMZDD005	118030516
Stock Status Inquiry	IMZQJ001	117637200
Stock Status Report	IMZRK001	118030416
Transaction Entry Batch	INZDH001	117833768
Unusual Usage Report	IMZRU001	118030506
Vendor Item List	IMZLG001	118096032
Warehouse List	IMZLK001	118095972
Warehouse Replenishment Maintenance	INZMS001	117506228
Multicurrency Management		
Accounts Payable Revaluation	MCZDB001	168165378

Menu Item	Program Name	Task ID
Accounts Receivable Revaluation	MCZDC001	168165377
Currency List	MCZLA001	168427524
Currency Setup	MCZMA001	167837698
Exchange Rate List	MCZLB001	168427521
Exchange Rate Maintenance	MCZMB001	167837699
GL Account Revaluation	MCZDA001	168165379
GL Account Trial Balance Report	GLZRL001	168361994
Options List	MCZLC001	168427522
Options Setup	MCZSA001	167837697
Process Period End	MCZPA001	168558593
Purge MC Data	MCZUE001	168296449
Project Accounting		
Options List	PAZLA001	319422564
Options Setup	PAZSA001	318832740
Purchase Order		
Back Ordered Purchase Orders Report	POZRL001	185139850
Blanket Order Maintenance	POZMC001	184615212
Blanket Order Report	POZRK001	185139800
Buyer List	IMZLB001	185205886
Buyer Maintenance	IMZMA001	184616012
Change Order Report	POZRH001	185139650
Custom Field Maintenance	CIZMD001	184615112
Department List	POZLB001	185204936
Department Maintenance	POZMB001	184615062
Expected Delivery Report	POZRG001	185139600
Open Purchase Order Item Report	POZRB001	185204836
Options List	POZLG001	185204836
Options Setup	POZMG001	184615012

Menu Item	Program Name	Task ID
Post PO Batches	POZUF001	185401544
Print Receiving Tickets	POZRI001	185139700
Print Requisitions	POZTB001	184942943
Process Period End	POZDK001	184943292
Purchase Analysis	POZRF001	185139550
Purchase Order Entry	POZDA001	184942742
Purchase Order Inquiry	POZQA001	184746085
Purchase Order Issue	POZTC001	184942692
Purchase Order Line Summary	POZQB001	186139400
Purchase Price Variance Report	POZRC001	185139400
Purchases Clearing Report	POZRJ001	185139750
Purchases Journal	POZRD001	185139500
Purchase Order Summary	POZQA001	184746084
Purge	POZDH001	184942992
Receipt of Goods Batch	POZTL001	184943092
Receipt Line Summary Inquiry DA	POZQI001	184746534
Receipt Summary Inquiry DA	POZQF001	184746484
Requisition Entry	POZDE001	184942925
Requisition Line Summary	POZQE001	184746234
Requisition Summary	POZQD001	184746184
Return Line Summary DA	POZQH001	184746684
Return Summary DA	POZQG001	184746634
Returns Batch Processing	POZTL001	184943142
Status Report	POZRA001	185139300
Tolerance Code Maintenance	POZMA001	184615162
Tolerance Code List	POZLA001	185204986
Vendor - Item Cross Reference List	IMZLA001	185205836
Vendor - Item Cross Reference Maint	IMZMB001	184616062

Menu Item	Program Name	Task ID
View Vendor Returns	POZDJ001	184943392
View /Edit Change Orders	POZDL001	184943442
View /Edit Receiver	POZDG001	184943342
Voucher Batch	POZTL001	184942792
Sales Order		
Aged Orders	SOZRX001	134808102
BackOrders	SOZRA001	134807902
Blanket Order Report	SOZRC001	134807752
Cancel Picks	SOZDX001	134611844
Change Order Report	SOZRV001	134808452
Change Order Summary	SOZQA001	134414436
Confirm Picks	SOZDG001	134611244
Create Pick List	SOZDD001	134611044
Customer Returns Batch	SOZTB001	134630000
Custom Field Maintenance	CIZMD001	134283514
Enter Quotes	SOZDB001	134611164
Entry	SOZDJ001	134611094
Expected Shipments	SOZ4H001	134808002
Generate Shipments Batch	SOZTB001	134620000
Maintain Blankets	SOZDA001	134611154
Open Order Items Report	SOZRN001	134807702
Options List	SOZLE001	134873243
Post SO Batches	CIZUF001	134611394
Print/ Acknowledge	SOZTC001	134611694
Process Period End	SOZDO001	134611494
Projected Sales	SOZRJ001	134808352
Quote Expiration Report	SOZRI001	134808052
Quote Summary	SOZQB001	134414586

Menu Item	Program Name	Task ID
Reprint Pick List	SOZDU001	134611594
Return Summary	SOZQM001	134414836
Return Line Summary	SOZQN001	134414886
Sales Analysis Report	SOZRK001	134808152
Sales Order History	SOZRU001	134807910
Sales Order Line Summary	SOZQL001	134414536
Sales Order Profitability Report	SOZRQ001	134808302
Sales Order Purge Process	SOZDM001	134611444
Sales Order Status Report	SOZRM001	134808202
Sales Order Summary	SOZQK001	134414486
Set Up Sources	SOZMF001	134283414
Setup Options	SOZME001	134283464
Shipment Line Summary	SOZQI001	134414736
Shipment Summary	SOZQH001	134414686
Source List	SOZLF001	134873238
View Change Orders	SOZDI001	134611219
View Customer Returns	SOZDK001	134611894
View Shipments	SOZDR001	134611744
System Manager		
AC Admin Maintenance	SMZUI001	16842972
Change AC Admin Password	SMZUJ001	16842762
Change Business Date	SMZMG001	17631534
Company List	SMZRC001	17432578
Company Maintenance	SMZMC001	16842761
Company Profile	SMZRJ001	17374075
Custom Report Maintenance	SMZMH001	16843052
Deferred Printing	SMZTH001	17629300
Launch Pad Customization	SOTA.CUS	16842760

Menu Item	Program Name	Task ID
Maintenance Audit Log	SMZRL001	17374077
Options Maintenance	SMZSA001	16842932
Order Business Forms	SMZMF001	17631524
Purge Activity Log	SMZTF001	16842952
Register Modules	SMZME001	17170547
Registered Modules Report	SMZRE001	17374071
System Activity Log	SMZRI001	17374073
System Status	SMZIA001	17631529
User Group List	SMZRB001	17432579
User Group Maintenance	SMZMB001	16842962
User Group Permission List	SMZRM001	17374078
User List	SMZRA001	17432577
User Maintenance	SMZMA001	16842757
User Preferences	SMZSB001	16842942

Appendix G: Silent mode installation

The Acuity Client installer includes scripting ability to facilitate a silent mode installation. This feature allows installation of the Acuity client programs without user intervention. This section explains the switches that you can use and the options that you can select within the scripting file.

Creating the script

To create the script file, execute the `Acuity\Setup.exe` file with the `-r` switch, then proceed through the installation prompts.

EXAMPLE

C:\Acuity\Setup -r

This creates a file in the default system folder (normally Windows) named `Setup.iss`. You can rename and move this file since it can be referenced specifically using the `-f1` switch mentioned below.

Executing the script

To execute the installation using the silent mode feature, the `-s` switch must pass to the setup executable. To execute the silent mode script from Microsoft SMS, the `-SMS` switch must also pass to the setup program. For a standard silent mode installation, we suggest providing the path to the `.iss` file and including a log file as shown in the following:

```
Setup -s -f1C:\<mydir>\<myfile>.iss  
-f2C:\<mydir>\<myfile>.log
```

- `-f1` is the full path to the `.iss` (script) file
- `-f2` is the full path to a log file (optional)

Following is an example of the script:

```
C:\Acuity\Setup -s -f1C:\Acuity\Setup.iss  
-f2C:\Acuity\Inst.log
```

Script definition

The following table defines the options available in the .iss file:

[InstallShield Silent] Version=v5.00.000 File=Response File
[File Transfer] OverwriteReadOnly=NoToAll
[DlgOrder] Dlg0=SdLicense-0 Count=5 Dlg1=AskOptions-0 Dlg2=SdComponentDialog-0 Dlg3=AskYesNo-0 Dlg4=SdFinish-0
[SdLicense-0] Result=1
[AskOptions-0] Result=1 Sel-0=1 Sel-1=0
[SdComponentDialog-0] szDir=C:\Acuity Common Information-type=string Common Information-count=2 Common Information-0=Common Information\Reports Common Information-1=Common Information\CI IM Reports System Manager-type=string System Manager-count=1 System Manager-0=System Manager Reports

```

General Ledger-type=string
General Ledger-count=3
General Ledger-0=General Ledger\Reports
General Ledger-1=General Ledger\Imports
General Ledger-2=General Ledger\Documents
Accounts Payable-type=string
Accounts Payable-count=3
Accounts Payable-0=Accounts Payable\Reports
Accounts Payable-1=Accounts Payable\Imports
Accounts Payable-2=Accounts Payable\Documents
Accounts Receivable-type=string
Accounts Receivable-count=3
Accounts Receivable-0=Accounts Receivable\Reports
Accounts Receivable-1=Accounts Receivable\Imports
Accounts Receivable-2=Accounts Receivable\Documents
MultiCurrency Management-type=string
MultiCurrency Management-count=1
MultiCurrency Management-0=MultiCurrency Management\Reports
Cash Management-type=string
Cash Management-count=1
Cash Management-0=Cash Management\Reports
Purchase Order-type=string
Purchase Order-count=2
Purchase Order-0=Purchase Order\Reports
Purchase Order-1=Purchase Order\Documents
Advanced Allocations-type=string
Advanced Allocations-count=1
Advanced Allocations-0=Advanced Allocations\Reports
Acuity Customizer-type=string
Acuity Customizer-count=1
Acuity Customizer-0=Acuity Customizer\Reports
Inventory Management-type=string
Inventory Management-count=2
Inventory Management-0=Inventory Management\Reports
Inventory Management-1=Inventory Management\Documents

```

Sales Order-type=string
 Sales Order-count=2
 Sales Order-0=Sales Order\Reports
 Sales Order-1=Sales Order\Documents
 Advanced Consolidations-type=string
 Advanced Consolidations-count=3
 Advanced Consolidations-0=Advanced Consolidations\Reports
 Advanced Consolidations-1=Advanced Consolidations\Drill Down Report
 Advanced Consolidations-2=Advanced Consolidations\Import Files
 Component-type=string
 Component-count=36
 Component-0=Windows System
 Component-1=System Manager Main
 Component-2=Altnt
 Component-3=Alt95
 Component-4=Crystal Non Self-Register
 Component-5=Help
 Component-6=Main
 Component-7=Common Information
 Component-8=System Manager
 Component-9=General Ledger
 Component-10=Accounts Payable
 Component-11=Accounts Receivable
 Component-12=MultiCurrency Management
 Component-13=Cash Management
 Component-14=Purchase Order
 Component-15=Advanced Allocations
 Component-16=Dao35
 Component-17=Ct13d95
 Component-18=Ct13dnt
 Component-19=Acuity Customizer
 Component-20=ODBC
 Component-21=ODBC Common
 Component-22=Inventory Management
 Component-23= Sales Order

Component-24=VBA Non Self-Register Component-25=WksClient Component-26=Sotactls Component-27=Advanced Consolidations Component-28=TLA Author 97 UD Component-29=TLA View 97 UD Component-30=TLA Author Help UD Component-31=TL Analyst 97 USNV Component-32=New Report 97 UD Component-33=SysDAO30_S Component-34=SysDAO30_SRS Component-35=DAO30_SRS Result=1
[AskYesNo-0] Result=1
[Application] Name=Acuity Financials Version=0.0 Company=State Of The Art Lang=0009
[SdFinish-0] Result=1 bOpt1=0 bOpt2=0

