Solid Edge

Installation and Licensing

Publication Number
SESETUP 18

Proprietary and Restricted Rights Notices

Copyright

©2005 UGS Corp. All Rights Reserved

Permission is granted to make and distribute complete and unmodified copies of this document, provided the copyright notice is preserved on each copy.

This software and related documentation are proprietary to UGS Corp. LIMITATIONS TO U.S. GOVERNMENT RIGHTS. UNPUBLISHED - RIGHTS RESERVED UNDER THE COPYRIGHT LAWS OF THE UNITED STATES. This computer software and related computer software documentation have been developed exclusively at private expense and are provided subject to the following rights: If this computer software and computer software documentation qualify as "commercial items" (as that term is defined in FAR 2.101), their use, duplication or disclosure by the U.S. Government is subject to the protections and restrictions as set forth in the UGS Corp. commercial license for the software and/or documentation, as prescribed in FAR 12.212 and FAR 27.405(b)(2)(i) (for civilian agencies) and in DFARS 227.7202-1(a) and DFARS 227.7202-3(a) (for the Department of Defense), or any successor or similar regulation, as applicable or as amended from time to time. If this computer software and computer documentation do not qualify as "commercial items," then they are "restricted computer software" and are provided with "restrictive rights," and their use, duplication or disclosure by the U.S. Government is subject to the protections and restrictions as set forth in FAR 27.404(b) and FAR 52-227-14 (for civilian agencies), and DFARS 227.7203-5(c) and DFARS 252.227-7014 (for the Department of Defense), or any successor or similar regulation, as applicable or as amended from time to time. UGS Corp., 5400 Legacy Drive, Plano, Texas 75024.

———————————————————————-

All trademarks and registered trademarks mentioned herein are the property of their respective owners.

©2005 UGS Corp.
All Rights Reserved.
Produced in the United States of America.

Contents

System Requirements 1-1

Minimum System Configuration 1- 1
Recommended System Configuration 1- 1
Recommended Graphics Cards 1- 1

Installing and Uninstalling Solid Edge 2-1

Installing with Setup 2- 1
Installing Silently 2- 2
Uninstalling 2- 3

Licensing Options 3-1

Dongles 3- 1
Node-Locked (Standalone) Configuration 3- 1
Floating Configuration 3- 2
License File 3- 2
Emergency Licensing 3- 2
Evaluation Licensing 3- 2
Web Retrieval 3- 2

Configuring Node-Locked Licensing 4-1

Loading Solid Edge Node-Locked License 4- 1

Configuring Floating Licensing 5-1

Identifying a License Server 5- 1
Installing the Sentinel Driver 5- 1
Loading Solid Edge for Floating Licenses 5- 3

Configuring Academic Licensing 6-1

Contact UGS 7-1

Chapter

1 System Requirements

Minimum System Configuration

- Intel Pentium, Intel Xeon, AMD Athlon, or AMD Opteron processor-based PC
- Windows 2000 or Windows XP Professional
- 512 MB RAM
- 1.1 GB of disk space for installation
- Minimum Resolution: 1,024x768, 65K colors
- CD-ROM (local or network) for installation

Recommended System Configuration

- Intel Xeon or AMD Opteron processor-based PC
- Windows XP Professional
- 1 GB or more RAM
- True Color (32 bit) or 16 million colors (24 bit)
- Screen resolution of 1280x1024

Recommended Graphics Cards

You can find a list of graphics cards recommended for use with Solid Edge at http://www.solidedge.com/graphics/default.htm.

Chapter

2 *Installing and Uninstalling Solid Edge*

To install Solid Edge, use any of the following methods:


- Insert the Solid Edge CD-ROM in the CD drive. If autorun is enabled, Solid Edge setup begins.
- In Windows Explorer, double-click the file (CD drive):\setup.exe.
- Use the Run command on the Start menu to run (CD drive):\setup.exe.

Keep these things in mind when installing Solid Edge:

- For information on addressing error messages you may encounter while installing Solid Edge, contact the Global Technical Access Center (GTAC) for product support at 800-955-0000, option 2 for Technical Software Support, option 2 for Solid Edge, option 3 for Solid Edge Installation & Licensing Issues.
- You must install FLEXlm and the Sentinel driver separately for floating licensing to work properly. If your node-locked installation requires a dongle, the Sentinel driver is automatically installed. If for some reason the Sentinel driver does not install properly, the Sentinel driver can be installed from the Solid Edge CD. The Sentinel driver is located in the Sentinel folder on the Solid Edge CD. Double-click sentinel.exe and follow the installation instructions to complete the installation of the driver.
- You must load and remove Solid Edge from an account that has Administrator privileges. Solid Edge will run under User, Administrator, or Guest privileges.
- Solid Edge always installs system files on the drive that contains the Windows operating system, regardless of the drive you specify for the installation.

Installing with Setup

Use the setup window to set installation options, including template files for default measurement units and installation directory. If you want, you can also specify a license file and/or options file.



If you run the setup program when Solid Edge is already installed, you have three options:

- Modify the existing installation of Solid Edge. Choose this option to install or uninstall template files or add-ins.
- Repair the existing installation of Solid Edge. Choose this option to repair problems like missing files and invalid shortcuts.
- Remove the existing installation of Solid Edge. Choose this option to remove Solid Edge from the computer.

Installing Silently

You can silently install Solid Edge with the following command:

Enclose paths names in quotes if they contain spaces.

C:\>msiexec /i "D:\CM_SETUP\DISK1\Solid Edge V18.msi" MYTEMPLATE=2 USERFILESPECXML="K:\temp\My Docs\Options.xml" USERFILESPEC="K:\temp\My Docs\selicense.dat" KERNELTYPE="P4" INSTALLDIR="C:\Program Files\Silent Solid Edge\" /qn+ /l*v k:\temp\mysilentsetup.log

- The string "D:\CM_SETUP\DISK1\Solid Edge V18.msi" represents the fully qualified path to the Solid Edge MSI file.

- The MSI Property MYTEMPLATE indicates which type template files are to be installed. The integer 1 is for Metric and the integer 2 is for English. Ignoring this property defaults the installation to Metric template files.

- The MSI Property USERFILESPECXML allows the user to optionally provide the optional installation of an SE Admin file. The user should supply a fully qualified path and filename. This file will be copied to the Solid Edge Program folder and processed at the end of the setup.

- The MSI Property USERFILESPEC allows the user to optionally provide a license file that setup will copy to the Solid Edge Program folder at the end of the setup.

- The MSI Property KERNELTYPE is used to install either the P3 or P4 Parasolid Kernel.

- The MSI Property INSTALLDIR is used to specify the installation folder for Solid Edge.

- The argument "/qn+" instructs the windows installer to provide NO user interface and alert the user at the completion of the setup with a dialog box. Refer to the Windows help system for further information about Windows Installer arguments. Leaving this argument off the command line will display the setup user interface with selections made and fields provided.

- The argument "/l*v" tells the windows installer to create a log file of important messages, warnings and errors and write it to the location provided, in this example, k:\temp\mysilentsetup.log.

Do not silently install Solid Edge if you use Standard Parts or Web Parts. These components require the .NET framework, and the .NET framework is installed only when you run setup.exe.



Setup no longer supports the use of the ADDLOCAL property

Uninstalling

Use the Add/Remove Programs utility (located in the operating system Control Panel) to remove Solid Edge. Select Solid Edge from the list of installed products, and click Remove.

For more information on installation and uninstallation of Solid Edge and product enhancements, see the readme.txt file in the product folder.


Chapter

3 *Licensing Options*

When you purchase Solid Edge, you can choose between two licensing options. With node-locked licensing, a license is locked to a specific hardware key, or dongle. With floating licensing, the FLEXlm software manages licenses for use on a network, and a system administrator typically configures the dongle-equipped license server.

Dongles

A hardware key, or dongle, is a small device that plugs into your computer and works with the software to provide licensing. The dongle plugs into the USB or parallel port on the back of your computer. If you have a parallel dongle, you can continue to utilize the port by plugging another parallel device (a printer, for example) into the rear of the dongle.



With node-locked licensing, if your license requires a dongle, it must be installed on your computer. With floating licensing, the license server must have a server dongle installed.

You must install the Sentinel driver separately for floating licensing to work properly. If your node-locked installation requires a dongle, the Sentinel driver is automatically installed. If for some reason the Sentinel driver does not install properly, the Sentinel driver can be installed from the Solid Edge CD. The Sentinel driver is located in the Sentinel folder on the Solid Edge CD. Double-click sentinel.exe and follow the installation instructions to complete the installation of the driver.

Node-Locked (Standalone) Configuration

If your license requires a dongle, install it in the USB or parallel port of your computer. The Solid Edge License Utility will validate the dongle and license file.

Floating Configuration

Floating represents the ability to have multiple clients accessing the software through a license server. This means that you can install Solid Edge on as many computers as needed on your network, and then have users check out licenses from a pool, not to exceed the total number of purchased seats.

The license server can be any computer on your network that is running a 32-bit Windows operating system. The only limitation is that the machine selected as the server must be available for the users to access whenever needed. The license file used in a floating configuration establishes the location of the license server and the number of available licenses. The license server must have a server dongle installed. The FLEXlm utilities that are necessary to simplify the process and to make full use of your Solid Edge license are delivered on your Solid Edge product CD.

Floating licenses should not be shared across country borders. It is strongly recommended that the floating licenses only be shared across a single LAN to minimize any additional points of network interruption.

License File

Both the node-locked and floating options require a license file that is customized to your installation. You will not be able to run your Solid Edge product without completing the licensing phase of the product installation. An electronic copy of your Solid Edge license file (SELicense.dat) has been emailed to the point of contact on record for your company. If you cannot locate this file, you can download it from the UGS Support web page at *http://www.ugs.com/Support/LicenseManagement*, log in using your WebKey account, and enter the Sold-To / Install ID number you want to download a license for.

Emergency Licensing

Emergency standalone licensing is available in a situation where Solid Edge will not run because of problems with the current license file or hardware key. An emergency license file is valid for 7 days. To retrieve an emergency license, go to http://www.ugs.com/Support/LicenseManagement, log in using your WebKey account, and enter the Sold-To/Install ID number you want to create an emergency license for.

Evaluation Licensing

For a Solid Edge evaluation license, please contact your Solid Edge reseller.

Web Retrieval

on the web at *http://www.ugs.com/Support/LicenseManagement*, log in using your WebKey account, and enter the Sold-To / Install ID number you want to download a license for.

Chapter

4 Configuring Node-Locked Licensing

To use a node-locked license, you must install Solid Edge and complete the licensing phase after installation.

The Sentinel driver is automatically installed for your node-locked license that requires the use of a dongle. If for some reason the Sentinel driver does not install properly, the Sentinel driver can be installed from the Solid Edge CD. The Sentinel driver is located in the Sentinel folder on the Solid Edge CD. Double-click sentinel.exe and follow the installation instructions to complete the installation of the driver.

Loading Solid Edge Node-Locked License

Install Solid Edge from the product CD-ROM. After CD installation, Solid Edge must be licensed in one of following ways: by using the License File: Browse option on License Utility to navigate to an electronic copy of the Solid Edge license file (SELicense.dat) saved to disk, or by downloading an archived SELicense.dat file and saving it to the Solid Edge V18/Program folder, or by printing out the electronic copy of your Solid Edge license file (SELicense.dat) emailed to the point of contact on record for your company, then using License Utility to enter the 12-character license key(s) to generate a SELicense.dat file.

After installation, if you start Solid Edge with the delivered license file, licensing help is displayed. However, if you have altered or replaced the delivered license file, license validation occurs automatically.

To download a SELicense.dat file:

1. At *http://www.ugs.com/Support/LicenseManagement*, log in using your WebKey username and password.

2. Select the Sold-To ID for which to retrieve licenses, and click Retrieve License Information.

3. Select the Solid Edge license you want to download. If you are given a choice, choose to save the file to disk.

4. Save the Solid Edge license file, SELicense.dat, to a location on disk for use with License Utility or save it direct into the Solid Edge V18/Program folder.

To use License Utility to locate and install your SELicense.dat file:

Step 1: Start the license utility. On the Start menu, click Programs, point to Solid Edge V18, point to Licensing, and click License Utility.


Step 2: On the license Utility, click Browse to locate your license file.



Step 3: On the Open dialog, navigate to the location where you saved the SELicense.dat file, and click Open.

If you do not have a copy of your Solid Edge license file (SELicense.dat) saved to disk, cancel the Open dialog box, follow the instructions for downloading a SELicense.dat described in the previous procedure, and resume this procedure at the beginning of this step.

Step 4: On the License Utility, click Finish to complete licensing.




To use License Utility to generate a valid SELicense.dat:

Step 1: On the License Utility, click License Keys, then click Next.



Step 2: On the License Key Entry dialog, enter your Sold-To ID and WebKey Access Code, select your geographical zone, and enter the license key(s) for the purchased products, and click OK to finish the licensing process.



Assume the license data you receive in your license file is as follows:

FEATURE solidedgeclassic sedemon 18.0 permanent uncounted 33D4CF23D9A8 \ HOSTID=SE_HWKEY=12345

For this example, the node-locked license key is 33D4CF23D9A8. Once you have provided the license key(s), click OK.



Both the Customer Sold-To ID and WebKey Access Code fields are optional. The Customer Sold-To ID is a unique customer identification number used to track products, maintenance, etc. The WebKey Access Code is a unique encrypted password. The information captured in these two fields are the unique identifiers required to create a WebKey Account. A WebKey Account is the single point of account authentication into the tools available on support.ugs.com.

Both the WebKey Access Code and the Customer Sold-To ID can be found in the SELicense.dat file received via e-mail or downloaded from http://www.ugs.com/Support/LicenseManagement. If you have further questions regarding WebKey Accounts, please call 714-952-5444 (US and Canada residents may use 800-955-0000) and select option 2,6. A representative from the GTAC organization will be available to assist you.

Chapter

5 *Configuring Floating Licensing*

Configuring floating licenses involves identifying a license server, installing and configuring FLEXlm, and installing Solid Edge.

Identifying a License Server

The license server is the computer on your network on which the FLEXlm software will reside. The license server can be any computer on your network that is running a 32-bit Windows operating system. The server and the client machines must be running the TCP/IP protocol and must be able to communicate with the server over the network. The license server must have the provided server dongle installed for floating licensing to work.

Installing the Sentinel Driver

The Solid Edge FLEXlm floating license configuration requires the use of a dongle (hardware key). The dongle plugs into the USB or parallel ports on your license server and requires the installation of Rainbow's Sentinel driver. The Sentinel driver is located in the Sentinel folder on the Solid Edge CD. Double-click sentinel.exe and follow the installation instructions to complete the installation of the driver.


The FLEXlm software is included on your Solid Edge product CD. You need to install the FLEXlm software on your licensing server. To install and configure FLEXlm, log in with administrative privileges and follow these steps:

Step 1: Run <CD-ROM>:\ResKit\License Manager\setup.exe, where <CD-ROM> is the drive letter of the CD-ROM drive. Follow the installation prompts. If Solid Edge is not installed on the licensing server, install the drivers from the ResKit folder.

Step 2: Copy your license file (SElicense.dat) to the <DRIVE>:\SEFlex/program folder, where <DRIVE> is the drive letter of the hard drive where you installed FLEXlm.


Step 3: Double-click lmtools.exe in the <DRIVE>:\SEFlex/program folder to display the LMTOOLS dialog box.

Step 4: On the Service/License File tab, specify Configuration Using Services. Ensure that FLEXlm License Manager is highlighted in the list.




Step 5: On the Configure Services tab, specify the location of the License Manager daemon, lmgrd.exe, and the Solid Edge License File, SElicense.dat. Also specify a location for the debug log file.

Step 6: Select the Use Services and Start Server at Power Up options.




Step 7: Click Save Service. If prompted to save the FLEXlm settings, click Yes.



Step 8: On the Start/Stop/Reread tab, click Start Server to start licensing.


Loading Solid Edge for Floating Licenses

Step 1: When installing a floating seat of Solid Edge on a client machine, use the Solid Edge License File Browse option to locate your Solid Edge license file on disk or shared folder.



Step 2: Using the Open dialog, navigate to the SELicense.dat file saved to disk, and click Open.

If you do not have a copy of your Solid Edge license file (SELicense.dat) saved to disk, please follow the instructions for downloading a SELicense.dat or contact the person responsible for managing FLEXlm at your company to determine the license file location.



Once you return to the Solid Edge Install Shield Wizard, click Install. When the installation is complete you are ready to use the product.

Install Solid Edge on each client that will be running Solid Edge. Copy the SElicense.dat file from the server to each client. Place it in the ~\Solid Edge/program folder.

Chapter

6 Configuring Academic Licensing

Using a Solid Edge Academic license involves installing Solid Edge and completing the licensing phase after installation.

You do not need a dongle or a license server to set up a Solid Edge Academic license. The Academic version of Solid Edge works identically to other versions with the following exceptions:

- Whenever a drawing is printed from the Academic version of Solid Edge, it includes the watermark Solid Edge Academic Copy.
- Files saved with an Academic version of Solid Edge can only be opened with an Academic version of Solid Edge. Academic files will not open in other versions.

Step 1: Start the license utility. On the Start menu, click Programs, point to Solid Edge V18, Point to Licensing, and click License Utility.



Step 2: On the license utility, click Browse to locate your license file.

Step 3: On the License Utility, click OK to complete licensing



Chapter

7 Contact UGS

In the United States or Canada, call the Global Technical Access Center:

Step 1: Dial 1–800–955–0000.

Step 2: Press 2 for technical software support.

Step 3: Enter your Sold-to/Server ID, followed by the # sign.

Step 4: Press 2 for Solid Edge.

Step 5: Press 1 for Solid Edge application issues.

Outside the United States or Canada, contact your local Solid Edge reseller.