Asset Status Add-In: Technical Documentation

Nov 9, 2026 · @Andrew Hwang

Overview

Asset Status is a MyGeotab page add-in that lists every active asset, tracked or untracked, in one sortable table whose columns each client chooses and saves.

It is built by Advantage One for its customers. It runs inside MyGeotab as the signed-in user, so it only shows what that user is allowed to see, and it never asks for a separate login.

Item	Detail
Add-in name	Asset Status
Menu location	Activity, menu name "Asset Status"
Data	MyGeotab API (Device, DeviceStatusInfo, Group, User, MaintenanceWorkRequest, AddInData)

Page Layout and Toolbar

The page has four stacked parts: a white header bar with the logos, the page title, three summary tiles, and a card holding the toolbar and the table.

Element	Behavior
Header	Advantage One logo at the upper left, Geotab logo at the upper right. The Advantage One logo is the larger of the two.
Summary tiles	Assets, Tracked and Untracked counts for the active assets in the current group filter.
Search	Matches the asset name, the driver name or the address as you type.

Element	Behavior
Group dropdown	"All groups" or one group. The page respects the MyGeotab group filter when no group is chosen.
Assets dropdown	All assets, Tracked or Untracked.
Last update dropdown	Filters by how long ago the asset last reported (see below). Defaults to Today.
Refresh every	Minutes between automatic reloads of the data. Default 5, allowed 1 to 60. Applies on Enter or when the field loses focus; a value outside the range snaps back.
Columns button	Opens the column panel on the right (see Column Settings). Always the last control.
Data updated	Date and time of the last data load, right-aligned under the refresh field and Columns button.

All six controls sit on one line on wide screens, with search, group and assets on the left and the rest on the right. On narrow screens the toolbar wraps.

Last update filter

Option	Shows assets whose last update was
Today (default)	Today (local time)
Yesterday	The previous calendar day
3 to 5 days	2 to 5 days ago, so no asset falls between Yesterday and this range
5 days or more	Older than that
Never reported	Never; untracked assets are included here
All	Every active asset, whatever its last update

The choice is remembered in the browser, so it survives a page refresh.

Table Features

Which assets are listed. Only active assets appear: an asset is hidden if it is archived, or if its rate plan is Terminated or Suspended. Assets with no rate plan, which are the untracked assets, are listed. Untracked assets are those with no telematics device installed.

Feature	Behavior
Sorting	Every data column shows up and down arrows. Click a header to sort ascending, again for descending. Sorting covers every page, not just the one on screen. Link-only columns (Camera Health, Live Stream) do not sort.
Frozen Asset column	The Asset column always stays on the left when the table scrolls sideways.
Reorder	Drag any column header, except Asset, onto another to move it. Alt+Left and Alt+Right move a focused header. The order is saved.
Resize	Drag the right edge of any header, or focus the edge and press Left or Right (10 px steps). Width ranges from 60 to 600 px. The width is saved when the drag ends.
Default widths	Asset 200 px, Address 280 px, Work Requests 170 px, all others 160 px. Text wider than its column is cut with an ellipsis.
Pagination	50 assets per page. Previous and next arrows sit at the bottom right below the table. A new search or filter returns to page one; a refresh or a sort does not.
Highlighting	A reading below its minimum turns that one cell light yellow (see Column Settings).

Column Catalogue

The Asset column is always shown first. The default columns are Driver, Last Update, Speed and Address. Every other column is switched on in the Columns panel, in the five groups below. A dash means the asset has no reading.

Asset Information

Column	What it shows	Source
Driver	The driver's name. A tracked asset with no driver shows an "Assign Driver" link to the asset's page (new window). Untracked assets are blank.	DeviceStatusInfo.driver, User
Last Update	Date and time of the asset's last report.	DeviceStatusInfo.dateTime
Speed	Current speed in km/h.	DeviceStatusInfo.speed
Address	Street address of the last position; click it to open the position on Google Maps in a new window.	GetAddresses from latitude and longitude
Serial Number, VIN, License Plate	Identifiers of the asset.	Device
Make And Model	Make and model decoded from the VIN.	Device.vinInfoMake, vinInfoModel
Work Requests	Number of unreviewed High or Critical work requests, the same number as "Immediate Actions > High or critical work requests" on the asset's Maintenance tab. A number above 0 is a link to that tab (new window). 0 is plain text.	MaintenanceWorkRequest

Engine Data

Column	Diagnostic	Threshold
Odometer	DiagnosticOdometerId	No
Engine Hours	DiagnosticEngineHoursId	No
Fuel Level	DiagnosticFuelLevelId	Yes, 0 to 100%
Driver Seatbelt	DiagnosticDriverSeatbeltId	No
Coolant Temperature	DiagnosticEngineCoolantTemperatureId	No
Battery Voltage	DiagnosticGoDeviceVoltageId	Yes, volts
State Of Charge	DiagnosticStateOfChargeId	Yes, 0 to 100%

Aux Inputs. Aux 1 to Aux 4 (DiagnosticAux1Id to DiagnosticAux4Id). Each can be given a name.

Dashcam

Column	Behavior
Camera Health	A "View" link to the asset's page, where its camera is shown. Tracked assets only.
Live Stream	A "Watch live" link to the MyGeotab map with the asset selected, where live video starts. Tracked assets only.

Camera data is not exposed by the MyGeotab API, so these two columns are links, not values.

Winter Operations. Solid Material Rate, Liquid Material Rate, Prewet Material Rate, Air Temperature, Road Temperature, and Third-Party Aux 5 to 8. The material rates use DiagnosticSolidMaterialRateId, DiagnosticLiquidMaterialRateId and DiagnosticPreWetMaterialRateId; the temperatures use IoxWrksAirTemperature and IoxWrksRoadTemperature; the third-party inputs use DiagnosticThirdPartyAux5Id to 8Id. The Third-Party Aux columns can be given names like the Aux inputs.

Column Settings

The Columns button opens a panel beside the table, listing the columns by group. Close it with the x button or Escape.

Choosing columns. Tick a column to show it and untick it to hide it. Any column except Asset can be switched off. The change is saved at once and the table loads the new readings.

Naming Aux inputs. Aux 1 to 4 and Third-Party Aux 5 to 8 each have a pencil icon. Enter a name, for example "Front Door", and the column heading becomes "Front Door (Aux 1)". Names are limited to 40 characters. Clearing the name restores the default heading.

Minimum thresholds. Fuel Level, Battery Voltage and State Of Charge have a "Set min" button. Enter only the number, with no % or V; the unit is shown on the button after saving, for example "Min 25%".

- A reading below its minimum turns that one cell light yellow. The rest of the row stays unchanged.
- With no minimum set, or no reading, nothing is highlighted.
- A minimum on a column that is not ticked highlights nothing. Ticking the column again restores it; the saved minimum is kept.
- Fuel Level and State Of Charge accept 0 to 100. Leave the box empty and save to remove a minimum.
- Enter or Save applies the value; Escape cancels the edit without closing the panel.

Saved Settings

Most settings are saved once per MyGeotab database in AddInData, so every user of the database sees the same columns. One setting is stored per browser instead.

Setting	Where it is kept	Shared by
Ticked columns and their order	AddInData (`details.kind = "columns"`)	All users of the database
Refresh minutes	AddInData	All users
Aux input names	AddInData	All users
Minimum thresholds	AddInData	All users

Setting	Where it is kept	Shared by
Column widths	AddInData	All users
Last update filter	Browser local storage, key `assetStatus.ui`	That browser only
Search, group and assets filter	Page memory only	Not saved

The saved document looks like this:

```
{
  "columns": ["driver", "lastUpdate", "speed", "address", "fuelLevel"],
  "refreshMinutes": 5,
  "auxLabels": { "aux1": "Front Door" },
  "thresholds": { "fuelLevel": 20 },
  "columnWidths": { "name": 200, "address": 320 }
}
```

When the page loads, the saved document is cleaned: unknown column ids are dropped, refresh minutes outside 1 to 60 revert to 5, labels are trimmed to 40 characters, thresholds outside a column's range are discarded, and widths are clamped to 60 to 600. Older saved documents that only list optional columns (`extraColumns`) are upgraded automatically.

A change shows on screen immediately and is put back if saving fails.

Geotab API Usage

All calls go through the MyGeotab session the add-in is running in, as the signed-in user. The add-in only reads data, except that it writes its own settings document to AddInData.

Purpose	Call	Notes
Asset list	`Get Device`	Search `fromDate` = now (leaves out archived assets) and the group filter; sorted by name. Fields: id, name, deviceType, productId, serialNumber, VIN, licensePlate, vinInfoMake, vinInfoModel, activeTo, devicePlanBillingInfo. Then filtered to active rate plans.
Latest status	`Get DeviceStatusInfo`	One row per device: position, speed, driver, last update, and one reading per ticked diagnostic. Up to 50,000 rows. Only diagnostics for ticked columns are requested.
Group names	`Get Group`	Fills the group dropdown.
Driver names	`Get User`	Resolves driver ids to names; while loading the cell shows a skeleton, and an unknown driver shows "Unknown driver".
Addresses	`GetAddresses`	Only when the Address column is ticked, from each asset's latitude and longitude.
Work requests	`Get MaintenanceWorkRequest`	Search `isReviewed = false`, `isSnoozed = true`, severities Critical and High, counted per `device.id`. Only when the Work Requests column is ticked. Up to 10,000 requests.
Settings	`Get`, `Add`, `Set` on `AddInData`	One document per database, `details.kind = "columns"`.

Refresh. The status data and work request counts reload every N minutes (the Refresh every setting). The table stays on screen while new data loads. Query keys include the group filter and the requested diagnostics, so changing the group or a column fetches fresh data.

Privacy. Device ids and user ids are never shown on screen. Names are shown, or "Unknown device" and "Unknown driver" when a name cannot be found.

Known Limitations and Troubleshooting

Limitations

- Camera Health and Live Stream are links, not values, because MyGeotab does not expose camera data through its API. The Live Stream link format (`#map,liveVehicleIds:!(id)`) has not been verified against a camera-equipped asset.
- The Work Requests count uses the same filters as the Maintenance tab's "High or critical work requests" number. It was built from the calls that tab makes, and should be checked against a few assets with known counts after the first install.
- Rate plans are matched by name: any plan whose name starts with "Terminate" or "Suspend" hides the asset. Plans named differently are treated as active.
- Settings are shared by everyone in a database. There is no per-user layout.
- The Last update filter is stored per browser, so it can differ between users and devices.
- Column text wider than its column is cut with an ellipsis until the column is widened.

Troubleshooting

Symptom	Likely cause and fix
Red error message instead of the table	Read the message: it is MyGeotab's own error. For example, "unknown property" means the request asked for a field MyGeotab does not accept. Contact support with the text.
Table is empty	The Last update filter is on Today and no asset has reported today. Choose All. Also check the group dropdown and the MyGeotab group filter.
An asset is missing	It is archived, or its rate plan is Terminated or Suspended.
Work Requests shows a dash	The work request lookup failed; the other columns still work. Reload, and if it persists, report it.
A column setting did not save	The save failed and the previous choice was put back. Check the connection and try again.
Address shows a dash	The asset has no position yet.

Support: andrew.hwang@advtracking.net