#### **Altibase Tools & Utilities**

# iSQL User's Manual

Release 6.1.1

May 11, 2012



Altibase Tools & Utilities iSQL User's Manual Release 6.1.1

Copyright © 2001~2012 Altibase Corporation. All rights reserved.

This manual contains proprietary information of Altibase® Corporation; it is provided under a license agreement containing restrictions on use and disclosure and is also protected by copyright patent and other intellectual property law. Reverse engineering of the software is prohibited.

All trademarks, registered or otherwise, are the property of their respective owners

Altibase Corporation 10F, Daerung PostTower II, 182-13, Guro-dong Guro-gu Seoul, 152-847, Korea

Telephone: +82-2-2082-1000 Fax: 82-2-2082-1099

E-mail: support@altibase.com www: http://www.altibase.com

# **Contents**

Preface	i
About This Manual	
Intended Audience	ii
Software Environment	ii
Organization	ii
Documentation Conventions	ii
Related Documents	V
On-line Manuals	V
Altibase Welcomes Your Comments	
1. Using iSQL	
1.1 iSQL Overview	
1.1.1 iSQL Main Functionality	
1.2 Setting Up iSQL	
1.3 iSQL Command-Line Options	
1.4 iSQL Commands	
1.5 iSQL Environment Variables	
1.5.1 ALTIBASE_HOME	
1.5.2 ALTIBASE_PORT_NO	
1.5.3 ALTIBASE_NLS_USE	
1.5.4 ALTIBASE_NLS_NCHAR_LITERAL_REPLACE	
1.5.5 ISQL_CONNECTION	
1.5.6 ISQL_BUFFER_SIZE	
1.5.7 ALTIBASE_DATE_FORMAT	
1.5.8 ISQL_EDITOR	
1.5.9 ALTIBASE_IPC_FILEPATH	
1.6 Personalizing iSQL	
1.6.1 glogin.sql	
1.6.2 login.sql	
1.6.3 Editing the LOGIN file	
2. Examples of iSQL in Use	
2.1 Login Postvictions	
2.1.1 Login Restrictions 2.2 Starting Up and Shutting Down ALTIBASE HDB	
2.2.1 Starting Up ALTIBASE HDB	
2.2.2 Shutting Down ALTIBASE HDB	
2.3 Connecting and Disconnecting	
2.3.1 Connecting to a Database	
2.3.2 Disconnecting from a Database	
2.4 Retrieving Information Related to the Database and Database Objects	
2.4.1 Performance Views	
2.4.2 Viewing the List of Tables	
2.4.3 Viewing a Table Structure	
2.4.4 Viewing Sequence Information	
2.5 Controlling Transactions	
2.5.1 Defining Transaction Modes	
2.5.2 PLANCOMMIT	
2.6 File Management	
2.6.1 Saving Results	
2.6.2 Running Scripts	
2.6.3 Saving SQL Statements	
2.6.4 Loading SQL Statements	
2.6.5 Saving DML Statements	
2.6.6 Editing Query Statements	
2.7 Formatting SELECT Query Results	
2.7.1 SET LINESIZE	

2.7.2 SET LOBSIZE	36
2.7.3 SET LOBOFFSET	37
2.7.4 SET FEEDBACK	37
2.7.5 SET PAGESIZE	38
2.7.6 SET HEADING	38
2.7.7 SET COLSIZE	39
2.8 Setting Output Options	40
2.8.1 Getting the Elapsed Time	40
2.8.2 Setting Execution Time Units for Output	40
2.8.3 Describing Foreign Key Information	41
2.8.4 Outputting Script Execution Results	42
2.8.5 Outputting an Execution Plan	43
2.8.6 Setting Result Output Orientation	45
2.9 Viewing iSQL Display Settings	46
2.10 Host Variables	
2.10.1 Declaring a Host Variable	
2.10.2 Assigning a Value to a Host Variable	
2.10.3 Viewing Host Variables	
2.11 Executing Prepared SQL Statements	
2.11.1 Prepared SQL versus Dynamic SQL Statements	50
2.11.2 Prepared SQL Statements	
2.12 Creating, Executing and Dropping Stored Procedures	
2.12.1 Creating Procedures	
2.12.2 Executing Procedures	
2.12.3 Dropping Procedures	
2.13 Creating, Executing and Dropping Functions	
2.13.1 Creating Functions	
2.13.2 Executing Functions	
2.13.3 Dropping Functions	
2.14 Convenient User Functions	
2.14.1 History	
2.14.2 Shell Commands	
2.14.3 Getting Help	
2.15 Using National Character Sets	60

# **Preface**

i Preface

#### **About This Manual**

This manual describes how to use iSOL to access a database.

#### **Intended Audience**

The following ALTIBASE® HDB™ users will find this manual useful:

- database administrators
- performance managers
- database administrators
- application developers
- technical support workers

It is recommended that those reading this manual possess the following background knowledge:

- basic knowledge in the use of computers, operating systems, and operating system utilities
- experience in using relational databases and an understanding of database concepts
- computer programming experience
- experience in database server, operating system or network administration

#### **Software Environment**

This manual has been prepared assuming that ALTIBASE HDB 5.5.1 is used as the database server.

#### **Organization**

This manual is organized as follows:

Chapter1: Using iSQL

This chapter presents an overview of iSQL and explains the commands and how to use iSQL.

Chapter2: Examples of iSQL in Use

This chapter provides in-depth examples of each of the commands provided with iSQL.

#### **Documentation Conventions**

This section describes the conventions used in this manual. Understanding these conventions will make it easier to find information in this manual and other manuals in the series.

There are two sets of conventions:

- syntax diagrams
- sample code conventions

# **Syntax Diagrams**

This manual describes command syntax using diagrams composed of the following elements:

Elements	Meaning
Reserved word	The start of a command. If a syntactic element starts with an arrow, it is not a complete command.
	The command continues to the next line. If a syntactic element ends with this symbol, it is not a complete command.
-	The command continues from the previous line. If a syntactic element starts with this symbol, it is not a complete command.
	The end of a statement.
SELECT	Indicates a mandatory element.
NOT	Indicates an optional element.
ADD	Indicates a mandatory element comprised of options. One, and only one, option must be specified.
ASC DESC	Indicates an optional element comprised of options.

iii Preface

Elements	Meaning
ASC DESC	Indicates an optional element in which multiple elements may be specified. A comma must precede all but the first option.

#### **Sample Code Conventions**

The code examples explain SQL, stored procedures, iSQL, and other command line statements.

The following table describes the printing conventions used in the code examples.

Rules	Meaning	Example
[]	Indicates an optional item.	VARCHAR [(size)] [[FIXED  ] VARIABLE]
{}	Indicates a mandatory field for which one or more items must be selected.	{ ENABLE   DISABLE   COMPILE }
I	A delimiter between optional or mandatory arguments.	{ ENABLE   DISABLE   COMPILE } [ ENABLE   DISABLE   COMPILE ]
	Indicates that the previous argument is repeated, or that sample code has been omitted.	iSQL> select e_lastname from employees; E_LASTNAME
Other Symbols	Symbols other than those shown above are part of the actual code.	EXEC :p1 := 1; acc NUMBER(11,2);
Italics	Statement elements in italics indicate variables and special values specified by the user.	SELECT * FROM table_name; CONNECT userID/password;
Lower Case Characters	Indicate program elements set by the user, such as table names, col- umn names, file names, etc.	SELECT e_lastname FROM employees;

Rules	Meaning	Example
Upper Case Characters	Keywords and all elements provided by the system appear in upper case.	DESC SYSTEMSYS_INDICES_;

#### **Related Documents**

For more detailed information, please refer to the following documents:

- ALTIBASE HDB Installation Guide
- ALTIBASE HDB Getting Started
- ALTIBASE HDB Administrators' Manual
- ALTIBASE HDB Replication Manual
- ALTIBASE HDB Precompiler Users' Manual
- ALTIBASE HDB ODBC Reference
- ALTIBASE HDB Application Program Interface Users' Manual
- ALTIBASE HDB iSQL Users' Manual
- ALTIBASE HDB Utilities Manual
- ALTIBASE HDB Error Message Reference

#### **On-line Manuals**

Manuals are available at Altibase Technical Center (http://atc.altibase.com/).

#### **Altibase Welcomes Your Comments**

Please let us know what you like or dislike about our manuals. To help us with future versions of our manuals, please tell us about any corrections or classifications that you would find useful.

Include the following information:

- The name and version of the manual that you are using
- Any comments that you have about the manual
- Your name, address, and phone number

Write to us at the following electronic mail address: support@altibase.com

When you need an immediate assistance regarding technical issues, please contact Altibase Technical Center.

*r* Preface

#### **About This Manual**

Thank you. We appreciate your feedback and suggestions.

# 1 Using iSQL

Using iSQL

1

# 1.1 iSQL Overview

iSQL is a user tool for accessing an Altibase database and retrieving and modifying stored data using SQL statements and a number of additional commands.

## 1.1.1 iSQL Main Functionality

#### **ALTIBASE HDB Startup and Shutdown**

iSQL allows you to perform database management tasks, such as starting up and shutting down the server, and execute SQL statements using the same command prompt.

#### **Database Connection & Disconnection**

After ALTIBASE HDB starts up, you can use various user names to connect to and disconnect from the database.

#### **Database Object Information Inquiry**

iSQL allows you to use SQL statements to query all database object information, and supports convenient commands for inquiring about main objects.

#### **Database Management via SQL Statements**

Because iSQL can be used to execute any kind of SQL statement, you can control transactions and alter databases quickly and conveniently.

#### **Functions to Improve User Convenience**

The above tasks can be easily and conveniently accomplished using the file management and editing functions, the ability to execute shell commands over iSQL, and the HISTORY function.

# 1.2 Setting Up iSQL

In order for iSQL to access a server, the following information is necessary.

- ALTIBASE\_HOME
   A path to a server or client installation
- server\_name
   The name (or IP address) of a computer on which ALTIBASE HDB Server is running
- port\_no
   The port number to be used when connecting via TCP or IPC
- user\_id
   A User ID registered in the database
- password
   The password corresponding to the User ID
- NLS\_USE
   The character set with which to display retrieved data to the user

ALTIBASE\_HOME can only be set using an environment variable, while the other settings may be made using command-line options. (For more information, please refer to 1.3 iSQL Command-Line Options.)

The ALTIBASE\_HOME environment variable must be set in order to use iSQL. In the case of Windows, this is set automatically when the server is installed, but, in the case of the client, must be set manually by the user. We strongly suggest that you verify that this setting has been properly made, as the application may not run properly if this setting is not made.

port\_no and NLS\_USE can be set using the environment variables or the server settings file (altibase.properties). If these settings are made via all three methods, they will take priority as follows, in descending order:

- 1. command-line options
- 2. environment variables (ALTIBASE\_PORT\_NO, ALTIBASE\_NLS\_USE)
- 3. server settings file (altibase.properties)

Therefore, when it is desired to connect using options other than those that have been previously set, the command-line options can be used, so that it is not necessary to change the settings in the server setting file or the environment variables.

If any options have not been set, when iSQL is executed for the first time, the user will be prompted to enter the corresponding variables. At this time, it is essential to enter values that are valid and follow the proper format, otherwise iSQL may not run properly.

However, if the NLS\_USE option in particular has not been set, no command prompt will appear at the time of execution. Instead, US7ASCII will be used, and a connection attempt will be made. In this case, if the character set of the database is not US7ASCII, the application will not execute properly, or some of the user's data may become corrupted. Thus it is paramount that NLS\_USE be set to a suitable value for the usage environment.

In order to ensure stable iSQL operation, we recommend that the following environment variables

#### 1.2 Setting Up iSQL

#### be set:

- ALTIBASE\_HOME : the path to a server or client installation
- ALTIBASE\_PORT\_NO: the port number to use to connect to the server
- ALTIBASE\_NLS\_USE: the character set to use to display retrieved data to the user
- PATH: the path containing the executable file, which must equal \$ALTIBASE\_HOME/bin

# 1.3 iSQL Command-Line Options

The ALTIBASE HDB server must be started before iSQL is executed. The following options are case-insensitive.

```
isql [-H]
   [-S server_name] [-U user_id] [-P password]
   [-PORT port_no]
   [-UNIXDOMAIN_FILEPATH filepath]
   [-IPC_FILEPATH filepath]
   [-SILENT]
   [-F infile_name] [-O outfile_name] [-NLS_USE]
   [-NLS_NCHAR_LITERAL_REPLACE 0|1]
   [-prefer_ipv6]
```

-S server\_name

Specifies the name (or IP address) of a computer on which ALTIBASE HDB Server is running.

When connecting in IPC, if this option is specified, it is ignored and no error is raised regardless of the operating system. It can be a host name, an IPv4 address, or an IPv6 address. An IPv6 address must be enclosed by a left square bracket([) and a right square bracket(]). For example, in the case of localhost (meaning this computer), localhost can be specified as the host name, 127.0.0.1 as the IPv4 address, or [::1] as the IPv6 address. For more information about the IPv6 address notation, please refer to the ALTIBASE HDB Administrator's Manual.

-U user id

Specifies a user ID registered in the database.

-P password

Specifies the password corresponding to the user ID.

-PORT port\_no

Specifies the port number for connecting via TCP/IP or IPC. However, when connecting in a Unix environment via IPC, this option can be omitted. If it is specified, it is ignored and no error is raised. To connect via TCP, first set 'ISQL\_CONNECTION=TCP' on the client and then enter the PORT NO.

To connect via IPC in a Windows environment, set the environment variable 'ISQL\_CONNECTION=IPC' and specify the port number using one of the following:

- the -PORT option
- the ALTIBASE IPC PORT NO environment variable
- the IPC\_PORT\_NO property in altibase.properties

If the environment variable ISQL\_CONNECTION is not set to IPC and the -PORT option is omitted, the port number will be checked for first in the environment variable ALTIBASE\_PORT\_NO and then in the PORT\_NO property in altibase.properties, and if it is not set in either of those places, a prompt to enter it will be raised.

-UNIXDOMAIN\_FILEPATH filepath

#### 1.3 iSQL Command-Line Options

When a server and client connect using a Unix domain socket in a Unix environment (ISQL\_CONNECTION=UNIX), the connection will fail if the server and client have different values for ALTIBASE\_HOME and also have different Unix domain socket paths. In this case, if the server and client use corresponding files (e.g. ALTIBASE\_HOME/trc/cm-unix), Unix domain communication is possible.

#### • -IPC\_FILEPATH filepath

When the client and the server are to connect via IPC (ISQL\_CONNECTION=IPC) in a Unix environment, if ALTIBASE\_HOME is set differently on them, they will not be able to connect if they have different socket paths. In this case, Unix domain communication can be achived using the ALTIBASE\_HOME/trc/cm-ipc file, and then information about shared memory can be retrieved. However, this option can be omitted if ALTIBASE\_IPC\_FILEPATH is set.

#### -F infile\_name

Specifies a script file to be executed immediately after iSQL is launched.

#### O outfile\_name

Specifies a file in which to store the results of the excuted iSQL commands. This file will be created in the current directory. If the file already exists, it will be overwritten.

#### -H

Outputs help information for iSQL execution.

#### -SILENT

This option turns on silent mode. If silent mode is on, noncritical messages, such as the copyright notice, etc. will not be displayed.

#### -NLS USE

Specifies the character set with which to display data to the user. The following character sets may be specified:

- US7ASCII
- KO16KSC5601
- MS949
- BIG5
- GB231280
- UTF8
- SHIFTJIS
- EUCJP

If omitted, the environment variable ALTIBASE\_NLS\_USE or altibase.properties will be used, in descending order of preference, and if it is still not specified, the basic character set (US7ASCII) will be used.

#### -NLS\_NCHAR\_LITERAL\_REPLACE

- 0: convert all strings to the database character set without checking for the "N" character
- 1: do not convert strings that are preceded by the "N" character to the database character set

#### -prefer\_ipv6

This option determines the IP address to be connected first when a host name is given for the s option.

If this option is specified and a host name is given for the -s option, this means that resolving the host name to the IPv6 address is prefered.

If this option is omitted, isql connects to the IPv4 address by default.

If it fails to connect to the prefered IP version address, an attempt is made to connect using the other IP version address.

For example, when localhost is given for the -s option and this option is specified, isql first tries to connect to the [::1] IPv6 address. If this attempt fails, isql proceeds to connect to the 127.0.0.1 IPv4 address.

If any of the -S, -U, or -P options are missing from the above command, the user will be prompted to input the option values.

# 1.4 iSQL Commands

When iSQL is started, an iSQL command prompt will appear, and when iSQL commands are entered, the results of execution will be displayed. The iSQL commands are described individually in the following table.

Category	Туре	Commands	Description
iSQL startup and shut- down	Startup	\$ isql [option]	If you execute this command in a shell, iSQL will start up. For information on the available options, please refer to the 1.3 iSQL Command-Line Options section.
	Prompt	iSQL>	Type a command at the iSQL prompt and press the ENTER key.
	Shutdown	EXIT; QUIT;	Used to shut down iSQL.
ALTIBASE HDB startup and shutdown	ALTIBASE HDB Startup	STARTUP	Use the PRE-PROCESS, PROCESS, CONTROL, META, or SERVICE option to start ALTIBASE HDB up to the corresponding stage.
	ALTIBASE HDB Shutdown	SHUTDOWN	Use one of the NORMAL, IMMEDIATE, or ABORT options to shut down ALTIBASE HDB.
Database connection and disconnection	Access the server as another user	CONNECT [logon] [nls] [AS sysdba]; where logon has the syntax: user1[/pass1] where nls has the syntax: NLS=character_set	This command allows access to the database as user1 with password pass1 after having already accessed the database as another user in iSQL. If CONNECT is successful, the information related to the previous session is cleared. The AS clause allows the SYS user to access the server in sysdba manager mode. Only one user is allowed to connect as sysdba at a time. The nls option specifies the character set. For detailed information on character sets, please refer to the 1.3 iSQL Command-Line Options: -NLS_USE option.
	Terminate a connection	DISCONNECT;	Ends the current session and terminates the connection with the server.

Category	Туре	Commands	Description
Database object infor- mation inquiry	Display per- formance view list	SELECT * FROM V\$TAB;	Displays the list of all of the performance views provided by the system. This command is available only in iSQL.
	Display table list	SELECT * FROM TAB;	Displays the list of currently created tables. This command is only available in iSQL.
	Display table structure	DESC samp ;	Lists the column definitions for the table samp
	Display sequence Information	SELECT * FROM V\$SEQ;	If you accessed the server with the SYS account, information on all sequences is displayed. If you accessed the server as another user, only the information on the sequences generated by that user will be displayed. This command is available only in iSQL.
Transaction control	Setting trans- action mode	AUTOCOMMIT ON; AUTOCOMMIT OFF;	Determines whether to commit commands automatically at the time that they are executed.  Default: ON
	Other SET functions	SET PLANCOMMIT ON; SET PLANCOMMIT OFF;	Determines whether to automatically commit commands such as DESC, SELECT * FROM TAB, or SELECT * FROM seq_name when EXPLAIN PLAN is ON (or ONLY) and AUTOCOMMIT is OFF. Default: OFF

9

Using iSQL

#### 1.4 iSQL Commands

Category	Туре	Commands	Description	
File manage- ment	Output data to a file	SPOOL file_name ;	Starts writing the results shown on the screen to the file <i>file_name</i> .	
		SPOOL OFF;	Stops writing the results shown on the screen to the file <i>file_name</i> .	
	SQL script execution	START file_name ;	Reads a script file and executes the SQL statements in sequence.	
		@ file_name;	Performs a function similar to that of startup when executed via an iSQL prompt.	
		@@ file_name;	When used in a script, this command executes the file <i>file_name</i> in the same directory as the calling script.	
	Save SQL statement to file	SAVE abc.sql;	Saves the last of the commands currently in the iSQL buffer to a file.	
	Load SQL statement	LOAD abc.sql;	Loads the first of the commands saved in a file at the end of the command buffer.	
Save DML statements file	statements to	statements to	SET QUERYLOGGING ON; SET QUERYLOGGING OFF;	This writes executed DML statements, such as INSERT, UPDATE, DELETE and MOVE, in \$ALTIBASE_HOME/trc/isql_query.log.
		ED	For creating and editing temporary files.	
		ED file_name[.sql]	For editing existing files or creating new files.	
		2ED or 2 ED	Edits query command number 2 in the history list.	

Category	Туре	Commands	Description
Control out- put option	Format SELECT result column	SET LINESIZE 100;	Sets the length of a display line for outputting the result of a SELECT query. Must be between 10 and 32767 inclusive. Default: 80
	Format SELECT result column of	SET LOBSIZE 10;	Sets the number of characters to display when a CLOB column is output.  Default: 80
	type CLOB	SET LOBOFFSET 3;	Sets the number of characters by which to offset the display when a CLOB column is output.  Default: 0
	Output SELECT result count	SET FEED[BACK] ON; SET FEED[BACK] OFF; SET FEED[BACK] n;	Determines whether to output the number of rows in a query result.
	Format rows of SELECT result	SET PAGESIZE 10;	Sets how many records of a SELECT query result are output at one time. When set to 0, all resultant records are output. Default: 0
	Show/hide SELECT result header	SET HEADING ON; SET HEADING OFF;	Sets whether to output the header of a SELECT result Default: ON
	Set SELECT result output size.	SET COLSIZE N;	Sets the number of characters to output when CHAR or VARCHAR type columns are output as a SELECT query result.
	Show SQL statement execution time	SET TIMING ON; SET TIMING OFF;	Sets whether to output the amount of time taken to execute a SQL command.  Default: OFF
	Set the SQL statement execution time units for output	SET TIMESCALE SEC; SET TIMESCALE MILSEC; SET TIMESCALE MICSEC; SET TIMESCALE NANSEC;	Sets the unit of time for executing SQL statements as seconds, milliseconds, microseconds or nanoseconds.
	Show/hide foreign key information	SET FOREIGNKEYS ON; SET FOREIGNKEYS OFF;	Determines whether to include foreign key information in the output when displaying the table structure (using DESC). Default: OFF
	Show/hide script execu- tion result	SET TERM ON; SET TERM OFF;	Determines whether to display the results of execution of a script file on the screen. Default: ON

#### 1.4 iSQL Commands

Category	Туре	Commands	Description
Control out- put option	Output executionplan tree	ALTER SESSION SET EXPLAIN PLAN = ON; ALTER SESSION SET EXPLAIN PLAN = ONLY; ALTER SESSION SET EXPLAIN PLAN = OFF;	Determines whether to output an execution plan for a SELECT statement. Default: OFF
	SELECT result output direc- tion	SET VERTICAL ON; SET VERTICAL OFF;	Displays SELECT results vertically when set to ON. Default: OFF
	Show value of	SHOW LINESIZE	Displays the current LINESIZE value.
	iSQL display settings	SHOW COLSIZE	Displays the current COLSIZE value.
		SHOW LOBOFFSET	Displays the current LOBOFFSET value.
		SHOW LOBSIZE	Displays the current LOBSIZE value.
		SHOW PAGESIZE	Displays the current PAGESIZE value.
		SHOW PLANCOMMIT	Shows whether PLANCOMMIT is ON or OFF.
		SHOW QUERYLOGGING	Shows whether DML statements wil be written to ALTIBASE_HOME/trc/isql_query.log when executed.
		SHOW FEEDBACK	Shows the current FEEDBACK value.
		SHOW HEADING	Shows the current HEADING setting.
		SHOW TERM	Shows the current TERM setting.
		SHOW TIMING	Shows the current TIMING setting.
		SHOW TIMESCALE	This shows the current time units for the execution of SQL statements.
		SHOW USER	Shows the current user.
		SHOW FOREIGNKEYS	Shows the current foreign key display setting.
		SHOW VERTICAL	Shows whether the results of a SELECT query will be output vertically.
		SHOW ALL	Shows the set values of the display settings for the current session.

Category	Туре	Commands	Description
Variable and	Variable dec-	VAR p1 INTEGER;	Declares the variable <i>p1</i> as integer type.
Prepared SQL statements	laration	VARIABLE p2 CHAR(10);	Declares the variable <i>p2</i> as CHAR type.
	Assign values	EXECUTE :p1 := 100 ;	Assigns the value 100 to variable p1.
	to variables	EXEC :p2 := 'abc' ;	Assigns the text 'abc' to variable p2.
	Variable dis-	PRINT VAR[IABLE];	Shows the currently declared variables.
	play	PRINT p1;	Shows the type and value of variable <i>p1</i> .
	Prepared SQL statement execution	PREPARE SQL statement ;	Separates the processes of query optimization and execution, and executes the query as a prepared SQL statement. In iSQL, the default execution method for executing SQL statements is the Direct Execution method, in which optimization and execution are performed at once. There is no difference between the two execution methods in iSQL in terms of the results obtained, however, prepared SQL statements can be used to bind variables to values and execute SQL statements based thereon.
Functions for user conve-	Historylist dis- play	HISTORY; H;	Shows a list of the commands currently saved in the iSQL buffer.
nience	Repeat execution	/	Repeats execution of the command currently in the iSQL buffer. The most recently executed command will be executed again.
		2/	Executes the second command in a list output using the HISTORY command.
	Shell com- mand execu- tion	! shell command	A shell command that follows an exclamation point will be immediately executed from within iSQL.
	Comment	/* comment */ comment	Indicate a multiple-line comment and a single-line comment, respectively.
	Help	HELP; HELP INDEX; HELP EXIT;	Provides information on how to use help, outputs a list of commands, and describes (e.g.) the EXIT command, respectively.

# 1.5 iSQL Environment Variables

#### 1.5.1 ALTIBASE\_HOME

Sets the directory in which the package is installed.

In the case of MS Windows, this is set automatically when the server is installed, however, when the client is installed, this is not automatically set due to the danger of a conflict with the environment variables for the server. When installing the client, the user must manually set this directory.

This environmental variable must be set in order to use ISOL.

```
Ex)
Windows (Server): 'set ALTIBASE_HOME=C:/Program Files/Altibase/
Altibase5_Server/altibase_home',
Windows (Client): 'set ALTIBASE_HOME=C:/Program Files/Altibase/
Altibase5 Client/altibase home client')
```

#### 1.5.2 ALTIBASE PORT NO

This is the port number of the server to connect to. This can be specified either by using the -PORT option or in altibase.properties.

If no designated port number can be found (in descending order of precedence) in the -PORT option, in the environment variable ALTIBASE\_PORT\_NO, or in altibase.properties, a prompt to enter the port number will appear.

#### 1.5.3 ALTIBASE\_NLS\_USE

This is the character set used to display retrieved results to the user.

- US7ASCII
- KO16KSC5601
- MS949
- BIG5
- GB231280
- UTF8
- SHIFTJIS
- EUCJP

This can be set either using the -NLS\_USE option or in altibase.properties.

If NLS\_USE is not specified using the -NLS\_USE option, the environment variable ALTIBASE\_NLS\_USE, or altibase.properties (in descending order of precedence), US7ASCII is used as

the default character set.

#### 1.5.4 ALTIBASE\_NLS\_NCHAR\_LITERAL\_REPLACE

By default, iSQL converts an entire query string to the database character set before sending the data to the database. This behavior can be prevented for a given string literal by setting this property to 1 and placing the "N" character in front of the string literal.

A property setting of 1 instructs iSQL to search for the "N" character in front of every string literal. If the "N" character is found, iSQL sends the string to the database without converting it to the database character set. This is useful when it is desired to use NCHAR type data that are encoded differently from the database character set.

- 0: convert all strings to the database character set without checking for the "N" character
- 1: do not convert strings that are preceded by the "N" character to the database character set

Note: Setting this variable to 1 can be expensive in terms of usage of client resources.

#### 1.5.5 ISQL CONNECTION

When ALTIBASE HDB is used in a client-server arrangement, the user can set environment variables to select the client-server protocol that is suitable for the operating environment. ALTIBASE HDB supports the TCP/IP, IPC and Unix domain socket protocols. The default protocol for communication with ALTIBASE HDB servers is TCP/IP. Note that when using the IPC protocol the value of ALTIBASE HDB properties related to the IPC channel (IPC\_CHANNEL\_COUNT) must be considered.

The following example shows how to set the environment variable when using the IPC protocol:

```
CSH: setenv ISQL_CONNECTION IPC SH: ISQL CONNECTION=IPC; export ISQL CONNECTION
```

#### 1.5.6 ISQL BUFFER SIZE

The size of the buffer in which to store queries can be set using this environment variable.

```
Ex)

CSH: setenv ISQL_BUFFER_SIZE 128000

SH: ISQL BUFFER SIZE = 128000; export ISQL BUFFER SIZE
```

#### 1.5.7 ALTIBASE\_DATE\_FORMAT

When retrieving Date type data using a SELECT statement, the environment variable ALTIBASE\_DATE\_FORMAT can be used to change the default date format, which is YYYY/MM/DD HH:MI:SS, to some other date format.

```
Ex) For Born, Korn, or Bash Shell export ALTIBASE DATE FORMAT='DD-MON-YYYY'
```

#### 1.5.8 ISQL\_EDITOR

This environment variable can be used to change the default editor (/usr/bin/vi).

```
Ex)
CSH: setenv ISQL_EDIT usr/bin/ed
SH: ISQL_EDIT=/usr/bin/ed; export ISQL_EDITOR
```

#### 1.5.9 ALTIBASE\_IPC\_FILEPATH

In a Unix environment, if a client and the server have different values for ALTIBASE\_HOME, they will not be able to connect via IPC if they have different Unix domain socket paths. In this case, in order to be able to connect via IPC, it will be necessary to set the ALTIBASE\_IPC\_FILEPATH environment variable or the -IPC\_FILEPATH iSQL option to the \$ALTIBASE\_HOME/trc/cm-ipc file used by the server.

# 1.6 Personalizing iSQL

iSQL users can customize their iSQL environment and use the same settings for each session. For example, using the OS file, the user can specify a desired output format so that each query result displays the current time whenever query results are output. These files can be categorized into the following two types.

#### 1.6.1 glogin.sql

For initialization tasks that must be conducted when iSQL is started, iSQL supports the creation of a global script file, glogin.sql, by the DB administrator. iSQL executes this script whenever any user executes iSQL or attempts to connect to ALTIBASE HDB for the first time. The global file allows the DB administrator to make site-specific iSQL environment settings for all users. The global script file is located in \$ALTIBASE\_HOME/conf.

#### 1.6.2 login.sql

iSQL also supports the login.sql file, which is executed after glogin.sql. If both the glogin.sql file and the login.sql file exist, login.sql is executed after glogin.sql during iSQL startup, so the commands in login.sql will take precedence.

If several people share one Unix account, it will be impossible for them to personalize the glogin.sql file. In this case, individual users may add SQL commands, stored procedures, or iSQL commands to their respective login.sql files in their personal work directories. When a user starts up iSQL, iSQL automatically searches the current directory for the login.sql file and executes the commands in it.

The login.sql file cannot modify initial iSQL settings or individual session actions.

## 1.6.3 Editing the LOGIN file

The user may change the LOGIN file, like any other script. The following is an example of user1 creating a LOGIN file that turns off autocommit mode and executes SQL statements:

```
$ vi glogin.sql
AUTOCOMMIT ON
SET HEADING OFF
SELECT sysdate FROM dual;
$ vi login.sql
AUTOCOMMIT OFF
SET HEADING ON
DROP TABLE savept;
CREATE TABLE savept(num INTEGER);
INSERT INTO savept VALUES(1);
SAVEPOINT sp1;
INSERT INTO savept VALUES(2);
SELECT * FROM savept;
ROLLBACK TO SAVEPOINT sp1;
SELECT * FROM savept;
COMMIT;
$ isql
Altibase Client Query utility.
```

#### 1.6 Personalizing iSQL

```
Release Version 6.1.1.1
 Copyright 2000, Altibase Corporation or its subsidiaries.
All Rights Reserved.
Write Server Name (default:127.0.0.1) :
Write UserID : user1
Write Password :
ISQL_CONNECTION = TCP, SERVER = 127.0.0.1, PORT_NO = 20300
Set autocommit on success. -> Executing glogin.sql first
28-DEC-2004
                                -> heading off
1 row selected.
Set autocommit off success. -> Execute login.sql in the current work directory of the user after
glogin.sql is executed.
Drop success.
Create success.
1 row inserted.
                                -> It is executable only when Autocommit mode is off
Savepoint success.
1 row inserted.
                                -> heading on
NUM
1
2 rows selected.
Rollback success.
NUM
1
1 row selected.
Commit success.
```

# 2 Examples of iSQL in Use

This chapter describes several examples of the use of iSQL to manipulate databases.

# 2.1 Logging In to iSQL

To use iSQL, users must first be logged in. Connection information may be input directly via a command line, or via the iSQL input prompt.

```
isql -U userID -P password [-SYSDBA]
or
isql [-SYSDBA]
```

Additional information necessary for connection with the server is the server name (-S), user ID (-U), and password (-P). The user ID and password are not case-sensitive.

In order for the SYS user to use iSQL as an administrator, the SYSDBA option is used. The SYSDBA option can be used for remote access.

#### 2.1.1 Login Restrictions

- Only one user is permitted to connect in SYSDBA mode at one time. Two or more users cannot connect in SYSDBA mode at the same time.
- You can access the database remotely in SYSDBA mode, but can't start up the database.

For detailed information on system privileges, please refer to the *ALTIBASE HDB SQL Reference*. For detailed information on errors that may arise during iSQL execution, please refer to the *ALTIBASE HDB Error Message Reference*.

```
$ isql -S 127.0.0.1 -U sys -P manager [-SYSDBA]

or

$ isql [-sysdba]

Altibase Client Query utility.
Release Version 6.1.1.1
Copyright 2000, Altibase Corporation or its subsidiaries.
All Rights Reserved.

Write Server Name (default:127.0.0.1) :
Write UserID : sys
Write Password : manager -> The password on the screen is not displayed.
ISQL_CONNECTION = UNIX, SERVER = 127.0.0.1, PORT_NO = 20300
iSQL (sysdba) > -> iSQL is connected to the server, and SQL, iSQL, and PSM commands can be input and executed here.
```

# 2.2 Starting Up and Shutting Down ALTIBASE HDB

iSQL can be used to start up and shut down ALTIBASE HDB.

#### 2.2.1 Starting Up ALTIBASE HDB

To start up ALTIBASE HDB, iSQL must first be launched with the -sysdba option, in the same way as when a database is created.

Note: ALTIBASE HDB startup commands can be executed only with the UNIX account with which ALTI-BASE HDB (including iSQL) was installed.

The following is an example of the use of iSQL to start up ALTIBASE HDB. For more information on starting up ALTIBASE HDB, please refer to the *ALTIBASE HDB Administrators' Manual Chapter 4: Startup and Shutdown*.

```
$ isql -s 127.0.0.1 -u sys -p manager -sysdba
Altibase Client Query utility.
Release Version 6.1.1.1
Copyright 2000, Altibase Corporation or its subsidiaries.
All Rights Reserved.
ISQL CONNECTION = UNIX, SERVER = 127.0.0.1, PORT NO = 20300
[ERR-910FB : Connected to idle instance]
iSOL(sysdba) > startup service
Connecting to the DB server... Connected.
TRANSITION TO PHASE: PROCESS
TRANSITION TO PHASE : CONTROL
TRANSITION TO PHASE : META
  [SM] Recovery Phase - 1 : Preparing Database
                     : Dynamic Memory Version => Parallel Loading
  [SM] Recovery Phase - 2 : Loading Database
  [SM] Recovery Phase - 3 : Skipping Recovery & Starting Threads...
                       Refining Disk Table
 [SM] Refine Memory Table :
............
..... [SUCCESS]
 [SM] Rebuilding Indices [Total Count:101]
......
[SUCCESS]
TRANSITION TO PHASE : SERVICE
 [CM] Listener started: TCP on port 20300
  [CM] Listener started : UNIX
 [RP] Initialization : [PASS]
--- STARTUP Process SUCCESS ---
Command execute success.
```

# 2.2.2 Shutting Down ALTIBASE HDB

Use the SHUTDOWN command to shut down a running ALTIBASE HDB server.

#### 2.2 Starting Up and Shutting Down ALTIBASE HDB

The following is an example of the use of iSQL to shut down ALTIBASE HDB. For more information on shutting down ALTIBASE HDB, please refer to the *ALTIBASE HDB Administrators' Manual Chapter 4: Startup and Shutdown*.

iSQL(sysdba) > shutdown normal
Ok..Shutdown Proceeding....

TRANSITION TO PHASE : Shutdown Altibase [RP] Finalization : PASS shutdown normal success.

# 2.3 Connecting and Disconnecting

#### 2.3.1 Connecting to a Database

The CONNECT command is used to connect to ALTIBASE HDB with a specified user ID. If the first connection attempt fails, the CONNECT command does not prompt again for the user ID or password.

```
CONNECT [logon] [nls] [AS SYSDBA];
where longon has the syntax:
userID[/password]
and nls has the syntax:
NLS=character_set
```

#### 2.3.1.1 userID/password

The user ID and password with which to establish a connection to ALTIBASE HDB.

#### 2.3.1.2 NLS=character\_set

The NLS option specifies the character set.

```
iSQL> CONNECT sys/manager NLS=US7ASCII
Connect success.
```

#### 2.3.1.3 AS SYSDBA

The AS clause permits the SYS user to access the server in sysdba manager mode.

If CONNECT is successful, the current session is terminated, and a connection is established to the server using the specified user ID and password and the information in altibase.properties. Accordingly, the session information is cleared before connecting.

For instance, if AUTOCOMMIT mode is set to TRUE in altibase.properties and AUTOCOMMIT mode is changed to FALSE in iSQL, when the CONNECT statement is executed, AUTOCOMMIT mode will be changed to TRUE, because of the value in altibase.properties.

If CONNECT fails, the previous session is terminated and the connection with the server is closed. In other words, the result of all SQL statements executed thereafter will be a "Not connected" message. Execute "CONNECT userID/password [AS SYSDBA]" to attempt to re-establish a connection with the server.

#### 2.3 Connecting and Disconnecting

```
Write UserID : SYS
Write Password :
ISQL_CONNECTION = TCP, SERVER = 127.0.0.1, PORT NO = 20300
iSQL> SHOW USER;
User : SYS
iSQL> CREATE USER altiadmin IDENTIFIED BY alti1234;
Create success.
iSQL> CONNECT altiadmin/alti1234;
Connect success.
iSQL> SHOW USER;
User : ALTIADMIN
iSQL> CREATE TABLE altitbl(i1 INTEGER, i2 CHAR(5));
Create success.
iSQL> SELECT * FROM tab;
TABLE NAME
_____
ALTITBL
                                       TABLE
CLEAR DP
EXPORT PARTITION TO FILE
                                       SYNONYM
EXPORT_TO_FILE
                                       SYNONYM
EXPORT_USER_TABLES
                                       SYNONYM
FCLOSE
                                       SYNONYM
FCLOSE ALL
                                       SYNONYM
FCOPY
                                       SYNONYM
FFLUSH
                                       SYNONYM
FOPEN
                                       SYNONYM
FREMOVE
                                       SYNONYM
FRENAME
                                       SYNONYM
GET LINE
                                       SYNONYM
IMPORT_FROM_FILE
                                       SYNONYM
IS OPEN
                                       SYNONYM
NEW LINE
                                       SYNONYM
PRINT
                                       SYNONYM
PRINTLN
                                       SYNONYM
PUT
                                       SYNONYM
PUT LINE
                                       SYNONYM
RAISE APPLICATION ERROR
REGISTER
                                       SYNONYM
REMOVE
                                       SYNONYM
REMOVEALL
                                       SYNONYM
REMOVE DP
                                       SYNONYM
REMOVE XID
RESUME DP
                                       SYNONYM
SET DEFAULTS
                                       SYNONYM
SIGNAL
                                       SYNONYM
SLEEP
                                       SYNONYM
WAITANY
                                       SYNONYM
WAITONE
                                       SYNONYM
33 rows selected.
iSQL> CONNECT sys/manager;
Connect success.
iSOL> SHOW USER;
User : SYS
iSQL> CREATE TABLE systbl(i1 INTEGER, i2 CHAR(5));
Create success.
```

iSQL> SELECT * FROM tab;			
USER NAME		TYPE	
SYSTEM	STO_COLUMNS_ STO_DATUMS_ STO_DATUMS_ STO_ELLIPSOIDS_ STO_GEOCCS_ STO_GEOGCS_ STO_PRIMEMS_ STO_PROJCS_ STO_PROJECTIONS_ STO_SRS_ STO_USER_COLUMNS_ SYS_COLUMNS_ SYS_COMMENTS_ SYS_CONSTRAINTS_ SYS_CONSTRAINTS_ SYS_CONSTRAINT	SYSTEM	TABLE
SYSTEM_	STO_DATUMS_	SYSTEM	TABLE
SYSTEM_	STO_ELLIPSOIDS_	SYSTEM	
SYSTEM_	STO_GEOCCS_	SYSTEM	
SYSTEM_	STO_GEOGCS_	SYSTEM	
SYSTEM_	STO_PRIMEMS_	SYSTEM	
SYSTEM_	STO_PROJES_	SYSTEM	
SYSTEM_ SYSTEM	STO_PROJECTIONS_	SYSTEM SYSTEM	
SYSTEM_ SYSTEM	STO_SRS_	SYSTEM	
SYSTEM_ SYSTEM	SVS COLUMNS	SYSTEM	TABLE
SYSTEM	SYS COMMENTS	SYSTEM	TABLE
SYSTEM	SYS CONSTRAINTS	SYSTEM	
SYSTEM	SYS CONSTRAINT COLUMNS	SYSTEM	
SYSTEM	SYS DATABASE	SYSTEM	
SYSTEM	SYS DATABASE LINKS	SYSTEM	TABLE
SYSTEM_	SYS_DATA_PORTS_	SYSTEM	TABLE
SYSTEM_	SYS_DIRECTORIES_	SYSTEM	
SYSTEM_	SYS_DN_USERS_	SYSTEM	TABLE
SYSTEM_	SYS_DUMMY_	SYSTEM	TABLE
SYSTEM_	SYS_ENCRYPTED_COLUMNS_	SYSTEM	TABLE
SYSTEM_	SYS_GRANT_OBJECT_	SYSTEM	
SYSTEM_	SYS_GRANT_SYSTEM_	SYSTEM	
SYSTEM_	SYS_INDEX_COLUMNS_	SYSTEM	
SYSTEM_	SYS_INDEX_PARTITIONS_	SYSTEM SYSTEM	
SISIEM_ CVCTEM	SIS_INDICES_	SYSTEM	
SISIEM_	SIS_HOBS_	SYSTEM	
SYSTEM_	SYS PART KEY COLUMNS	SYSTEM	
SYSTEM	STO_USER_COLUMNS_ SYS_COLUMNS_ SYS_COMMENTS_ SYS_CONSTRAINTS_ SYS_CONSTRAINT_COLUMNS_ SYS_DATABASE_ SYS_DATABASE_LINKS_ SYS_DATA_PORTS_ SYS_DIRECTORIES_ SYS_DIRECTORIES_ SYS_DUMMY_ SYS_ENCRYPTED_COLUMNS_ SYS_GRANT_OBJECT_ SYS_GRANT_SYSTEM_ SYS_INDEX_COLUMNS_ SYS_INDEX_PARTITIONS_ SYS_INDEX_PARTITIONS_ SYS_INDICES_ SYS_PART_INDICES_ SYS_PART_INDICES_ SYS_PART_LOBS_ SYS_PART_LOBS_ SYS_PART_TABLES_ SYS_PART_TABLES_ SYS_PROC_PARAS_ SYS_PROC_PARAS_ SYS_PROC_PARAS_ SYS_PROC_PARAS_ SYS_REPL_HOSTS_ SYS_REPL_ITEMS_ SYS_REPL_OLD_COLUMNS_ SYS_REPL_OLD_INDEX_COLUMNS_ SYS_REPL_OLD_INDEX_COLUMNS_ SYS_REPL_OLD_INDEX_COLUMNS_ SYS_REPL_OLD_INDICES	SYSTEM	
SYSTEM	SYS PART TABLES	SYSTEM	
SYSTEM	SYS PRIVILEGES	SYSTEM	TABLE
SYSTEM	SYS_PROCEDURES_	SYSTEM	TABLE
SYSTEM_	SYS_PROC_PARAS_	SYSTEM	TABLE
SYSTEM_	SYS_PROC_PARSE_	SYSTEM	
SYSTEM_	SYS_PROC_RELATED_	SYSTEM	
SYSTEM_	SYS_REPLICATIONS_	SYSTEM	
SYSTEM_	SYS_REPL_HOSTS_	SYSTEM	
SYSTEM_	SYS_REPL_ITEMS_	SYSTEM	TABLE
SYSTEM_	SYS_REPL_OFFLINE_DIR_	SYSTEM SYSTEM	
SYSTEM_ SYSTEM	SYS_REPL_OLD_INDEX_COLUMNS_	SYSTEM	
SYSTEM_ SYSTEM	SYS_REPL_OLD_INDICES_	SYSTEM	
SYSTEM_	SYS REPL OLD ITEMS	SYSTEM	
	SYS REPL RECOVERY INFOS	SYSTEM	
SYSTEM	SYS SECURITY	SYSTEM	
SYSTEM	SYS SYNONYMS	SYSTEM	TABLE
_	SYS_TABLES_	SYSTEM	TABLE
SYSTEM_	SYS_TABLE_PARTITIONS_	SYSTEM	TABLE
SYSTEM_	SYS_TBS_USERS_	SYSTEM	TABLE
SYSTEM_	SYS_TRIGGERS_	SYSTEM	
SYSTEM_	SYS_TRIGGER_DML_TABLES_	SYSTEM	
	SYS_TRIGGER_STRINGS_	SYSTEM	
<del>-</del>	SYS_TRIGGER_UPDATE_COLUMNS_	SYSTEM	
SYSTEM_	SYS_USERS_	SYSTEM	
	SYS_VIEWS_ SYS_VIEW_PARSE_	SYSTEM	
	SYS_VIEW_PARSE_ SYS_VIEW_RELATED	SYSTEM SYSTEM	
SYSTEM_ SYSTEM	SYS_XA_HEURISTIC_TRANS_	SYSTEM	
ALTIADMIN	ALTITBL	TABLE	تاللاصلاءـ
SYS	SYSTBL	TABLE	

#### 2.3 Connecting and Disconnecting

```
CLEAR DP
                                             SYNONYM
             DUAL
                                             SYNONYM
             EXPORT_PARTITION_TO_FILE
EXPORT_TO_FILE
EXPORT_USER_TABLES
                                           SYNONYM
                                           SYNONYM
                                           SYNONYM
             FCLOSE
             FCLOSE ALL
                                           SYNONYM
                                           SYNONYM
             FCOPY
             FFLUSH
                                           SYNONYM
             FOPEN
                                            SYNONYM
             FREMOVE
                                             SYNONYM
                                            SYNONYM
             FRENAME
             GET LINE
                                            SYNONYM
             IMPORT_FROM_FILE
                                           SYNONYM
             IS OPEN
                                           SYNONYM
             NEW LINE
                                           SYNONYM
             PRINT
                                           SYNONYM
             PRINTLN
                                            SYNONYM
                                            SYNONYM
             PUT
                                           SYNONYM
SYNONYM
             PUT LINE
             RAISE_APPLICATION_ERROR
                                           SYNONYM
             REGISTER
             REMOVE
                                            SYNONYM
             REMOVEALL
                                           SYNONYM
             REMOVE DP
                                           SYNONYM
             REMOVE XID
                                           SYNONYM
                                           SYNONYM
             RESUME DP
                                           SYNONYM
             SET DEFAULTS
             SIGNAL
                                            SYNONYM
             SLEEP
                                            SYNONYM
             WAITANY
                                            SYNONYM
             WATTONE
                                            SYNONYM
93 rows selected.
```

#### 2.3.2 Disconnecting from a Database

DISCONNECT is used to terminate the current session and disconnect from the server. The result of all subsequently executed SQL statements will be a "Not connected" message, and "CONNECT use-rID/password" must be executed in order to connect to the server again.

```
DISCONNECT;
iSQL> INSERT INTO systbl VALUES(1, 'A1');
1 row inserted.
iSQL> INSERT INTO systbl VALUES(2, 'A2');
1 row inserted.
iSQL> SELECT * FROM systbl;
I1 I2
1 A1
          A2
2 rows selected.
iSQL> DISCONNECT;
Disconnect success.
iSQL> INSERT INTO systbl VALUES(3, 'A3');
[ERR-91020 : No Connection State]
iSQL> SELECT * FROM systbl;
[ERR-91020 : No Connection State]
iSOL> CONNECT sys/manager;
Connect success.
```

# 2.4 Retrieving Information Related to the Database and **Database Objects**

#### 2.4.1 Performance Views

A performance view is a type of data dictionary table capable of inquiring about the server status and database information. The following SELECT statement can be used to view the list of performance views provided by ALTIBASE HDB:

```
iSQL> SELECT * FROM v$tab;
 TABLE NAME
  ______
                                                                   PERFORMANCE VIEW
 V$ALLCOLUMN
 V$ARCHIVE
                                                                    PERFORMANCE VIEW
 V$BUFFPAGEINFO
                                                                    PERFORMANCE VIEW
 V$BUFFPOOL STAT
                                                                    PERFORMANCE VIEW
 V$CATALOG
                                                                   PERFORMANCE VIEW
PERFORMANCE VIEW
PERFORMANCE VIEW
V$DBA_2PC_PENDING
V$DBLINK_REMOTE_STATEMENT_INFO
V$DBLINK_REMOTE_TRANSACTION_INFO
PERFORMANCE VIEW
V$DBLINK_TRANSACTION_INFO
PERFORMANCE VIEW
V$DB_FREEPAGELISTS
PERFORMANCE VIEW
V$DB_PROTOCOL
PERFORMANCE VIEW
V$DIRECT_PATH_INSERT
PERFORMANCE VIEW
V$DISKTBL_INFO
PERFORMANCE VIEW
V$DISK_BTREE_HEADER
V$DISK_RTREE_HEADER
V$FILESTAT
                                                                   PERFORMANCE VIEW
 VSDATABASE
 V$FILESTAT
                                                                    PERFORMANCE VIEW
 V$FLUSHER
                                                                    PERFORMANCE VIEW
 V$FLUSHINFO
                                                                     PERFORMANCE VIEW
```

For the complete list of the performance views provided with ALTIBASE HDB and the meanings of the columns, please refer to the ALTIBASE HDB General Reference Chapter 3: Data Dictionary. Data in a particular performance view can be queried in the same way as an ordinary table using a SELECT statement, and using JOIN, etc., results can be output in various forms.

## 2.4.2 Viewing the List of Tables

Information on all of the tables that exist in the database can be retrieved using the following SELECT statement. The SYS TABLES meta table is an internal system table that contains information about the database catalog provided by ALTIBASE HDB.

```
iSQL> SELECT * FROM system_.sys_tables_;
iSQL> SELECT * FROM tab; -> This command is available in iSQL only. USER NAME TABLE NAME TYPE
```

## 2.4.3 Viewing a Table Structure

The following command is used to retrieve information on user-created tables:

```
DESC table name;
CREATE TABLE departments (
DNO SMALLINT PRIMARY KEY,
DNAME CHAR(30) NOT NULL,
DEP_LOCATION CHAR(9),
MGR_NO INTEGER );
iSQL> DESC departments; -> table_name: The name of a table whose information (table structure) you
want to know.
[ TABLESPACE : SYS TBS MEM DATA ]
[ ATTRIBUTE ]
                  TYPE
DNO SMALLINT FIXED NOT NULL
DNAME CHAR(30) FIXED NOT NULL
DEP_LOCATION CHAR(9) FIXED
MGR_NO INTEGER FIXED
[ INDEX ]
   _____
                 TYPE IS UNIQUE COLUMN
NAME
______
 _SYS_IDX_ID_122 BTREE UNIQUE
                                      DNO ASC
[ PRIMARY KEY ]
______
DNO
```

## 2.4.4 Viewing Sequence Information

The following commands are used to obtain information on all sequences that exist in the database:

```
SELECT * FROM seq;
iSQL> CONNECT sys/manager;
Connect success.
iSQL> CREATE USER user1 IDENTIFIED BY user1;
Create success.
iSQL> CONNECT user1/user1;
Connect success.
iSQL> CREATE SEQUENCE seq1 MAXVALUE 100 CYCLE;
Create success.
iSQL> CREATE SEQUENCE seq2;
Create success.
iSQL> CONNECT sys/manager;
Connect success.
iSQL> CREATE SEQUENCE seq2 START WITH 20 INCREMENT BY 30;
Create success.
iSQL> CREATE SEQUENCE seq3 CACHE 40;
Create success.
iSQL> SELECT * FROM seq;
                        -> When accessing the database using the SYS account, information
of all sequences will be displayed.
-----
SEQUENCE NAME
                                   CURRENT VALUE
______
INCREMENT_BY MIN_VALUE MAX_VALUE CYCLE
```

## 2.4 Retrieving Information Related to the Database and Database Objects

CACHE_SIZE			
SYS SEQ2 30 20	1	9223372036854775806	NO
SYS SEQ3 1 40 USER1	1	9223372036854775806	NO
SEQ1 1 20 USER1	1	100	YES
SEQ2 1 20 4 rows selected.	1	9223372036854775806	NO
iSQL> CONNECT use Connect success. iSQL> SELECT * FF SEQUENCE_NAME	ROM seq; -> Infor	mation of all sequences created by User 1 will b	
	MIN_VALUE	MAX_VALUE	CYCLE
CACHE_SIZE			
SEQ1 1 20	1	100	YES
SEQ2 1 20 2 rows selected.	1	9223372036854775806	NO

# 2.5 Controlling Transactions

## 2.5.1 Defining Transaction Modes

AUTOCOMMIT determines whether to automatically commit the results of a command at the time of execution

 ${\tt iSQL}{\gt}$  AUTOCOMMIT OFF; -> Commands are not automatically committed before being manually committed by the user.

Set autocommit off success.

 $\verb|iSQL> AUTOCOMMIT ON; -> Commands are automatically committed at the time of execution. \\ Set autocommit on success.$ 

#### 2.5.2 PLANCOMMIT

SET PLANCOMMIT [ON/OFF];

When EXPLAIN PLAN has been set to ON or ONLY, there is the possibility that the iSQL commands DESC; SELECT \* FROM TAB; or SELECT \* FROM SEQ; will be committed, even if AUTOCOMMIT has been set to OFF. This setting determines whether to commit them automatically.

This setting has been provided to overcome the misunderstanding where the user believes that such a command has not been prepared, but the system prepares the command in order to generate the execution plan. The command would then be committed, without the user knowing it, when a COMMIT command is executed later. When this value is OFF (which is the default) in a session for which EXPLAIN PLAN is ON (or ONLY) and AUTOCOMMIT is OFF, ALTIBASE HDB does not autocommit the above commands (DESC, SELECT \* FROM tab; or SELECT \* FROM seq;). When this value is ON, iSQL issues a special commit command to commit these commands.

# 2.6 File Management

## 2.6.1 Saving Results

iSQL enables results returned through iSQL to be saved in a designated file. In the following example, results are stored in the designated file, book.txt, using the SPOOL command.

To cancel this command, use the SPOOL OFF command.

```
iSQL> SPOOL book.txt
Spool start. [book.txt] -> All subsequently executed commands and their results will be written to book.txt. The file is created in the current directory.
iSQL> SPOOL OFF
Spool Stop -> From this point on, no more commands or results will be saved in the file.
```

## 2.6.2 Running Scripts

#### 2.6.2.1 @ Command

```
@ file_name[.sql]
or
START file name[.sql]
```

file\_name[.sql]: The script file to be executed. If the filename extension is omitted, iSQL assumes the default command file extension (.sql).

When this command is executed, , iSQL executes all of the commands in the specified script file in sequence.

@command performs the same function as START.

- An EXIT or QUIT command in the script file terminates iSQL.
- The script file may include general SQL statements, iSQL commands, references to stored procedures, etc.

The following is an example in which the schema.sql script, which can be found in the \$ALTIBASE\_HOME/sample/APRE/schema directory, which is the current directory, is executed.

```
isQL> START schema.sql -> The SQL statements in the file are executed.  \\ or  isQL> @schema.sql
```

When specifying a script file, you can use a question mark ("?") to indicate the ALTIBASE HDB home directory (\$ALTIBASE\_HOME) of the user account. The following is an example in which the schema.sql script, which can be found in the \$ALTIBASE\_HOME/sample/APRE/schema directory, is executed regardless of which directory is the current directory.

#### 2.6 File Management

```
iSQL> @?/sample/APRE/schema/schema.sql
```

The question mark ("?") can also be used with the following iSQL commands:

```
EDIT, SAVE, LOAD, SPOOL, START
```

The -- or /\* \*/ characters can be used to insert comments in script files. -- means that everything that follows until the end of the line will be handled as a comment, whereas comments that span several lines are placed between /\* and \*/.

#### 2.6.2.2 @@ Command

```
@@ file name[.sql]
```

*file\_name*[.*sql*]: This indicates the embedded script to be executed. If the extension is omitted, iSQL assumes the default command file extension(.sql).

Executes the specified script. The functionality of the @@ command is similar to that of the @ command.

This command searches for script files in the same path as the script currently being executed, and is thus useful for executing embedded scripts.

The @@ command can be used for the following purposes:

If a script file that contains the text @@file\_name.sql is executed, iSQL looks for the file specified by file\_name.sql, and executes its contents in sequence.

file\_name.sql must be located in the same directory as the script file that called it. If no such file exists, iSQL raises an error.

- If a user inputs @@file\_name.sql at the iSQL prompt, the result will be the same as when using iSQL to execute @file\_name.sql.
- The script typically may include SQL statements, iSQL commands, or stored procedures.
- An EXIT or QUIT command in the script terminates iSQL.

The following is an example of the execution of a.sql, in which schema.sql is referenced, from the \$ALTIBASE\_HOME directory. In order for this example to be executed without error, a.sql must exist in the \$ALTIBASE\_HOME/sample/APRE/schema directory alongside schema.sql.

```
iSQL> @sample/APRE/schema/a.sql
$ cat a.sql
@@schema.sql
```

Note: The following chapter provides examples of editing the results of a query in an iSQL environment based on the tables created by execution of the above script (see appendix Schema).

## 2.6.3 Saving SQL Statements

Of the commands currently in the iSQL buffer, the SAVE command saves the most recently executed one in a file.

This file will be created in the current directory.

```
iSQL> SELECT * FROM book; iSQL> SAVE book.sql -> 'SELECT * FROM book;' is saved in the file book.sql. Save completed.
```

## 2.6.4 Loading SQL Statements

This function loads the first command in the specified file to the last position in the iSQL buffer.

```
iSQL> LOAD book.sql
iSQL> SELECT * FROM book;
Load completed.

iSQL> / -> The results of execution of SELECT * FROM book; can be seen.
```

## 2.6.5 Saving DML Statements

Executed DML statements such as INSERT, UPDATE, DELETE and MOVE are saved in \$ALTIBASE\_HOME/trc/isql\_query.log.

Specify SET QUERYLOGGING ON to use this functionality and OFF to disable it.

```
iSQL> SET QUERYLOGGING ON; -> From this point on, all executed DML statements will be saved in
$ALTIBASE_HOME/trc/isql_query.log.
iSQL> CREATE TABLE t1 ( I1 INTEGER );
Create success.
iSQL> INSERT INTO t1 VALUES ( 1 );
1 row inserted.
iSQL> UPDATE t1 SET i1 = 2;
1 row updated.
iSQL> SELECT * FROM t1;
T1
1 row selected.
iSQL> DELETE FROM t1;
1 row deleted.
iSQL> DROP TABLE t1;
Drop success.
iSQL> EXIT
$ cat $ALTIBASE HOME/trc/isql query.log -> All queries executed since SET QUERYLOGGING ON
was executed can be observed.
[2009/09/16 10:36:14] [127.0.0.1:20300 SYS] INSERT INTO t1 VALUES ( 1 )
[2009/09/16 10:36:25] [127.0.0.1:20300 SYS] UPDATE t1 SET i1 = 2
[2009/09/16 10:36:31] [127.0.0.1:20300 SYS] DELETE FROM t1
```

## 2.6.6 Editing Query Statements

#### 2.6.6.1 Editing the Most Recent Query Statement

The command ed is provided for creating and editing files in iSQL.

If you execute ed without parameters, a temporary file named iSQL.buf containing the most recently executed query statements will be created, and the following screen will be visible. (To save

space, only a few of the blank lines that would be displayed on the screen are shown here.)

```
iSQL> SELECT sysdate FROM dual;
SYSDATE
------
01-JAN-2000
1 row selected.

iSQL> ED
SELECT sysdate FROM dual;
~
~
~
"iSQL.buf" 1L, 26C
```

#### 2.6.6.2 Editing Existing Files

If you want to edit an existing file, type the file name in iSQL as a parameter when launching the text editor using the "ed" command. When the screen is initialized, blank lines will be displayed as ~ (tilde) characters.

```
iSQL> ED myquery.sql
"myquery.sql"
INSERT INTO employees(ENO, E_FIRSTNAME, E_LASTNAME, SEX) VALUES(21, 'Shiloh',
'Reynolds', 'F');
INSERT INTO employees(ENO, E_FIRSTNAME, E_LASTNAME, SEX, JOIN_DATE) VAL-
UES(22, 'Joshua', 'Baldwin', 'M', TO_DATE('2001-11-19 00:00:00', 'YYYYY-MM-DD
HH:MI:SS'));
~
~"myquery.sql"
```

#### 2.6.6.3 Editing Query Statements in History Lists

You can use the number in the history list to edit previously executed commands. In detail, the query statements are stored in the temporary file iSQL.buf in association with numbers, and can be edited with reference to them. The edited query will be stored again as the most recent record in the history list, and can be executed by entering the '/' (re-execute) character.

```
iSQL> H
1 : SELECT * FROM customers;
2 : SELECT * FROM employees;
iSQL> 2ed

or
iSQL> 2 ed
SELECT * FROM employees;
~
~
"iSOL.buf"
```

Note: The command-line parameter 2, which is the name of the file to be edited (iSQL> ed 2), must be distinguished from the number indicating the line in the file to edit.

After editing (employees was replaced with orders)

```
iSQL> h -> The history list currently in the isql buffer
1 : SELECT * FROM customers;
2 : SELECT * FROM employees;
```

3 : SELECT \* FROM orders; -> The query statement edited using the 2 ed command will be saved as the last command in the history list.

iSQL> / -> The most recently executed command will be executed.

ONO		ORDER_DATE ENO	CNO
GNO	QTY	ARRIVAL_DATE	PROCESSING
11290007 A111100002	70	29-NOV-2010 12 02-DEC-2010	7111111431202 C
11290011 E111100001	1000	29-NOV-2010 12 05-DEC-2010	7610011000001 D
11290100 E111100001	500	29-NOV-2010 19 07-DEC-2010	7001011001001 D
12100277		10-DEC-2010 19	7610121220475
12310012 C111100001 30 rows sel	250 ected.	31-DEC-2010 19 03-JAN-2011	7308281201145 O

#### 2.6.6.4 Environment Variables for the Default Editor

You can set the environment variable ISQL\_EDITOR to use an editor other than the default editor (/ usr/bin/vi) .

```
Ex)
```

```
CSH: setenv ISQL_EDITOR usr/bin/ed SH: ISQL_EDITOR=/usr/bin/ed; export ISQL_EDITOR
```

# 2.7 Formatting SELECT Query Results

The results of a SELECT query can be formatted as desired by the user.

#### 2.7.1 SET LINESIZE

Sets the size (number of characters) of one line to be displayed when the results of a SELECT statement are output. It must be between 10 and 32767.

#### 2.7.2 SET LOBSIZE

This specifies the number of characters to display when a CLOB column is queried using a SELECT statement

In order to query CLOB column data using a SELECT statement, the transaction mode must first be set to AUTOCOMMIT OFF.

iSQL> SET LOBSIZE 10; -> This specifies the number of characters to display on the screen when querying a CLOB column using a SELECT statement.

#### 2.7.3 SET LOBOFFSET

This specifies the starting location from which to display CLOB data when a CLOB column is queried using a SELECT statement.

In order to query CLOB column data using a SELECT statement, the transaction mode must first be set to AUTOCOMMIT OFF.

```
iSQL> CREATE TABLE c1(I1 INTEGER, I2 CLOB);
INSERT INTO c1 VALUES(1, 'A123456789');
INSERT INTO c1 VALUES(2, 'A1234');
INSERT INTO c1 VALUES(3, 'A12345');
INSERT INTO c1 VALUES(4, 'A1234567890123');
iSQL> AUTOCOMMIT OFF
Set autocommit off success.
```

 ${\tt iSQL}{\gt}$  SET LOBOFFSET 4; -> This specifies the starting location of data to be shown on the screen number of characters to skip) when querying a CLOB column using a SELECT statement.

## 2.7.4 SET FEEDBACK

Outputs the number of records found when the results of a SELECT statement are output.

```
SET FEEDBACK ON OFF | n;
```

ON: Output the number of resultant records after execution of a SELECT statement.

OFF: Do not output the number of resultant records after execution of a SELECT statement.

n: Output the number of resultant records when the number is n or greater.

#### 2.7 Formatting SELECT Query Results

1	Moon	Chan-seung			
CEO	01195662365	3002		M	
	R				
2	Davenport	Susan			
designer	0113654540		1500	F	
721219 18	3-NOV-2009 H				
2 rows selected.					

## 2.7.5 SET PAGESIZE

Specifies the number of resultant rows to display at one time.

```
iSQL> SET PAGESIZE 2; -> Show results in groups comprising two rows each.
iSQL> select eno, e_firstname, e_lastname from employees;
ENO E_FIRSTNAME E_LASTNAME
1 Chan-seung Moon
2 Susan Davenport
ENO E_FIRSTNAME E_LASTNAME
3 Ken Kobain
4 Aaron Foster
ENO E_FIRSTNAME E_LASTNAME
----<del>-</del>
5 Farhad Ghorbani
6 Ryu Momoi
20 rows selected.
\verb"iSQL> SET PAGESIZE 0; -> Show all of the results on one page.
iSQL> select eno, e_firstname, e_lastname from employees;
ENO E_FIRSTNAME E_LASTNAME
1 Chan-seung Moon
2 Susan Davenpo
3 Ken Kobain
4 Aaron Foster
5 Farhad Ghorbai
                               Davenport
                                Ghorbani
6
           Ryu
                                Momoi
20 rows selected.
```

## 2.7.6 SET HEADING

Sets whether to output the header with a SELECT result.

```
iSQL> SET HEADING OFF; -> Header is not displayed with the result.
iSQL> select eno, e_firstname, e_lastname from employees;
         Chan-seung
Susan
Ken
                                Moon
                               Davenport
         Ken
                                Kobain
         Aaron
                                Foster
4
         Farhad
5
                                Ghorbani
6
           Ryu
                                 Momoi
```

```
20 rows selected.
iSQL> SET HEADING ON; -> Outputs header in result.
iSQL> select eno, e_firstname, e_lastname from employees;
ENO E FIRSTNAME E LASTNAME
______
1 Chan-seung Moon
2 Susan Daven
                         Dave...
Kobain
                          Davenport
        Ken
        Aaron
                          Foster
        Aaron
Farhad
                         Ghorbani
                          Momoi
        Ryu
20 rows selected.
```

#### 2.7.7 SET COLSIZE

When the results of a SELECT statement are output, sets the number of characters from a column of type CHAR or VARCHAR to display so that columns containing long lines of text can be easily viewed.

In the following example, the number of characters of a column of type CHAR or VARCHAR is set to 7:

# 2.8 Setting Output Options

## 2.8.1 Getting the Elapsed Time

This function displays the time it took to execute the SQL statement.

## 2.8.2 Setting Execution Time Units for Output

This function sets the units with which to output SQL statement execution time. Can be set to the following units:

- Seconds
- Milliseconds
- Microseconds
- Nanoseconds

iSQL> SET TIMING ON

```
Susan
2
                            Davenport
         Ken
                            Kobain
                            Foster
         Aaron
         Farhad
                            Ghorbani
6
                            Momoi
         Ryu
20 rows selected.
elapsed time : 0.72
iSQL> SET TIMESCALE MICSEC;
iSQL> select eno, e_firstname, e_lastname from employees;
ENO E_FIRSTNAME E_LASTNAME
    Chan-seung Moon
Susan Daver
Ken Koba
                          Davenport
                         Mobain
Foster
Ghor'
3
        Ken
     Ken
Aaron
Farhad
Ryu
4
5
                            Ghorbani
6
         Ryu
                            Momoi
20 rows selected.
elapsed time : 966.00
iSQL> SET TIMESCALE NANSEC;
iSQL> select eno, e_firstname, e_lastname from employees;
ENO E_FIRSTNAME E_LASTNAME
______
        Chan-seung Moon
Susan Daver
     Susan
Ken
Aaron
Farhad
Ryu
                          Davenport
3
                           Kobain
                           Foster
                       Ghorbani
6
                            Momoi
20 rows selected.
elapsed time : 681000.00
```

# 2.8.3 Describing Foreign Key Information

This function displays information on foreign keys when the DESC command is used to view the table structure.

COMMENT PRICE DATE_SEEN [ INDEX ]	VARCHAR ( INTEGER DATE		FIXED FIXED FIXED	NO	7 NULL
NAME	TYPE		QUE	COLUMN	
SYS_IDX_ID_143 [ PRIMARY KEY ]	BTREE			ITEM_ID	ASC
ITEM_ID					
[ FOREIGN KEYS ]					
* MODEL_ID	*SYS_I SYS.CANDI information v	DATE_MO	DELS (	MID )	
NAME	TYPE			IS	NULL
MID YEAR USED SOLD KMS SAW_WHERE ITEM_ID COMMENT	SMALLINT SMALLINT BIT (1) BIT (1) INTEGER VARCHAR ( INTEGER VARCHAR (	20)	FIXED FIXED FIXED FIXED FIXED FIXED FIXED	NOT	T NULL
PRICE DATE_SEEN [ INDEX ]	INTEGER DATE		FIXED FIXED	NO.	O NULL
NAME	TYPE	IS UNI	QUE		
	BTREE				ASC
ITEM_ID iSQL>					

# 2.8.4 Outputting Script Execution Results

Commands can be used to control the output of created results.

When set to OFF, this function prevents the result of a script command executed in iSQL from being displayed on the screen.

However, even if it is set OFF, the results of queries that are directly entered (e.g. iSQL> select \* from t1;) will still be displayed on the screen; the OFF setting only prevents script execution results (e.g.: iSQL> @a.sql) from being displayed.

```
iSQL> SET TERM OFF;
iSQL> SET TIMING ON; -> The execution time is not output to the screen.
iSQL> @schema.sql -> The script execution results are not output.
iSQL> select eno, e_firstname, e_lastname from employees;
-> The results of directly input queries will be output.
ENO E_FIRSTNAME E_LASTNAME
```

```
1
             Chan-seung
                                    Moon
             Susan
                                    Davenport
3
            Ken
                                    Kobain
4
            Aaron
                                    Foster
5
             Farhad
                                    Ghorbani
             Ryu
                                    Momoi
20 rows selected.
elapsed time : 0.00
iSQL> SET TERM ON; -> Script execution results will be output.
iSQL> @schema.sql
iSQL> ALTER SESSION SET AUTOCOMMIT = TRUE; -> Start of results.
Alter success.
iSQL> DROP TABLE ORDERS;
Drop success.
elapsed time : 0.00
iSQL> DROP TABLE EMPLOYEES;
Drop success.
elapsed time : 0.00
iSQL> CREATE INDEX ODR IDX3 ON ORDERS (GNO ASC);
Create success.
elapsed time : 0.00 -> End of results.
```

## 2.8.5 Outputting an Execution Plan

In iSQL, an execution plan can be output to fine-tune SQL statements. Using an execution plan, DML statements such as SELECT, INSERT, UPDATE and DELETE can be checked.

In order to accomplish this, the following command must be executed before a statement such as a SELECT statement is executed.

```
ALTER SESSION SET EXPLAIN PLAN = option
```

This option can be set to ON, OFF or ONLY. The default is OFF.

- ON: After the SELECT statement is executed, the execution plan information is displayed along with the resultant records.
- ONLY: The SELECT statement is prepared but not executed, and only the execution plan information is output. This can be used to check the execution plan for a SELECT statement that involves host variable binding, or to quickly check the execution plan for queries that take a long time to execute.
- OFF: After the SELECT statement is executed, only the resultant records are displayed.

The following command is used to obtain detailed information about how conditions included in WHERE clauses written by the user will be execute:

```
ALTER SYSTEM SET TRCLOG DETAIL PREDICATE = 1
```

If this property is set to 1, signifying "ON", as in the above statement, the execution plan's WHERE clause conditions, including FIXED KEY RANGE, VARIBALE KEY RANGE and FILTER, are classified and displayed in detail. Therefore, if the WHERE clause is complicated, you can check which predicates

will be executed by scanning the sorted indexes. However, this information may not be output if queries are changed to optimize them in some way.

The following example shows the output when the given SQL statement is executed:

When TRCLOG\_DETAIL\_PREDICATE has been set to 1 (=on), and EXPLAIN PLAN = ON, the following is output in addition to the results.

```
iSQL> ALTER SYSTEM SET TRCLOG DETAIL PREDICATE = 1;
Alter success.
iSQL> ALTER SESSION SET EXPLAIN PLAN = ON;
Alter success.
iSQL> select eno, e lastname, e firstname from employees where eno = 1;
ENO E_LASTNAME E_FIRSTNAME
1
                            Chan-seung
1 row selected.
PROJECT ( COLUMN COUNT: 3, TUPLE SIZE: 48 )
SCAN ( TABLE: EMPLOYEES, INDEX: SYS IDX ID 164, ACCESS: 1, SELF ID: 2
  [ FIXED KEY ]
 AND
  OR
   ENO = 1
               iSOL>
```

When TRCLOG\_DETAIL\_PREDICATE is not set to 1, and EXPLAIN PLAN = ON, the following is output in addition to the results.

 When TRCLOG\_DETAIL\_PREDICATE is not set to 1, and EXPLAIN PLAN = ONLY, only the following is output.

iSQL>

1 row selected.

If EXPLAIN PLAN = ONLY, because only an execution plan is created and the query is not executed, values that would be determined after actual execution are indicated using question marks ("??"), like an ACCESS clause.

## 2.8.6 Setting Result Output Orientation

When querying data using a SELECT statement in iSQL, the results can be displayed either horizontally or vertically.

This function is suitable for outputting results that comprise a small number of rows and many columns.

If such a result set is output horizontally, as is usually the case, it is difficult to compare columns and check the values. However, it is easy to see when output vertically.

```
iSQL> SET VERTICAL ON; --> This sets the print direction vertically.
iSQL> SELECT * FROM employees WHERE eno = 2;
ENO : 2
E_LASTNAME : Davenport
E_FIRSTNAME : Susan
EMP_JOB : designer
EMP_TEL : 0113654540
DNO :
SALARY : 1500
SEX : F
BIRTH : 721219
JOIN_DATE : 18-NOV-2009
STATUS : H
```

# 2.9 Viewing iSQL Display Settings

The following is an example of viewing the values of the iSQL environment variables for the current session:

```
isqL> show user -> This is the current user.
User : SYS
iSQL> SHOW COLSIZE
ColSize : 0
iSQL> SHOW LOBOFFSET
LobOffset: 0
iSQL> SHOW LINESIZE
LineSize : 80
iSOL> SHOW LOBSIZE
LobSize : 80
iSQL> SHOW PAGESIZE
PageSize : 0
iSQL> SHOW TIMESCALE
TimeScale : Second
iSQL> SHOW HEADING
Heading : On
iSQL> SHOW TIMING
Timing : Off
iSQL> SHOW VERTICAL
Vertical : Off
iSQL> SHOW FOREIGNKEYS
ForeignKeys : Off
iSQL> SHOW PLANCOMMIT
PlanCommit : Off
iSQL> SHOW QUERYLOGGING
QueryLogging : Off
iSQL> SHOW TERM
Term : On
iSQL> SHOW FEEDBACK
Feedback : 1
iSQL> SHOW ALL
User : SYS
ColSize : 0
LobOffset : 0
LineSize : 80
LobSize : 80
PageSize : 0
TimeScale : Second
Heading : On
Timing : Off
Vertical : Off
ForeignKeys : Off
```

PlanCommit : Off

## 2.9 Viewing iSQL Display Settings

QueryLogging : Off Term : On Feedback : 1

## 2.10 Host Variables

Host variables are first declared and then used. Host variables are useful when executing procedures or functions.

## 2.10.1 Declaring a Host Variable

#### 2.10.1.1 Syntax

```
VAR[IABLE] var name var type
```

#### 2.10.1.2 Type

The following types can be used when declaring variables:

```
INTEGER, BYTE(n), NIBBLE(n),
NUMBER, NUMBER(n), NUMBER(n,m),
NUMERIC, NUMERIC(n), NUMERIC(n,m),
CHAR(n), VARCHAR(n), NCHAR(n), NVARCHAR(n), DATE
DECIMAL, DECIMAL(n), DECIMAL(n,m),
FLOAT, FLOAT(n), DOUBLE, REAL
BIGINT, SMALLINT
```

#### 2.10.1.3 Example

The following examples demonstrate how to declare variables:

```
iSQL> VAR p1 INTEGER
iSQL> VAR p2 CHAR(10)
iSQL> VAR v_double DOUBLE
iSQL> VAR v_real REAL
```

## 2.10.2 Assigning a Value to a Host Variable

#### 2.10.2.1 Syntax

```
EXEC[UTE] :var name := value;
```

#### 2.10.2.2 Example

The following example shows how to assign a value to a variable:

```
iSQL> EXECUTE :p1 := 100;
Execute success.
iSQL> EXEC :p2 := 'abc';
Execute success.
```

# 2.10.3 Viewing Host Variables

## 2.10.3.1 Syntax

PRINT VAR[IABLE]

-> Shows all declared variables.

PRINT var\_name

-> Shows the type and value of the variable *var\_name*.

## 2.10.3.2 Example

The following shows the values of all declared variable:

iSQL> PRINT VAR [ HOST VARIABLE ]					
NAME	TYPE	VALUE			
P1 P2 V_REAL V_DOUBLE	INTEGER CHAR (10) REAL DOUBLE	100 abc			
iSQL> PRINT p2 -> Outputs only variable p2 information. NAME TYPE VALUE					
P2	CHAR (10)	abc			

# 2.11 Executing Prepared SQL Statements

## 2.11.1 Prepared SQL versus Dynamic SQL Statements

SQL statements executed in iSQL are usually executed according to the so-called "Direct Execution" method.

In Direct Execution, syntax analysis, validity testing, optimization and execution of a query are all performed at once. However, in Prepared Execution, only the syntax analysis, validity testing, and optimization of the query are performed to set up an execution plan for the query, which is then executed when requested by the client. When creating an application that uses ODBC, the Prepared Execution method is typically used, and is more advantageous in terms of speed when an SQL statement is to be repeatedly executed using host variable binding.

In iSQL, the difference between these two methods lies only in whether variables are used or not; there is no advantage in terms of speed.

## 2.11.2 Prepared SQL Statements

## 2.11.2.1 Syntax

PREPARE SQL statement

#### 2.11.2.2 Example

The following is an example of the use of the PREPARE command to execute an SQL statement:

```
iSQL> VAR t1 INTEGER;
iSQL> EXEC :t1 := 3;
Execute success.
iSQL> PREPARE SELECT eno, e_firstname, e_lastname, sex
  FROM employees
  WHERE eno=:t1;
ENO
        : 3
E_FIRSTNAME : Ken
E_LASTNAME : Kobain
SEX : M
1 row selected.
```

# 2.12 Creating, Executing and Dropping Stored Procedures

## 2.12.1 Creating Procedures

Support is provided for the creation and execution of stored procedures. A stored procedure must end with the following:

```
END;
```

Successful creation of the procedures can be confirmed by checking the <code>sys\_procedures\_meta</code> table

## 2.12.2 Executing Procedures

Procedures are executed in order to execute multiple queries at one time. If the procedure to be executed has parameters, as many variables as there are parameters must be declared before the procedure is executed.

#### 2.12.2.1 Example 1

In the following example, a procedure named emp\_proc, which executes an INSERT statement using IN parameters, is created:

```
iSQL> CREATE OR REPLACE PROCEDURE emp proc(p1 IN INTEGER, p2 IN CHAR(20), p3
IN CHAR(20), p4 IN CHAR(1))
AS
BEGIN
INSERT INTO employees(eno, e_firstname, e_lastname, sex)
VALUES(p1, p2, p3, p4);
END;
Create success.
iSQL> SELECT * FROM system_.sys_procedures_ order by created desc limit 1;
USER ID PROC OID
PROC_NAME
                               OBJECT_TYPE STATUS
_____
PARA_NUM RETURN_DATA_TYPE RETURN_LANG_ID RETURN_SIZE
______
RETURN PRECISION RETURN SCALE PARSE NO PARSE LEN CREATED
LAST_DDL_TIME
        3208680
EMP PROC
                                 0
                    192 29-FEB-2012
29-FEB-2012
1 row selected.
```

emp\_proc, which was created above, is executed:

#### 2.12 Creating, Executing and Dropping Stored Procedures

```
iSOL> VAR eno INTEGER
iSQL> VAR first name CHAR(20)
iSQL> VAR last_name CHAR(20)
iSQL> VAR sex CHAR(1)
iSQL> EXECUTE :eno := 21;
Execute success.
iSQL> EXECUTE :first name := 'Joel';
Execute success.
iSQL> EXECUTE :last_name := 'Johnson';
Execute success.
iSQL> EXECUTE :sex := 'M';
Execute success.
iSQL> EXECUTE emp_proc(:eno, :firstname, :lastname, :sex);
Execute success.
iSQL> SELECT eno, e_firstname, e_lastname, sex FROM employees WHERE eno = 21;
ENO E_FIRSTNAME E_LASTNAME SEX
ENO E FIRSTNAME
21 Joel
                           Johnson M
1 row selected.
```

#### 2.12.2.2 Example 2

In the following example, a procedure called outProc, which executes a SELECT statement, is created:

```
iSQL> CREATE TABLE outTbl(i1 INTEGER, i2 INTEGER);
Create success.
iSQL> INSERT INTO outTbl VALUES(1,1);
1 row inserted.
iSQL> /
1 row inserted.
iSQL> SELECT * FROM outTbl;
I1 I2
   1
1
1
1
1
            1
5 rows selected.
iSQL> CREATE OR REPLACE PROCEDURE outProc(a1 OUT INTEGER, a2 IN OUT INTEGER)
BEGIN
SELECT COUNT(*) INTO a1 FROM outTbl WHERE i2 = a2;
END;
Create success.
In the following example, outProc is executed:
```

iSQL> VAR t3 INTEGER iSQL> VAR t4 INTEGER iSQL> EXEC :t4 := 1; Execute success.

Execute success.
iSQL> PRINT t3;

iSQL> EXEC outProc (:t3, :t4);

NAME	TYPE	VALUE	
T3	INTEGER	5	

#### 2.12.2.3 Example 3

In the following example, the procedure outProc1 is created:

```
iSQL> CREATE OR REPLACE PROCEDURE outProc1( p1 INTEGER, p2 IN OUT INTEGER, p3
OUT INTEGER)
BEGIN
p2 := p1;
p3 := p1 + 100;
END;
Create success.
iSQL> VAR v1 INTEGER
iSQL> VAR v2 INTEGER
iSQL> VAR v3 INTEGER
iSQL> EXEC :v1 := 3;
Execute success.
iSQL> EXEC outProc1(:v1, :v2, :v3);
Execute success.
iSQL> PRINT VAR;
[ HOST VARIABLE ]
NAME
                TYPE
                           VALUE
-----
                                3
3
103
V1
                INTEGER
                INTEGER
V2
V3
                INTEGER
```

#### 2.12.2.4 Example 4

In the following example, a procedure called inoutProc1, which executes a SELECT statement, is created:

#### 2.12 Creating, Executing and Dropping Stored Procedures

#### 2.12.2.5 Example 5

In the following example, the procedure inoutProc1 is created:

```
iSQL> CREATE OR REPLACE PROCEDURE inoutProc1( p1 INTEGER, p2 IN OUT INTEGER,
p3 OUT INTEGER)
AS
BEGIN
   p2 := p1 + p2;
   p3 := p1 + 100;
END;
/
Create success.
```

In the following example, the procedure inoutProc1 is executed:

```
iSQL> VAR v1 INTEGER
iSQL> VAR v2 INTEGER
iSQL> VAR v3 INTEGER
iSQL> EXEC :v1 := 3;
Execute success.
iSQL> EXEC :v2 := 5;
Execute success.
iSQL> EXEC inoutProc1(:v1, :v2, :v3);
Execute success.
iSQL> PRINT VAR;
[ HOST VARIABLE ]
                   TYPE
NAME
                                        VALUE
                  INTEGER 3
INTEGER 8
INTEGER 103
V1
V2
V3
```

# 2.12.3 Dropping Procedures

The DROP command is used to drop (delete) procedures.

## 2.12 Creating, Executing and Dropping Stored Procedures

In the following example, the procedure emp\_proc is deleted:

iSQL> DROP PROCEDURE emp\_proc; Drop success.

# 2.13 Creating, Executing and Dropping Functions

## 2.13.1 Creating Functions

A function is provided to create functions. When creating a function, you must end with the following syntax, and the return type must be defined.

```
END;
```

Successful creation of the function can be confirmed by checking the sys\_procedures\_meta table.

In the following example, the function emp\_func, which executes an UPDATE statement and a SELECT statement, is created:

```
iSQL> CREATE OR REPLACE FUNCTION emp_func(f1 IN INTEGER)
RETURN NUMBER
AS
f2 NUMBER;
BEGIN
UPDATE employees SET salary = 1000000 WHERE eno = f1;
SELECT salary INTO f2 FROM employees WHERE eno = f1;
END;
Create success.
iSQL> SELECT * FROM system_.sys_procedures_;
USER ID PROC OID PROC NAME
______
OBJECT_TYPE STATUS PARA_NUM RETURN_DATA_TYPE RETURN LANG ID
RETURN_SIZE RETURN_PRECISION RETURN_SCALE PARSE_NO PARSE_LEN
______
        LAST_DDL_TIME
CREATED
       3300024 INOUTPROC1 0 3
                                  132
30000
209
15-SEP-2010 15-SEP-2010
36 rows selected.
```

## 2.13.2 Executing Functions

Functions can be executed to simultaneously execute multiple queries. If the function to be executed has parameters, as many variables as there are functions must be declared before the function is executed. Additionally, a variable for saving the result of the function must also be defined.

The following is an example of executing the function emp\_func:

## 2.13.3 Dropping Functions

The DROP FUNCTION statement is used to drop functions.

In the following example, the function emp\_func is deleted:

```
iSQL> DROP FUNCTION emp_func;
Drop success.
```

## 2.14 Convenient User Functions

## **2.14.1 History**

A list of all previously executed commands can be displayed using the HISTORY command. The number corresponding to a previously executed command can be used to easily execute that command again.

```
iSQL> HISTORY; ->View history list.

or

iSQL> H;
1 : SELECT * FROM tab;
2 : SELECT * FROM v$tab;

iSQL> / -> Re-execute the most recent command(HISTORY;))
iSQL> 2/ -> Execute Command number 2 in history list(SELECT * FROM book;)
```

#### 2.14.2 Shell Commands

The exclamation point ("!") is a convenient function that allows direct execution of most shell commands from within iSQL.

```
iSQL> !ls -al
total 3417
-rw-r----- 1 wlgml337 section 1198 Nov 1 13:30 .aliases
-rw------ 1 wlgml337 section 5353 Oct 18 21:17 .bash_history
-rw-r---- 1 wlgml337 section 1436 Nov 2 15:42 .bashrc
-rw-r---- 1 wlgml337 section 1549 Dec 13 17:36 .profile
drwxr-x--- 2 wlgml337 section 512 Nov 2 02:00 TEMP
drwxr-xr-x 2 root root 512 Oct 16 11:29 TT_DB
-rw------ 1 wlgml337 section 3446548 Dec 18 13:19 core
drwxr-x--- 2 wlgml337 section 512 Nov 11 16:33 cron
drwxr-x--- 2 wlgml337 section 512 Nov 15 10:52 test
drwxr-xr-x 6 wlgml337 section 512 Nov 11 11:45 work
```

## 2.14.3 Getting Help

Help is available for the commands provided with iSQL. The HELP command without parameters outputs information on how to use help. For help on specific commands, enter HELP followed by the name of the command for which help is desired.

```
iSQL> HELP;
Use 'help [command]'
Enter 'help index' for a list of command

iSQL> HELP INDEX;
@ EDIT QUIT
/ EXIT ROLLBACK
ALTER HEADING SAVE
AUTOCOMMIT H[ISTORY] SELECT
COMMIT INSERT SPOOL
CREATE LINESIZE START
DELETE LOAD TIMING
DESC LOBOFFSET UPDATE
```

#### 2.14 Convenient User Functions

DROP LOBSIZE VAR[IABLE]
EXECUTE MOVE TERM
EXPLAINPLAN PAGESIZE VERTICAL

iSQL> HELP EXIT; exit;

quit; - exit iSQL

# 2.15 Using National Character Sets

When using NCHAR and NVARCHAR type character constants, if the following environment variables settings are made, there will be no concerns over possible data loss.

The ALTIBASE\_NLS\_NCHAR\_LITERAL\_REPLACE environment variable must be set to 1.

```
$ export ALTIBASE NLS NCHAR LITERAL REPLACE=1
```

• In order to use NCHAR type data that are encoded differently from the database character set, enter the character "N" in front of the string.

## Index

G glogin.sql 17 ! 13 @ 10, 31 @@ 10, 32 / 13 **HEADING ON/OFF 38** HELP 13, 58 HISTORY 13, 58 ALTIBASE\_DATE\_FORMAT 15 host variable 13, 48 ALTIBASE\_HOME 14 ALTIBASE IPC FILEPATH 16 ALTIBASE\_NLS\_NCHAR\_LITERAL\_REPLACE 15, 60 iSQL 2 ALTIBASE NLS USE 14 iSQL Command 8 ALTIBASE\_PORT\_NO 14 iSQL Command Line Options 5 **AUTOCOMMIT ON/OFF 30** ISQL\_BUFFER\_SIZE 15 ISQL\_CONNECTION 15 C ISQL\_EDIT 35 COLSIZE 11, 39 ISQL\_EDITOR 16 comment 13 Configuring iSQL 17 L **CONNECT 23** LINESIZE 36 LOAD 33 load 10 DESC 9, 28 LOBOFFSET 11, 37 DISCONNECT 8, 26 LOBSIZE 11, 36 Display Settings 46 log in 20 drop procedure 54 login.sql 17 Ε ED 10, 33 national character process 60 EDIT 33 NCHAR 60 Edit query statements 10 **NVARCHAR 60** Editing the LOGIN file 17 END 51 P environment variables 14 PAGESIZE 38 EXEC 13, 48 performance view 27 EXECUTE 13, 48 PLANCOMMIT ON/OFF 30 Execution time 11 PREPARE 13 EXIT 8 PREPARE SQL statement 50 **EXPLAIN PLAN 43** PRINT 13, 49 procedure creation 51 procedure execution 51 FEEDBACK ON/OFF 37 FOREIGNKEYS ON/OFF 41 Formatting SELECT result 36 QUERYLOGGING ON/OFF 33 fuction 56 QUIT 8 function creation 56 function execution 56

re-execution 58

#### Repeat execution 13

## S

SAVE 10, 32 seq 28 sequence 28 Sequence information 9 set foreignkeys 11 set heading 11 set linesize 11 set pagesize 11 set term 11 set timing 11 Setting Up iSQL 3 Shell command 13 shell commands 58 show all 12 show foreignkeys 12 show heading 12 show linesize 12 show pagesize 12 show timing 12 show user 12 shutdown 8, 21 SPOOL 10, 31 START 10 startup 8, 21 Stop 8 stored procedure 51 SYSDBA 23

#### T

tab 9, 27
Table list 9
Table structure 9
TERM ON/OFF 42
TIMESCALE 40
TIMING ON/OFF 40
Transaction mode 9
transaction mode 30

#### V

VAR 48 VARIABLE 48 VERTICAL ON/OFF 45