
# 一、配置yum源

### 1. 下载mysql源安装包

下载地址: https://dev.mysql.com/downloads/repo/yum/



# MySQL Community Downloads

### Login Now or Sign Up for a free account.

An Oracle Web Account provides you with the following advantages:

- · Fast access to MySQL software downloads
- · Download technical White Papers and Presentations
- · Post messages in the MySQL Discussion Forums
- · Report and track bugs in the MySQL bug system



复制下载链接: https://dev.mysql.com/get/mysql80-community-release-el7-3.noarch.rpm

进入执行目录,这里的目录是:/home

执行下载命令:

wget https://dev.mysql.com/get/mysql80-community-release-el7-3.noarch.rpm

# 2. 安装mysql源

yum localinstall mysql80-community-release-el7-3.noarch.rpm

# 3. 检查是否安装成功

```
yum repolist enabled | grep "mysql.*-community.*"
```

```
[root@orderer0 ~]# yum repolist enabled | grep "mysql.*-community.*"
mysql-connectors-community/x86_64 MySQL Connectors Community
mysql-tools-community/x86_64 h MySQL Jooks Community
mysql80-community/x86_64 h MySQL 8.0 Community Server pet/qq_385913356
```

# 4. 安装mysql

yum install mysql-community-server

# 二、启动mysql服务

### 1. 启动

```
systemctl start mysqld
或者
service mysqld start
```

### 2. 查看启动状态

```
systemctl status mysqld
或
service mysqld status
```

### 3. 设置开机启动

```
systemctl enable mysqld
systemctl daemon-reload
```

## 三、配置以及部分命令

#### 1. 修改登录密码

mysql安装完成后,会在/var/log/mysqld.log文件中给root默认生成一个密码。通过下面方式找到root默认密码,然后登录mysql进行修改

```
grep 'temporary password' /var/log/mysqld.log
```

```
[root@orderer0 ~]# grep 'temporary password' /var/log/mysqld.log
2018-08-07T03:02:35.497567Z 5 [Note] [MY-010454] [Server] A temporary password is generated for root@localhost: cb?&qh>HA5mr
```

#### 本地登录mysql

```
mysql -u root -p
```

#### 输入上面查询出来的密码,回撤进入

修改密码(密码必须包含大小写字母、数字和特殊符号,并且长度不能少于8位):

```
ALTER USER 'root'@'localhost' IDENTIFIED BY 'TestBicon@123';
或
set password for 'root'@'localhost'=password('TestBicon@123');
```

#### 2. 添加远程登录用户

```
use mysql;
select host, user from user;
```

```
GRANT ALL ON *.* TO 'root'@'%';
或
update user set host='%' where user ='root';
```

```
flush privileges;//命令刷新
```

### 3. Navicat、SQLyog连接时出错

### 登录客户端,执行下面的命令:

```
ALTER USER 'root'@'localhost' IDENTIFIED WITH mysql_native_password BY 'password';
```

如果报错: ERROR 1396 (HY000): Operation ALTER USER failed for 'root'@'localhost'则使用下面命令:

```
ALTER USER 'root'@'%' IDENTIFIED WITH mysql_native_password BY 'password';
```

#### 4. 修改默认编码格式

mysql8.0默认编码方式为utf8mb4,因此使用时不需要修改,可使用如下命令查看:

```
SHOW VARIABLES WHERE Variable_name LIKE 'character_set_%' OR Variable_name LIKE 'collation%';
```

# 5. 查找mysql配置文件my.cnf

```
mysql --help|grep 'my.cnf'
```

# 四、卸载mysql

# 1. 卸载软件

```
yum remove mysql-community-server
```

完成后使用rpm -qa|grep mysq|命令查看,如果有查询结果,则使用yum remove 名称清理掉。如图:

```
[root@peer0:lib] # rpm -qa|grep mysql
mysql-community-common-8.0.12-1.el7.x86_64
mysql-community-libs-8.0.12-1.el7.x86_64
mysql80-community-release-el7-1.noarch
mysql-community-client-8.0.12-1.el7.x86_64
[root@peer0:lib] # yum remove mysql-community-common-8.0.12-1.el7.x86_64
Loaded plugins: fastestmirror, langpacks
```

再使用命令rpm -qa | grep -i mysql查看,如果有结果使用rpm -e 名称卸载。如下:

```
[root@peer0:lib] # rpm -qa | grep -i mysql
perl-DBD-MySQL-4.023-6.el7.x86_64
[root@peer0:lib] # rpm he peri-DBD-MySQLd4.023-6.el78x86_64
```

#### 2. 删除文件

```
rm -rf /var/lib/mysql
rm /etc/my.cnf
rm -rf /usr/share/mysql-8.0
```

如果需要重新安装,在安装完成启动之前可以先对mysql目录赋予权限防止异常发生:

```
chmod -R 777 /var/lib/mysql
```

# 五、附加

#### 1. systemctl命令

```
systemctl is-enabled iptables.service
systemctl is-enabled servicename.service #查询服务是否开机启动
systemctl enable *.service #开机运行服务
systemctl disable *.service #取消开机运行
systemctl start *.service #启动服务
systemctl stop *.service #停止服务
systemctl restart *.service #重启服务
```

```
systemctl reload *.service #重新加载服务配置文件 systemctl status *.service #查询服务运行状态 systemctl --failed #显示启动失败的服务
```

# 六、参考

https://blog.csdn.net/qq\_38591756/article/details/82958333 https://blog.csdn.net/qq\_38567039/article/details/90090111