在RHEL5安裝NTOP

文@Lawrence Chiu

1.首先請先至rpmfind.net抓取給RHEL5所使用的NTOP,筆者的系統少安裝了glib套件,故自己抓下source rpm 來rebuild。

[root@new-host-6 tmp]# rpm -ivh ntop-3.2-2.el5.rf.i386.rpm warning: ntop-3.2-2.el5.rf.i386.rpm: Header V3 DSA signature: NOKEY, key ID 6b8d79e6 error: Failed dependencies:

libglib-1.2.so.0 is needed by ntop-3.2-2.el5.rf.i386

[root@new-host-6 tmp]# rpmbuild --rebuild glib-1.2.10-15.src.rpm

Rebuild書而跳過

[root@new-host-6 tmp]# cd /usr/src/redhat/RPMS/i386/

[root@new-host-6 i386]# ll

total 516

-rw-r--r-- 1 root root 145245 Apr 10 20:08 glib-1.2.10-15.i386.rpm

-rw-r--r-- 1 root root 236817 Apr 10 20:08 glib-debuginfo-1.2.10-15.i386.rpm

-rw-r--r-- 1 root root 129049 Apr 10 20:08 glib-devel-1.2.10-15.i386.rpm

[root@new-host-6 i386]# rpm -ivh *

Preparing... ########################## [100%]
1:glib ##################### [33%]
2:glib-debuginfo ############################# [67%]
3:glib-devel ################################## [100%]

[root@new-host-6 tmp]# rpm -ivh ntop-3.2-2.el5.rf.i386.rpm

warning: ntop-3.2-2.el5.rf.i386.rpm: Header V3 DSA signature: NOKEY, key ID 6b8d79e6

Preparing... ########################### [100%]
1:ntop ####################### [100%]

2. 備份ntop.conf

[root@new-host-6 tmp]# cp /etc/ntop.conf /etc/ntop.conf.bak

3.建立NTOP儲存db的資料夾:

[root@new-host-6 tmp]# mkdir /var/www/html/ntop

[root@new-host-6 tmp]# chown ntop.ntop /var/www/html/ntop

4.啟動NTOP:

啟動NTOP的方法有兩種,一種是依照/etc/ntop.conf的設定並透過/etc/init.d/ntop start 來啟動,另一種則是以命令列的方法啟動NTOP,第一種方法筆者有遇過啟動後一點反應也沒有,用status來看,也沒有任何的訊息,用echo \$?才知道指令執行的結果是失敗的,但卻不知原因為何?於是乎,我個人偏愛用命令列的方式啟動NTOP。第一次啟動NTOP時會要求輸入帳號與密碼,請用admin/admin輸入即可。

[root@new-host-6 tmp]# ntop -P /var/www/html/ntop/ -u nobody

啟動畫面跳過,跑到一半時會要求輸入密碼


ntop startup - waiting for user response!

Please enter the password for the admin user:

Please enter the password again:

5.瀏覽NTOP website:

預設的port為3000,如果您要自訂port的話,請在啟動NTOP時,加上一個參數,-w 比如說如果我要把它改成6000的話,可以這樣做: ntop -P /var/www/html/ntop -u nobody -w 6000接下來開啟瀏覽器,輸入 http://IP address:3000,就可以看到NTOP的流量統計的網頁。



後記:

更多有關於NTOP的參數,請參考man page。