Certbot Documentation

Release 0.16.0.dev0

Certbot Project

CONTENTS

1	Introduction	1
	1.1 Contributing	1
	1.2 Installation	1
	1.3 How to run the client	1
	1.4 Understanding the client in more depth	2
2	Get Certbot	3
	2.1 About Certbot	3
	2.2 System Requirements	3
	2.3 Alternate installation methods	4
3	User Guide	7
	3.1 Certbot Commands	7
	3.2 Getting certificates (and choosing plugins)	8
	3.3 Managing certificates	12
		16
	3.5 Pre and Post Validation Hooks	17
	3.6 Configuration file	19
	3.7 Certbot command-line options	19
	3.8 Getting help	30
4	Developer Guide	31
	4.1 Getting Started	32
	4.2 Code components and layout	33
		35
	4.4 Submitting a pull request	35
	4.5 Updating certbot-auto and letsencrypt-auto	36
	4.6 Updating the documentation	36
	4.7 Running the client with Docker	36
	4.8 Notes on OS dependencies	37
5	Packaging Guide	39
	5.1 Releases	39
	5.2 Notes for package maintainers	39
	5.3 Already ongoing efforts	40
6	Resources	43
7	API Documentation	45
		45
		46

	7.3	certbot.auth_handler	47
	7.4	certbot.client	50
	7.5	certbot.configuration	54
	7.6	certbot.constants	54
	7.7	certbot.crypto_util	55
	7.8	certbot.display	59
	7.9	certbot.errors	66
	7.10	certbot	68
	7.11	certbot.interfaces	68
	7.12	certbot.plugins.common	77
	7.13	certbot.plugins.disco	79
	7.14	certbot.plugins.dns_common	80
	7.15	certbot.plugins.dns_common_lexicon	82
	7.16	certbot.plugins.manual	83
	7.17	certbot.plugins.standalone	83
	7.18	certbot.plugins.util	85
	7.19	certbot.plugins.webroot	85
	7.20	certbot.reporter	85
	7.21	certbot.reverter	86
	7.22	certbot.storage	89
	7.23	certbot.util	96
8	Indic	es and tables	103
Py	thon N	Module Index	105
Inc	dex		107

CHAPTER

ONE

INTRODUCTION

Certbot is part of EFF's effort to encrypt the entire Internet. Secure communication over the Web relies on HTTPS, which requires the use of a digital certificate that lets browsers verify the identity of web servers (e.g., is that really google.com?). Web servers obtain their certificates from trusted third parties called certificate authorities (CAs). Certbot is an easy-to-use client that fetches a certificate from Let's Encrypt—an open certificate authority launched by the EFF, Mozilla, and others—and deploys it to a web server.

Anyone who has gone through the trouble of setting up a secure website knows what a hassle getting and maintaining a certificate is. Certbot and Let's Encrypt can automate away the pain and let you turn on and manage HTTPS with simple commands. Using Certbot and Let's Encrypt is free, so there's no need to arrange payment.

How you use Certbot depends on the configuration of your web server. The best way to get started is to use our interactive guide. It generates instructions based on your configuration settings. In most cases, you'll need root or administrator access to your web server to run Certbot.

If you're using a hosted service and don't have direct access to your web server, you might not be able to use Certbot. Check with your hosting provider for documentation about uploading certificates or using certificates issued by Let's Encrypt.

Certbot is a fully-featured, extensible client for the Let's Encrypt CA (or any other CA that speaks the ACME protocol) that can automate the tasks of obtaining certificates and configuring webservers to use them. This client runs on Unix-based operating systems.

Until May 2016, Certbot was named simply letsencrypt or letsencrypt-auto, depending on install method. Instructions on the Internet, and some pieces of the software, may still refer to this older name.

1.1 Contributing

If you'd like to contribute to this project please read Developer Guide.

1.2 Installation

The easiest way to install Certbot is by visiting certbot.eff.org, where you can find the correct installation instructions for many web server and OS combinations. For more information, see Get Certbot.

1.3 How to run the client

In many cases, you can just run certbot-auto or certbot, and the client will guide you through the process of obtaining and installing certs interactively.

For full command line help, you can type:

```
./certbot-auto --help all
```

You can also tell it exactly what you want it to do from the command line. For instance, if you want to obtain a cert for example.com, www.example.com, and other.example.net, using the Apache plugin to both obtain and install the certs, you could do this:

```
./certbot-auto --apache -d example.com -d www.example.com -d other.example.net
```

(The first time you run the command, it will make an account, and ask for an email and agreement to the Let's Encrypt Subscriber Agreement; you can automate those with --email and --agree-tos)

If you want to use a webserver that doesn't have full plugin support yet, you can still use "standalone" or "webroot" plugins to obtain a certificate:

```
./certbot-auto certonly --standalone --email admin@example.com -d example.com -d www. \rightarrowexample.com -d other.example.net
```

1.4 Understanding the client in more depth

To understand what the client is doing in detail, it's important to understand the way it uses plugins. Please see the explanation of plugins in the User Guide.

1.4.1 Links

Documentation: https://certbot.eff.org/docs

Software project: https://github.com/certbot/certbot

Notes for developers: https://certbot.eff.org/docs/contributing.html

Main Website: https://certbot.eff.org

Let's Encrypt Website: https://letsencrypt.org

IRC Channel: #letsencrypt on Freenode

Community: https://community.letsencrypt.org
ACME spec: http://ietf-wg-acme.github.io/acme/

ACME working area in github: https://github.com/ietf-wg-acme/acme

1.4.2 System Requirements

See https://certbot.eff.org/docs/install.html#system-requirements.

CHAPTER

TWO

GET CERTBOT

Table of Contents

- · About Certbot
- System Requirements
- Alternate installation methods
 - Certbot-Auto
 - Problems with Python virtual environment
 - Running with Docker
 - Operating System Packages
 - Installing from source

2.1 About Certbot

Certbot is packaged for many common operating systems and web servers. Check whether certbot (or letsencrypt) is packaged for your web server's OS by visiting certbot.eff.org, where you will also find the correct installation instructions for your system.

Note: Unless you have very specific requirements, we kindly suggest that you use the Certbot packages provided by your package manager (see certbot.eff.org). If such packages are not available, we recommend using certbot-auto, which automates the process of installing Certbot on your system.

2.2 System Requirements

Certbot currently requires Python 2.6, 2.7, or 3.3+. By default, it requires root access in order to write to /etc/letsencrypt, /var/log/letsencrypt, /var/lib/letsencrypt; to bind to ports 80 and 443 (if you use the standalone plugin) and to read and modify webserver configurations (if you use the apache or nginx plugins). If none of these apply to you, it is theoretically possible to run without root privileges, but for most users who want to avoid running an ACME client as root, either letsencrypt-nosudo or simp_le are more appropriate choices.

The Apache plugin currently requires an OS with augeas version 1.0; currently it supports modern OSes based on Debian, Fedora, SUSE, Gentoo and Darwin.

Installing with certbot-auto requires 512MB of RAM in order to build some of the dependencies. Installing from pre-built OS packages avoids this requirement. You can also temporarily set a swap file. See "Problems with Python virtual environment" below for details.

2.3 Alternate installation methods

If you are offline or your operating system doesn't provide a package, you can use an alternate method for installing certbot.

2.3.1 Certbot-Auto

The certbot-auto wrapper script installs Certbot, obtaining some dependencies from your web server OS and putting others in a python virtual environment. You can download and run it as follows:

```
user@webserver:~$ wget https://dl.eff.org/certbot-auto
user@webserver:~$ chmod a+x ./certbot-auto
user@webserver:~$ ./certbot-auto --help
```

Hint: The certbot-auto download is protected by HTTPS, which is pretty good, but if you'd like to double check the integrity of the certbot-auto script, you can use these steps for verification before running it:

```
user@server:~$ wget -N https://dl.eff.org/certbot-auto.asc
user@server:~$ gpg2 --recv-key A2CFB51FA275A7286234E7B24D17C995CD9775F2
user@server:~$ gpg2 --trusted-key 4D17C995CD9775F2 --verify certbot-auto.asc certbot-auto
```

The certbot-auto command updates to the latest client release automatically. Since certbot-auto is a wrapper to certbot, it accepts exactly the same command line flags and arguments. For more information, see Certbot command-line options.

For full command line help, you can type:

```
./certbot-auto --help all
```

2.3.2 Problems with Python virtual environment

On a low memory system such as VPS with less than 512MB of RAM, the required dependencies of Certbot will failed to build. This can be identified if the pip outputs contains something like internal compiler error: Killed (program ccl). You can workaround this restriction by creating a temporary swapfile:

```
user@webserver:~$ sudo fallocate -1 1G /tmp/swapfile
user@webserver:~$ sudo chmod 600 /tmp/swapfile
user@webserver:~$ sudo mkswap /tmp/swapfile
user@webserver:~$ sudo swapon /tmp/swapfile
```

Disable and remove the swapfile once the virtual environment is constructed:

```
user@webserver:~$ sudo swapoff /tmp/swapfile user@webserver:~$ sudo rm /tmp/swapfile
```

2.3.3 Running with Docker

Docker is an amazingly simple and quick way to obtain a certificate. However, this mode of operation is unable to install certificates or configure your webserver, because our installer plugins cannot reach your webserver from inside the Docker container.

Most users should use the operating system packages (see instructions at certbot.eff.org) or, as a fallback, certbot-auto. You should only use Docker if you are sure you know what you are doing and have a good reason to do so.

You should definitely read the *Where are my certificates*? section, in order to know how to manage the certs manually. Our ciphersuites page provides some information about recommended ciphersuites. If none of these make much sense to you, you should definitely use the *certbot-auto* method, which enables you to use installer plugins that cover both of those hard topics.

If you're still not convinced and have decided to use this method, from the server that the domain you're requesting a cert for resolves to, install Docker, then issue the following command:

Running Certbot with the certonly command will obtain a certificate and place it in the directory /etc/letsencrypt/live on your system. Because Certonly cannot install the certificate from within Docker, you must install the certificate manually according to the procedure recommended by the provider of your webserver.

For more information about the layout of the /etc/letsencrypt directory, see Where are my certificates?.

2.3.4 Operating System Packages

Arch Linux

```
sudo pacman -S certbot
```

Debian

If you run Debian Stretch or Debian Sid, you can install certbot packages.

```
sudo apt-get update
sudo apt-get install certbot python-certbot-apache
```

If you don't want to use the Apache plugin, you can omit the python-certbot-apache package.

Packages exist for Debian Jessie via backports. First you'll have to follow the instructions at http://backports.debian. org/Instructions/ to enable the Jessie backports repo, if you have not already done so. Then run:

```
sudo apt-get install certbot python-certbot-apache -t jessie-backports
```

Fedora

```
sudo dnf install certbot python2-certbot-apache
```

FreeBSD

- Port: cd /usr/ports/security/py-certbot && make install clean
- Package: pkg install py27-certbot

Gentoo

The official Certbot client is available in Gentoo Portage. If you want to use the Apache plugin, it has to be installed separately:

```
emerge -av app-crypt/certbot
emerge -av app-crypt/certbot-apache
```

When using the Apache plugin, you will run into a "cannot find a cert or key directive" error if you're sporting the default Gentoo httpd.conf. You can fix this by commenting out two lines in /etc/apache2/httpd.conf as follows:

Change

```
<IfDefine SSL>
LoadModule ssl_module modules/mod_ssl.so
</IfDefine>
```

to

```
#<IfDefine SSL>
LoadModule ssl_module modules/mod_ssl.so
#</IfDefine>
```

For the time being, this is the only way for the Apache plugin to recognise the appropriate directives when installing the certificate. Note: this change is not required for the other plugins.

NetBSD

- Build from source: cd /usr/pkgsrc/security/py-certbot && make install clean
- Install pre-compiled package: pkg_add py27-certbot

OpenBSD

- Port: cd /usr/ports/security/letsencrypt/client && make install clean
- Package: pkg add letsencrypt

Other Operating Systems

OS packaging is an ongoing effort. If you'd like to package Certbot for your distribution of choice please have a look at the *Packaging Guide*.

2.3.5 Installing from source

Installation from source is only supported for developers and the whole process is described in the *Developer Guide*.

Warning: Please do not use python setup.py install or python pip install .. Please do not attempt the installation commands as superuser/root and/or without virtual environment, e.g. sudo python setup.py install, sudo pip install, sudo ./venv/bin/.... These modes of operation might corrupt your operating system and are not supported by the Certbot team!

THREE

USER GUIDE

Table of Contents

- Certbot Commands
- Getting certificates (and choosing plugins)
 - Apache
 - Webroot
 - Nginx
 - Standalone
 - Manual
 - Third-party plugins
- Managing certificates
 - Re-creating and Updating Existing Certificates
 - Changing a Certificate's Domains
 - Revoking certificates
 - Renewing certificates
 - Modifying the Renewal Configuration File
- Where are my certificates?
- Pre and Post Validation Hooks
- Configuration file
- Certbot command-line options
- Getting help

3.1 Certbot Commands

Certbot uses a number of different commands (also referred to as "subcommands") to request specific actions such as obtaining, renewing, or revoking certificates. The most important and commonly-used commands will be discussed throughout this document; an exhaustive list also appears near the end of the document.

The certbot script on your web server might be named letsencrypt if your system uses an older package, or certbot—auto if you used an alternate installation method. Throughout the docs, whenever you see certbot, swap in the correct name as needed.

3.2 Getting certificates (and choosing plugins)

The Certbot client supports two types of plugins for obtaining and installing certificates: authenticators and installers.

Authenticators are plugins used with the certonly command to obtain a certificate. The authenticator validates that you control the domain(s) you are requesting a certificate for, obtains a certificate for the specified domain(s), and places the certificate in the /etc/letsencrypt directory on your machine. The authenticator does not install the certificate (it does not edit any of your server's configuration files to serve the obtained certificate). If you specify multiple domains to authenticate, they will all be listed in a single certificate. To obtain multiple separate certificates you will need to run Certbot multiple times.

Installers are Plugins used with the install command to install a certificate. These plugins can modify your webserver's configuration to serve your website over HTTPS using certificates obtained by certbot.

Plugins that do both can be used with the certbot run command, which is the default when no command is specified. The run subcommand can also be used to specify a combination of distinct authenticator and installer plugins.

Plugin	Auth	Inst	Notes	Challenge types (and port)
apache	Y	Y	Automates obtaining and installing a certificate with Apache 2.4 on Debian-based distributions with libaugeas0 1.0+.	tls-sni-01 (443)
webroot	Y	N	Obtains a certificate by writing to the webroot directory of an already running webserver.	http-01 (80)
nginx	Y	Y	Automates obtaining and installing a certificate with Nginx. Shipped with Certbot 0.9.0.	tls-sni-01 (443)
standalone	Y	N	Uses a "standalone" webserver to obtain a certificate. Requires port 80 or 443 to be available. This is useful on systems with no webserver, or when direct integration with the local webserver is not supported or not desired.	http-01 (80) or tls- sni-01 (443)
manual	Y	N	Helps you obtain a certificate by giving you instructions to perform domain	http-01 (80) or dns- 01 (53)
.2. Getting ce	rtificates (and choo	osing plugins)	validation yourself. Additionally allows you to specify scripts to	

automate the

Under the hood, plugins use one of several ACME protocol challenges to prove you control a domain. The options are http-01 (which uses port 80), tls-sni-01 (port 443) and dns-01 (requiring configuration of a DNS server on port 53, though that's often not the same machine as your webserver). A few plugins support more than one challenge type, in which case you can choose one with --preferred-challenges.

There are also many *third-party-plugins* available. Below we describe in more detail the circumstances in which each plugin can be used, and how to use it.

3.2.1 Apache

The Apache plugin currently requires an OS with augeas version 1.0; currently it supports modern OSes based on Debian, Fedora, SUSE, Gentoo and Darwin. This automates both obtaining *and* installing certificates on an Apache webserver. To specify this plugin on the command line, simply include —apache.

3.2.2 Webroot

If you're running a local webserver for which you have the ability to modify the content being served, and you'd prefer not to stop the webserver during the certificate issuance process, you can use the webroot plugin to obtain a certificate by including certonly and --webroot on the command line. In addition, you'll need to specify --webroot-path or -w with the top-level directory ("web root") containing the files served by your webserver. For example, --webroot-path /var/www/html or --webroot-path /usr/share/nginx/html are two common webroot paths.

If you're getting a certificate for many domains at once, the plugin needs to know where each domain's files are served from, which could potentially be a separate directory for each domain. When requesting a certificate for multiple domains, each domain will use the most recently specified ——webroot-path. So, for instance,

```
certbot certonly --webroot -w /var/www/example/ -d www.example.com -d example.com -w / -var/www/other -d other.example.net -d another.other.example.net
```

would obtain a single certificate for all of those names, using the /var/www/example webroot directory for the first two, and /var/www/other for the second two.

The webroot plugin works by creating a temporary file for each of your requested domains in \${webroot-path}/.well-known/acme-challenge. Then the Let's Encrypt validation server makes HTTP requests to validate that the DNS for each requested domain resolves to the server running certbot. An example request made to your web server would look like:

```
66.133.109.36 - - [05/Jan/2016:20:11:24 -0500] "GET /.well-known/acme-challenge/

HGR8U1IeTW4kY_Z6UIyaakzOkyQgPr_7ArlLgtZE8SX HTTP/1.1" 200 87 "-" "Mozilla/5.0"

Compatible; Let's Encrypt validation server; +https://www.letsencrypt.org)"
```

Note that to use the webroot plugin, your server must be configured to serve files from hidden directories. If /. well-known is treated specially by your webserver configuration, you might need to modify the configuration to ensure that files inside /.well-known/acme-challenge are served by the webserver.

3.2.3 Nginx

The Nginx plugin has been distributed with Certbot since version 0.9.0 and should work for most configurations. We recommend backing up Nginx configurations before using it (though you can also revert changes to configurations with certbot --nginx rollback). You can use it by providing the --nginx flag on the commandline.

```
certbot --nginx
```

3.2.4 Standalone

Use standalone mode to obtain a certificate if you don't want to use (or don't currently have) existing server software. The standalone plugin does not rely on any other server software running on the machine where you obtain the certificate.

To obtain a certificate using a "standalone" webserver, you can use the standalone plugin by including certonly and —standalone on the command line. This plugin needs to bind to port 80 or 443 in order to perform domain validation, so you may need to stop your existing webserver. To control which port the plugin uses, include one of the options shown below on the command line.

- --preferred-challenges http to use port 80
- --preferred-challenges tls-sni to use port 443

It must still be possible for your machine to accept inbound connections from the Internet on the specified port using each requested domain name.

Note: The --standalone-supported-challenges option has been deprecated since certbot version 0.9.0.

3.2.5 Manual

If you'd like to obtain a certificate running certbot on a machine other than your target webserver or perform the steps for domain validation yourself, you can use the manual plugin. While hidden from the UI, you can use the plugin to obtain a certificate by specifying certonly and --manual on the command line. This requires you to copy and paste commands into another terminal session, which may be on a different computer.

The manual plugin can use either the http or the dns challenge. You can use the --preferred-challenges option to choose the challenge of your preference. The http challenge will ask you to place a file with a specific name and specific content in the /.well-known/acme-challenge/ directory directly in the top-level directory ("web root") containing the files served by your webserver. In essence it's the same as the *webroot* plugin, but not automated. When using the dns challenge, certbot will ask you to place a TXT DNS record with specific contents under the domain name consisting of the hostname for which you want a certificate issued, prepended by _acme-challenge.

For example, for the domain example.com, a zone file entry would look like:

```
_acme-challenge.example.com. 300 IN TXT "gfj9Xq...Rg85nM"
```

Additionally you can specify scripts to prepare for validation and perform the authentication procedure and/or clean up after it by using the --manual-auth-hook and --manual-cleanup-hook flags. This is described in more depth in the *hooks* section.

3.2.6 Third-party plugins

There are also a number of third-party plugins for the client, provided by other developers. Many are beta/experimental, but some are already in widespread use:

Plugin	Auth	Inst	Notes
plesk	Y	Y	Integration with the Plesk web hosting tool
haproxy	Y	Y	Integration with the HAProxy load balancer
s3front	Y	Y	Integration with Amazon CloudFront distribution of S3 buckets
gandi	Y	Y	Integration with Gandi's hosting products and API
varnish	Y	N	Obtain certificates via a Varnish server
external	Y	N	A plugin for convenient scripting (See also ticket 2782)
icecast	N	Y	Deploy certificates to Icecast 2 streaming media servers
pritunl	N	Y	Install certificates in pritunl distributed OpenVPN servers
proxmox	N	Y	Install certificates in Proxmox Virtualization servers
postfix	N	Y	STARTTLS Everywhere is becoming a Certbot Postfix/Exim plugin
heroku	Y	Y	Integration with Heroku SSL

If you're interested, you can also write your own plugin.

3.3 Managing certificates

To view a list of the certificates Certbot knows about, run the certificates subcommand:

certbot certificates

This returns information in the following format:

```
Found the following certs:
    Certificate Name: example.com
    Domains: example.com, www.example.com
    Expiry Date: 2017-02-19 19:53:00+00:00 (VALID: 30 days)
    Certificate Path: /etc/letsencrypt/live/example.com/fullchain.pem
    Private Key Path: /etc/letsencrypt/live/example.com/privkey.pem
```

Certificate Name shows the name of the certificate. Pass this name using the --cert-name flag to specify a particular certificate for the run, certonly, certificates, renew, and delete commands. Example:

```
certbot certonly --cert-name example.com
```

3.3.1 Re-creating and Updating Existing Certificates

You can use certonly or run subcommands to request the creation of a single new certificate even if you already have an existing certificate with some of the same domain names.

If a certificate is requested with run or certonly specifying a certificate name that already exists, Certbot updates the existing certificate. Otherwise a new certificate is created and assigned the specified name.

The --force-renewal, --duplicate, and --expand options control Certbot's behavior when re-creating a certificate with the same name as an existing certificate. If you don't specify a requested behavior, Certbot may ask you what you intended.

--force-renewal tells Certbot to request a new certificate with the same domains as an existing certificate. Each domain must be explicitly specified via -d. If successful, this certificate is saved alongside the earlier one and symbolic links (the "live" reference) will be updated to point to the new certificate. This is a valid method of renewing a specific individual certificate.

--duplicate tells Certbot to create a separate, unrelated certificate with the same domains as an existing certificate. This certificate is saved completely separately from the prior one. Most users will not need to issue this command in normal circumstances.

--expand tells Certbot to update an existing certificate with a new certificate that contains all of the old domains and one or more additional new domains.

--allow-subset-of-names tells Certbot to continue with certificate generation if only some of the specified domain authorizations can be obtained. This may be useful if some domains specified in a certificate no longer point at this system.

Whenever you obtain a new certificate in any of these ways, the new certificate exists alongside any previously obtained certificates, whether or not the previous certificates have expired. The generation of a new certificate counts against several rate limits that are intended to prevent abuse of the ACME protocol, as described here.

3.3.2 Changing a Certificate's Domains

The --cert-name flag can also be used to modify the domains a certificate contains, by specifying new domains using the -d or --domains flag. If certificate example.com previously contained example.com and www.example.com, it can be modified to only contain example.com by specifying only example.com with the -d or --domains flag. Example:

```
certbot certonly --cert-name example.com -d example.com
```

The same format can be used to expand the set of domains a certificate contains, or to replace that set entirely:

```
certbot certonly --cert-name example.com -d example.org, www.example.org
```

3.3.3 Revoking certificates

If your account key has been compromised or you otherwise need to revoke a certificate, use the revoke command to do so. Note that the revoke command takes the certificate path (ending in cert.pem), not a certificate name or domain. Example:

```
certbot revoke --cert-path /etc/letsencrypt/live/CERTNAME/cert.pem
```

Additionally, if a certificate is a test certificate obtained via the <code>--staging</code> or <code>--test-cert</code> flag, that flag must be passed to the <code>revoke</code> subcommand. Once a certificate is revoked (or for other certificate management tasks), all of a certificate's relevant files can be removed from the system with the <code>delete</code> subcommand:

```
certbot delete --cert-name example.com
```

Note: If you don't use delete to remove the certificate completely, it will be renewed automatically at the next renewal event.

3.3.4 Renewing certificates

Note: Let's Encrypt CA issues short-lived certificates (90 days). Make sure you renew the certificates at least once in 3 months.

As of version 0.10.0, Certbot supports a renew action to check all installed certificates for impending expiry and attempt to renew them. The simplest form is simply

```
certbot renew
```

This command attempts to renew any previously-obtained certificates that expire in less than 30 days. The same plugin and options that were used at the time the certificate was originally issued will be used for the renewal attempt, unless you specify other plugins or options. Unlike certonly, renew acts on multiple certificates and always takes into account whether each one is near expiry. Because of this, renew is suitable (and designed) for automated use, to allow your system to automatically renew each certificate when appropriate. Since renew only renews certificates that are near expiry it can be run as frequently as you want - since it will usually take no action.

The renew command includes hooks for running commands or scripts before or after a certificate is renewed. For example, if you have a single certificate obtained using the *standalone* plugin, you might need to stop the webserver before renewing so standalone can bind to the necessary ports, and then restart it after the plugin is finished. Example:

```
certbot renew --pre-hook "service nginx stop" --post-hook "service nginx start"
```

If a hook exits with a non-zero exit code, the error will be printed to stderr but renewal will be attempted anyway. A failing hook doesn't directly cause Certbot to exit with a non-zero exit code, but since Certbot exits with a non-zero exit code when renewals fail, a failed hook causing renewal failures will indirectly result in a non-zero exit code. Hooks will only be run if a certificate is due for renewal, so you can run the above command frequently without unnecessarily stopping your webserver.

--pre-hook and --post-hook hooks run before and after every renewal attempt. If you want your hook to run only after a successful renewal, use --renew-hook in a command like this.

```
certbot renew --renew-hook /path/to/renew-hook-script
```

For example, if you have a daemon that does not read its certificates as the root user, a renew hook like this can copy them to the correct location and apply appropriate file permissions.

/path/to/renew-hook-script

```
#!/bin/sh
set -e
for domain in $RENEWED_DOMAINS; do
        case $domain in
        example.com)
                daemon_cert_root=/etc/some-daemon/certs
                # Make sure the certificate and private key files are
                # never world readable, even just for an instant while
                # we're copying them into daemon_cert_root.
                umask 077
                cp "$RENEWED_LINEAGE/fullchain.pem" "$daemon_cert_root/$domain.cert"
                cp "$RENEWED_LINEAGE/privkey.pem" "$daemon_cert_root/$domain.key"
                # Apply the proper file ownership and permissions for
                # the daemon to read its certificate and key.
                chown some-daemon "$daemon_cert_root/$domain.cert" \
                        "$daemon_cert_root/$domain.key"
                chmod 400 "$daemon_cert_root/$domain.cert" \
                        "$daemon_cert_root/$domain.key"
                service some-daemon restart >/dev/null
                ;;
        esac
done
```

More information about renewal hooks can be found by running certbot --help renew.

If you're sure that this command executes successfully without human intervention, you can add the command to crontab (since certificates are only renewed when they're determined to be near expiry, the command can run on a regular basis, like every week or every day). In that case, you are likely to want to use the -q or --quiet quiet flag to silence all output except errors.

If you are manually renewing all of your certificates, the --force-renewal flag may be helpful; it causes the expiration time of the certificate(s) to be ignored when considering renewal, and attempts to renew each and every installed certificate regardless of its age. (This form is not appropriate to run daily because each certificate will be renewed every day, which will quickly run into the certificate authority rate limit.)

Note that options provided to certbot renew will apply to *every* certificate for which renewal is attempted; for example, certbot renew --rsa-key-size 4096 would try to replace every near-expiry certificate with an equivalent certificate using a 4096-bit RSA public key. If a certificate is successfully renewed using specified options, those options will be saved and used for future renewals of that certificate.

An alternative form that provides for more fine-grained control over the renewal process (while renewing specified certificates one at a time), is certbot certonly with the complete set of subject domains of a specific certificate specified via -d flags. You may also want to include the -n or --noninteractive flag to prevent blocking on user input (which is useful when running the command from cron).

```
certbot certonly -n -d example.com -d www.example.com
```

All of the domains covered by the certificate must be specified in this case in order to renew and replace the old certificate rather than obtaining a new one; don't forget any www. domains! Specifying a subset of the domains creates a new, separate certificate containing only those domains, rather than replacing the original certificate. When run with a set of domains corresponding to an existing certificate, the certonly command attempts to renew that specific certificate.

Please note that the CA will send notification emails to the address you provide if you do not renew certificates that are about to expire.

Certbot is working hard to improve the renewal process, and we apologize for any inconvenience you encounter in integrating these commands into your individual environment.

Note: certbot renew exit status will only be 1 if a renewal attempt failed. This means certbot renew exit status will be 0 if no cert needs to be updated. If you write a custom script and expect to run a command only after a cert was actually renewed you will need to use the --post-hook since the exit status will be 0 both on successful renewal and when renewal is not necessary.

3.3.5 Modifying the Renewal Configuration File

For advanced certificate management tasks, it is possible to manually modify the certificate's renewal configuration file, located at /etc/letsencrypt/renewal/CERTNAME.

Warning: Modifying any files in /etc/letsencrypt can damage them so Certbot can no longer properly manage its certificates, and we do not recommend doing so.

For most tasks, it is safest to limit yourself to pointing symlinks at the files there, or using --renew-hook to copy / make new files based upon those files, if your operational situation requires it (for instance, combining certificates and keys in different way, or having copies of things with different specific permissions that are demanded by other programs).

If the contents of /etc/letsencrypt/archive/CERTNAME are moved to a new folder, first specify the new folder's name in the renewal configuration file, then run certbot update_symlinks to point the symlinks in

/etc/letsencrypt/live/CERTNAME to the new folder.

If you would like the live certificate files whose symlink location Certbot updates on each run to reside in a different location, first move them to that location, then specify the full path of each of the four files in the renewal configuration file. Since the symlinks are relative links, you must follow this with an invocation of certbot update_symlinks.

For example, say that a certificate's renewal configuration file previously contained the following directives:

```
archive_dir = /etc/letsencrypt/archive/example.com
cert = /etc/letsencrypt/live/example.com/cert.pem
privkey = /etc/letsencrypt/live/example.com/privkey.pem
chain = /etc/letsencrypt/live/example.com/chain.pem
fullchain = /etc/letsencrypt/live/example.com/fullchain.pem
```

The following commands could be used to specify where these files are located:

3.4 Where are my certificates?

All generated keys and issued certificates can be found in /etc/letsencrypt/live/\$domain. Rather than copying, please point your (web) server configuration directly to those files (or create symlinks). During the *renewal*, /etc/letsencrypt/live is updated with the latest necessary files.

Note: /etc/letsencrypt/archive and /etc/letsencrypt/keys contain all previous keys and certificates, while /etc/letsencrypt/live symlinks to the latest versions.

The following files are available:

privkey.pem Private key for the certificate.

Warning: This **must be kept secret at all times!** Never share it with anyone, including Certbot developers. You cannot put it into a safe, however - your server still needs to access this file in order for SSL/TLS to work.

This is what Apache needs for SSLCertificateKeyFile, and Nginx for ssl_certificate_key.

fullchain.pem All certificates, **including** server certificate (aka leaf certificate or end-entity certificate). The server certificate is the first one in this file, followed by any intermediates.

This is what Apache >= 2.4.8 needs for SSLCertificateFile, and what Nginx needs for ssl_certificate.

cert.pem and chain.pem (less common) cert.pem contains the server certificate by itself, and chain.pem
contains the additional intermediate certificate or certificates that web browsers will need in order to validate the
server certificate. If you provide one of these files to your web server, you must provide both of them, or some
browsers will show "This Connection is Untrusted" errors for your site, some of the time.

Apache < 2.4.8 needs these for SSLCertificateFile. and SSLCertificateChainFile, respectively.

If you're using OCSP stapling with Nginx >= 1.3.7, chain.pem should be provided as the ssl_trusted_certificate to validate OCSP responses.

Note: All files are PEM-encoded. If you need other format, such as DER or PFX, then you could convert using openssl. You can automate that with --renew-hook if you're using automatic *renewal*.

3.5 Pre and Post Validation Hooks

Certbot allows for the specification of pre and post validation hooks when run in manual mode. The flags to specify these scripts are --manual-auth-hook and --manual-cleanup-hook respectively and can be used as follows:

```
certbot certonly --manual --manual-auth-hook /path/to/http/authenticator.sh --manual- \rightarrow cleanup-hook /path/to/http/cleanup.sh -d secure.example.com
```

This will run the authenticator.sh script, attempt the validation, and then run the cleanup.sh script. Additionally certbot will pass three environment variables to these scripts:

- CERTBOT_DOMAIN: The domain being authenticated
- CERTBOT_VALIDATION: The validation string
- CERTBOT_TOKEN: Resource name part of the HTTP-01 challenge (HTTP-01 only)

Additionally for cleanup:

• CERTBOT_AUTH_OUTPUT: Whatever the auth script wrote to stdout

Example usage for HTTP-01:

```
certbot certonly --manual --preferred-challenges=http --manual-auth-hook /path/to/

http/authenticator.sh --manual-cleanup-hook /path/to/http/cleanup.sh -d secure.

example.com
```

/path/to/http/authenticator.sh

```
#!/bin/bash echo $CERTBOT_VALIDATION > /var/www/htdocs/.well-known/acme-challenge/$CERTBOT_TOKEN
```

/path/to/http/cleanup.sh

```
#!/bin/bash
rm -f /var/www/htdocs/.well-known/acme-challenge/$CERTBOT_TOKEN
```

Example usage for DNS-01 (Cloudflare API v4) (for example purposes only, do not use as-is)

```
certbot certonly --manual --preferred-challenges=dns --manual-auth-hook /path/to/dns/ \rightarrow authenticator.sh --manual-cleanup-hook /path/to/dns/cleanup.sh -d secure.example.com
```

/path/to/dns/authenticator.sh

```
#!/bin/bash

# Get your API key from https://www.cloudflare.com/a/account/my-account
```

```
API_KEY="your-api-key"
EMAIL="your.email@example.com"
# Strip only the top domain to get the zone id
DOMAIN=$(expr match "$CERTBOT_DOMAIN" '.*\.\(.*\..*\)')
# Get the Cloudflare zone id
ZONE_EXTRA_PARAMS="status=active&page=1&per_page=20&order=status&direction=desc&
→match=all"
ZONE_ID=$(curl -s -X GET "https://api.cloudflare.com/client/v4/zones?name=$DOMAIN&
→$ZONE_EXTRA_PARAMS" \
    -H
           "X-Auth-Email: $EMAIL" \
     -H
            "X-Auth-Key: $API_KEY" \
    -H
            "Content-Type: application/json" | python -c "import sys, json; print (json.
→load(sys.stdin)['result'][0]['id'])")
# Create TXT record
CREATE_DOMAIN="_acme-challenge.$CERTBOT_DOMAIN"
RECORD_ID=$(curl -s -X POST "https://api.cloudflare.com/client/v4/zones/$ZONE_ID/dns_
→records" \
            "X-Auth-Email: $EMAIL" \
    -H
    -H
           "X-Auth-Key: $API_KEY" \
    -H
            "Content-Type: application/json" \
     --data '{"type":"TXT", "name":"'"$CREATE_DOMAIN"'", "content":"'"$CERTBOT_
→VALIDATION"'","ttl":120}' \
            | python -c "import sys, json; print(json.load(sys.stdin)['result']['id'])
→")
# Save info for cleanup
if [ ! -d /tmp/CERTBOT_$CERTBOT_DOMAIN ]; then
       mkdir -m 0700 /tmp/CERTBOT_$CERTBOT_DOMAIN
fi
echo $ZONE_ID > /tmp/CERTBOT_$CERTBOT_DOMAIN/ZONE_ID
echo $RECORD_ID > /tmp/CERTBOT_$CERTBOT_DOMAIN/RECORD_ID
# Sleep to make sure the change has time to propagate over to DNS
sleep 25
```

/path/to/dns/cleanup.sh

```
curl -s -X DELETE "https://api.cloudflare.com/client/v4/zones/$ZONE_ID/dns_

→records/$RECORD_ID" \

-H "X-Auth-Email: $EMAIL" \

-H "X-Auth-Key: $API_KEY" \

-H "Content-Type: application/json"

fi

fi
```

3.6 Configuration file

It is possible to specify configuration file with certbot-auto --config cli.ini (or shorter -c cli.ini). An example configuration file is shown below:

```
# This is an example of the kind of things you can do in a configuration file.
# All flags used by the client can be configured here. Run Certbot with
# "--help" to learn more about the available options.
# Note that these options apply automatically to all use of Certbot for
# obtaining or renewing certificates, so options specific to a single
# certificate on a system with several certificates should not be placed
# here.
# Use a 4096 bit RSA key instead of 2048
rsa-kev-size = 4096
# Uncomment and update to register with the specified e-mail address
# email = foo@example.com
# Uncomment to use the standalone authenticator on port 443
# authenticator = standalone
# standalone-supported-challenges = tls-sni-01
# Uncomment to use the webroot authenticator. Replace webroot-path with the
# path to the public_html / webroot folder being served by your web server.
# authenticator = webroot
# webroot-path = /usr/share/nginx/html
```

By default, the following locations are searched:

- /etc/letsencrypt/cli.ini
- \$XDG_CONFIG_HOME/letsencrypt/cli.ini (or ~/.config/letsencrypt/cli.ini if \$XDG_CONFIG_HOME is not set).

3.7 Certbot command-line options

Certbot supports a lot of command line options. Here's the full list, from certbot --help all:

```
usage:
    certbot [SUBCOMMAND] [options] [-d DOMAIN] [-d DOMAIN] ...

Certbot can obtain and install HTTPS/TLS/SSL certificates. By default, it will attempt to use a webserver both for obtaining and installing the certificate. The most common SUBCOMMANDS and flags are:
```

```
obtain, install, and renew certificates:
    (default) run Obtain & install a certificate in your current webserver
   certonly Obtain or renew a certificate, but do not install it
                   Renew all previously obtained certificates that are near expiry
   renew
  -d DOMAINS
                   Comma-separated list of domains to obtain a certificate for
                   Use the Apache plugin for authentication & installation
 --apache
 --standalone
                  Run a standalone webserver for authentication
 --nainx
                   Use the Nginx plugin for authentication & installation
                  Place files in a server's webroot folder for authentication
 --webroot
  --manual
                   Obtain certificates interactively, or using shell script hooks
                   Run non-interactively
                   Obtain a test certificate from a staging server
  --test-cert
                   Test "renew" or "certonly" without saving any certificates to disk
 --dry-run
manage certificates:
   certificates Display information about certificates you have from Certbot
   revoke
                  Revoke a certificate (supply --cert-path)
   delete
                  Delete a certificate
manage your account with Let's Encrypt:
   register
               Create a Let's Encrypt ACME account
                  Agree to the ACME server's Subscriber Agreement
  --agree-tos
  -m EMAIL
                  Email address for important account notifications
optional arguments:
 -h, --help
                       show this help message and exit
 -c CONFIG_FILE, --config CONFIG_FILE
                      path to config file (default: /etc/letsencrypt/cli.ini
                       and ~/.config/letsencrypt/cli.ini)
 -v, --verbose
                       This flag can be used multiple times to incrementally
                       increase the verbosity of output, e.g. -vvv. (default:
 -n, --non-interactive, --noninteractive
                       Run without ever asking for user input. This may
                       require additional command line flags; the client will
                       try to explain which ones are required if it finds one
                       missing (default: False)
                       Force Certbot to be interactive even if it detects
  --force-interactive
                       it's not being run in a terminal. This flag cannot be
                       used with the renew subcommand. (default: False)
 -d DOMAIN, --domains DOMAIN, --domain DOMAIN
                       Domain names to apply. For multiple domains you can
                       use multiple -d flags or enter a comma separated list
                       of domains as a parameter. (default: Ask)
  --cert-name CERTNAME Certificate name to apply. Only one certificate name
                       can be used per Certbot run. To see certificate names,
                       run 'certbot certificates'. When creating a new
                       certificate, specifies the new certificate's name.
                       (default: None)
  --dry-run
                       Perform a test run of the client, obtaining test
                       (invalid) certificates but not saving them to disk.
                       This can currently only be used with the 'certonly'
                       and 'renew' subcommands. Note: Although --dry-run
                       tries to avoid making any persistent changes on a
                       system, it is not completely side-effect free: if used
```

with webserver authenticator plugins like apache and nginx, it makes and then reverts temporary config changes in order to obtain test certificates, and reloads webservers to deploy and then roll back those changes. It also calls --pre-hook and --post-hook commands if they are defined because they may be necessary to accurately simulate renewal. --renew-hook commands are not called. (default: False) --debug-challenges After setting up challenges, wait for user input before submitting to CA (default: False) --preferred-challenges PREF_CHALLS A sorted, comma delimited list of the preferred challenge to use during authorization with the most preferred challenge listed first (Eq, "dns" or "tlssni-01, http, dns"). Not all plugins support all challenges. See https://certbot.eff.org/docs/using.html#plugins for details. ACME Challenges are versioned, but if you pick "http" rather than "http-01", Certbot will select the latest version automatically. (default: []) --user-agent USER_AGENT Set a custom user agent string for the client. User agent strings allow the CA to collect high level statistics about success rates by OS, plugin and use case, and to know when to deprecate support for past Python versions and flags. If you wish to hide this information from the Let's Encrypt server, set this to "". (default: CertbotACMEClient/0.15.0 (certbot; Ubuntu 16.04.2 LTS) Authenticator/XXX Installer/YYY (SUBCOMMAND; flags: FLAGS) Py/2.7.12). The flags encoded in the user agent are: --duplicate, --forcerenew, --allow-subset-of-names, -n, and whether any hooks are set. automation: Arguments for automating execution & other tweaks --keep-until-expiring, --keep, --reinstall If the requested certificate matches an existing certificate, always keep the existing one until it is due for renewal (for the 'run' subcommand this means reinstall the existing certificate). (default: Ask) If an existing certificate is a strict subset of the --expand requested names, always expand and replace it with the additional names. (default: Ask) --version show program's version number and exit --force-renewal, --renew-by-default If a certificate already exists for the requested domains, renew it now, regardless of whether it is near expiry. (Often --keep-until-expiring is more appropriate). Also implies --expand. (default: False) --renew-with-new-domains If a certificate already exists for the requested certificate name but does not match the requested domains, renew it now, regardless of whether it is near expiry. (default: False) --allow-subset-of-names When performing domain validation, do not consider it

```
a failure if authorizations can not be obtained for a
                        strict subset of the requested domains. This may be
                        useful for allowing renewals for multiple domains to
                        succeed even if some domains no longer point at this
                        system. This option cannot be used with --csr.
                        (default: False)
  --agree-tos
                        Agree to the ACME Subscriber Agreement (default: Ask)
  --duplicate
                       Allow making a certificate lineage that duplicates an
                        existing one (both can be renewed in parallel)
                        (default: False)
                        (certbot-auto only) install OS package dependencies
 --os-packages-only
                        and then stop (default: False)
                       (certbot-auto only) prevent the certbot-auto script
  --no-self-upgrade
                        from upgrading itself to newer released versions
                        (default: Upgrade automatically)
  --no-bootstrap
                        (certbot-auto only) prevent the certbot-auto script
                        from installing OS-level dependencies (default: Prompt
                        to install OS-wide dependencies, but exit if the user
                        says 'No')
 -q, --quiet
                        Silence all output except errors. Useful for
                        automation via cron. Implies --non-interactive.
                        (default: False)
security:
 Security parameters & server settings
  --rsa-key-size N
                        Size of the RSA key. (default: 2048)
                        Adds the OCSP Must Staple extension to the
  --must-staple
                        certificate. Autoconfigures OCSP Stapling for
                        supported setups (Apache version >= 2.3.3 ). (default:
                        False)
  --redirect
                        Automatically redirect all HTTP traffic to HTTPS for
                        the newly authenticated vhost. (default: Ask)
  --no-redirect
                        Do not automatically redirect all HTTP traffic to
                        HTTPS for the newly authenticated vhost. (default:
                        Ask)
                        Add the Strict-Transport-Security header to every HTTP
  --hsts
                        response. Forcing browser to always use SSL for the
                        domain. Defends against SSL Stripping. (default:
                        False)
                        Add the "Content-Security-Policy: upgrade-insecure-
  --uir
                        requests" header to every HTTP response. Forcing the
                        browser to use https:// for every http:// resource.
                        (default: None)
                        Enables OCSP Stapling. A valid OCSP response is
  --staple-ocsp
                        stapled to the certificate that the server offers
                        during TLS. (default: None)
  --strict-permissions Require that all configuration files are owned by the
                        current user; only needed if your config is somewhere
                        unsafe like /tmp/ (default: False)
testing:
 The following flags are meant for testing and integration purposes only.
  --test-cert, --staging
                        Use the staging server to obtain or revoke test
                        (invalid) certificates; equivalent to --server https
                        ://acme-staging.api.letsencrypt.org/directory
```

```
(default: False)
                        Show tracebacks in case of errors, and allow certbot-
  --debug
                        auto execution on experimental platforms (default:
                        False)
                        Disable verification of the ACME server's certificate.
  --no-verify-ssl
                        (default: False)
  --tls-sni-01-port TLS_SNI_01_PORT
                        Port used during tls-sni-01 challenge. This only
                        affects the port Certbot listens on. A conforming ACME
                        server will still attempt to connect on port 443.
                        (default: 443)
  --tls-sni-01-address TLS_SNI_01_ADDRESS
                        The address the server listens to during tls-sni-01
                        challenge. (default: )
 --http-01-port HTTP01_PORT
                        Port used in the http-01 challenge. This only affects
                        the port Certbot listens on. A conforming ACME server
                        will still attempt to connect on port 80. (default:
                        80)
  --http-01-address HTTP01_ADDRESS
                        The address the server listens to during http-01
                        challenge. (default: )
 --break-my-certs
                        Be willing to replace or renew valid certificates with
                        invalid (testing/staging) certificates (default:
                        False)
paths:
 Arguments changing execution paths & servers
 --cert-path CERT_PATH
                        Path to where certificate is saved (with auth --csr),
                        installed from, or revoked. (default: None)
 --key-path KEY_PATH
                        Path to private key for certificate installation or
                        revocation (if account key is missing) (default: None)
  --fullchain-path FULLCHAIN_PATH
                        Accompanying path to a full certificate chain
                        (certificate plus chain). (default: None)
 --chain-path CHAIN_PATH
                        Accompanying path to a certificate chain. (default:
                        None)
  --config-dir CONFIG_DIR
                        Configuration directory. (default: /etc/letsencrypt)
 --work-dir WORK_DIR Working directory. (default: /var/lib/letsencrypt)
 --logs-dir LOGS_DIR Logs directory. (default: /var/log/letsencrypt)
 --server SERVER
                       ACME Directory Resource URI. (default:
                        https://acme-v01.api.letsencrypt.org/directory)
manage:
 Various subcommands and flags are available for managing your
 certificates:
 certificates
                        List certificates managed by Certbot
 delete
                        Clean up all files related to a certificate
                        Renew all certificates (or one specified with --cert-
 renew
 revoke
                        Revoke a certificate specified with --cert-path
                        Recreate symlinks in your /etc/letsencrypt/live/
 update_symlinks
                        directory
```

run: Options for obtaining & installing certificates certonly: Options for modifying how a certificate is obtained Path to a Certificate Signing Request (CSR) in DER or PEM format. Currently --csr only works with the 'certonly' subcommand. (default: None) renew: The 'renew' subcommand will attempt to renew all certificates (or more precisely, certificate lineages) you have previously obtained if they are close to expiry, and print a summary of the results. By default, 'renew' will reuse the options used to create obtain or most recently successfully renew each certificate lineage. You can try it with `--dry-run` first. For more fine-grained control, you can renew individual lineages with the `certonly` subcommand. Hooks are available to run commands before and after renewal; see https://certbot.eff.org/docs/using.html#renewal for more information on these. --pre-hook PRE_HOOK Command to be run in a shell before obtaining any certificates. Intended primarily for renewal, where it can be used to temporarily shut down a webserver that might conflict with the standalone plugin. This will only be called if a certificate is actually to be obtained/renewed. When renewing several certificates that have identical pre-hooks, only the first will be executed. (default: None) --post-hook POST_HOOK Command to be run in a shell after attempting to obtain/renew certificates. Can be used to deploy renewed certificates, or to restart any servers that were stopped by --pre-hook. This is only run if an attempt was made to obtain/renew a certificate. If multiple renewed certificates have identical posthooks, only one will be run. (default: None) --renew-hook RENEW_HOOK Command to be run in a shell once for each successfully renewed certificate. For this command, the shell variable \$RENEWED_LINEAGE will point to the config live subdirectory (for example, "/etc/letsencrypt/live/example.com") containing the new certificates and keys; the shell variable \$RENEWED_DOMAINS will contain a space-delimited list of renewed certificate domains (for example, "example.com www.example.com" (default: None) --disable-hook-validation Ordinarily the commands specified for --pre-hook /--post-hook/--renew-hook will be checked for validity, to see if the programs being run are in the \$PATH, so that mistakes can be caught early, even when the hooks aren't being run just yet. The validation is

rather simplistic and fails if you use more advanced shell constructs, so you can use this switch to

disable it. (default: False)

```
certificates:
 List certificates managed by Certbot
delete:
 Options for deleting a certificate
revoke:
 Options for revocation of certificates
 --reason {keycompromise, affiliationchanged, superseded, unspecified,
Specify reason for revoking certificate. (default: 0)
register:
 Options for account registration & modification
 --register-unsafely-without-email
                       Specifying this flag enables registering an account
                       with no email address. This is strongly discouraged,
                       because in the event of key loss or account compromise
                       you will irrevocably lose access to your account. You
                       will also be unable to receive notice about impending
                       expiration or revocation of your certificates. Updates
                       to the Subscriber Agreement will still affect you, and
                       will be effective 14 days after posting an update to
                       the web site. (default: False)
  --update-registration
                       With the register verb, indicates that details
                       associated with an existing registration, such as the
                       e-mail address, should be updated, rather than
                       registering a new account. (default: False)
 -m EMAIL, --email EMAIL
                       Email used for registration and recovery contact.
                       (default: Ask)
  --eff-email
                       Share your e-mail address with EFF (default: None)
 --no-eff-email
                       Don't share your e-mail address with EFF (default:
                       None)
unregister:
 Options for account deactivation.
 --account ACCOUNT_ID Account ID to use (default: None)
install:
 Options for modifying how a certificate is deployed
config_changes:
 Options for controlling which changes are displayed
 --nım NUM
                       How many past revisions you want to be displayed
                        (default: None)
rollback:
 Options for rolling back server configuration changes
                       Revert configuration N number of checkpoints.
 --checkpoints N
                        (default: 1)
```

```
plugins:
 Options for for the "plugins" subcommand
 --init
                       Initialize plugins. (default: False)
                      Initialize and prepare plugins. (default: False)
 --prepare
 --authenticators Limit to authenticator plugins only. (default: None)
 --installers
                      Limit to installer plugins only. (default: None)
update_symlinks:
 Recreates certificate and key symlinks in /etc/letsencrypt/live, if you
 changed them by hand or edited a renewal configuration file
plugins:
 Plugin Selection: Certbot client supports an extensible plugins
 architecture. See 'certbot plugins' for a list of all installed plugins
 and their names. You can force a particular plugin by setting options
 provided below. Running --help <plugin_name> will list flags specific to
 that plugin.
 --configurator CONFIGURATOR
                       Name of the plugin that is both an authenticator and
                       an installer. Should not be used together with
                       --authenticator or --installer. (default: Ask)
 -a AUTHENTICATOR, --authenticator AUTHENTICATOR
                       Authenticator plugin name. (default: None)
 -i INSTALLER, --installer INSTALLER
                       Installer plugin name (also used to find domains).
                        (default: None)
  --apache
                       Obtain and install certificates using Apache (default:
                       False)
                       Obtain and install certificates using Nginx (default:
  --nginx
                       False)
  --standalone
                       Obtain certificates using a "standalone" webserver.
                       (default: False)
  --manual
                      Provide laborious manual instructions for obtaining a
                       certificate (default: False)
                       Obtain certificates by placing files in a webroot
  --webroot
                       directory. (default: False)
  --dns-cloudflare
                       Obtain certificates using a DNS TXT record (if you are
                       using Cloudflare for DNS). (default: False)
  --dns-cloudxns
                       Obtain certificates using a DNS TXT record (if you are
                       using CloudXNS for DNS). (default: False)
 --dns-digitalocean Obtain certificates using a DNS TXT record (if you are
                       using DigitalOcean for DNS). (default: False)
                       Obtain certificates using a DNS TXT record (if you are
 --dns-dnsimple
                       using DNSimple for DNS). (default: False)
  --dns-google
                       Obtain certificates using a DNS TXT record (if you are
                       using Google Cloud DNS). (default: False)
  --dns-nsone
                       Obtain certificates using a DNS TXT record (if you are
                       using NS1 for DNS). (default: False)
  --dns-route53
                       Obtain certificates using a DNS TXT record (if you are
                       using Route53 for DNS). (default: False)
apache:
 Apache Web Server plugin
 --apache-enmod APACHE_ENMOD
                       Path to the Apache 'a2enmod' binary. (default:
```

```
--apache-dismod APACHE_DISMOD
                        Path to the Apache 'a2dismod' binary. (default:
                        a2dismod)
  --apache-le-vhost-ext APACHE_LE_VHOST_EXT
                        SSL vhost configuration extension. (default: -le-
                        ssl.conf)
  --apache-server-root APACHE_SERVER_ROOT
                        Apache server root directory. (default: /etc/apache2)
  --apache-vhost-root APACHE_VHOST_ROOT
                        Apache server VirtualHost configuration root (default:
                        /etc/apache2/sites-available)
  --apache-logs-root APACHE_LOGS_ROOT
                        Apache server logs directory (default:
                        /var/log/apache2)
  --apache-challenge-location APACHE_CHALLENGE_LOCATION
                        Directory path for challenge configuration. (default:
                        /etc/apache2)
 --apache-handle-modules APACHE_HANDLE_MODULES
                        Let installer handle enabling required modules for
                        you. (Only Ubuntu/Debian currently) (default: True)
  --apache-handle-sites APACHE_HANDLE_SITES
                        Let installer handle enabling sites for you. (Only
                        Ubuntu/Debian currently) (default: True)
certbot-route53:auth:
 Obtain certificates using a DNS TXT record (if you are using AWS Route53
 for DNS).
 --certbot-route53:auth-propagation-seconds CERTBOT_ROUTE53:AUTH_PROPAGATION_SECONDS
                        The number of seconds to wait for DNS to propagate
                        before asking the ACME server to verify the DNS
                        record. (default: 10)
dns-cloudflare:
 Obtain certificates using a DNS TXT record (if you are using Cloudflare
 for DNS).
 --dns-cloudflare-propagation-seconds DNS_CLOUDFLARE_PROPAGATION_SECONDS
                        The number of seconds to wait for DNS to propagate
                        before asking the ACME server to verify the DNS
                        record. (default: 10)
 --dns-cloudflare-credentials DNS_CLOUDFLARE_CREDENTIALS
                        Cloudflare credentials INI file. (default: None)
dns-cloudxns:
 Obtain certificates using a DNS TXT record (if you are using CloudXNS for
 --dns-cloudxns-propagation-seconds DNS_CLOUDXNS_PROPAGATION_SECONDS
                        The number of seconds to wait for DNS to propagate
                        before asking the ACME server to verify the DNS \,
                        record. (default: 30)
  --dns-cloudxns-credentials DNS_CLOUDXNS_CREDENTIALS
                        CloudXNS credentials INI file. (default: None)
dns-digitalocean:
 Obtain certs using a DNS TXT record (if you are using DigitalOcean for
```

```
DNS).
 --dns-digitalocean-propagation-seconds DNS_DIGITALOCEAN_PROPAGATION_SECONDS
                        The number of seconds to wait for DNS to propagate
                        before asking the ACME server to verify the DNS
                        record. (default: 10)
 --dns-digitalocean-credentials DNS_DIGITALOCEAN_CREDENTIALS
                        DigitalOcean credentials INI file. (default: None)
dns-dnsimple:
 Obtain certificates using a DNS TXT record (if you are using DNSimple for
 DNS).
  --dns-dnsimple-propagation-seconds DNS_DNSIMPLE_PROPAGATION_SECONDS
                        The number of seconds to wait for DNS to propagate
                        before asking the ACME server to verify the DNS
                        record. (default: 30)
 --dns-dnsimple-credentials DNS_DNSIMPLE_CREDENTIALS
                        DNSimple credentials INI file. (default: None)
dns-google:
 Obtain certificates using a DNS TXT record (if you are using Google Cloud
 DNS for DNS).
 --dns-google-propagation-seconds DNS_GOOGLE_PROPAGATION_SECONDS
                        The number of seconds to wait for DNS to propagate
                        before asking the ACME server to verify the DNS
                        record. (default: 60)
 --dns-google-credentials DNS_GOOGLE_CREDENTIALS
                        Path to Google Cloud DNS service account JSON file.
                        (See https://developers.google.com/identity/protocols/
                        OAuth2ServiceAccount#creatinganaccount forinformation
                        about creating a service account and
                        https://cloud.google.com/dns/access-
                        control#permissions_and_roles for information about
                        therequired permissions.) (default: None)
dns-nsone:
 Obtain certificates using a DNS TXT record (if you are using NS1 for DNS).
  --dns-nsone-propagation-seconds DNS_NSONE_PROPAGATION_SECONDS
                        The number of seconds to wait for DNS to propagate
                        before asking the ACME server to verify the DNS
                        record. (default: 30)
 --dns-nsone-credentials DNS_NSONE_CREDENTIALS
                        NS1 credentials file. (default: None)
dns-route53:
 Obtain certificates using a DNS TXT record (if you are using AWS Route53
 for DNS).
 --dns-route53-propagation-seconds DNS_ROUTE53_PROPAGATION_SECONDS
                        The number of seconds to wait for DNS to propagate
                        before asking the ACME server to verify the DNS
                        record. (default: 10)
manual:
 Authenticate through manual configuration or custom shell scripts. When
```

```
using shell scripts, an authenticator script must be provided. The
 environment variables available to this script are $CERTBOT_DOMAIN which
 contains the domain being authenticated, $CERTBOT_VALIDATION which is the
 validation string, and CERTBOT\_TOKEN which is the filename of the
 resource requested when performing an HTTP-01 challenge. An additional
 cleanup script can also be provided and can use the additional variable
 $CERTBOT_AUTH_OUTPUT which contains the stdout output from the auth
 script.
 --manual-auth-hook MANUAL_AUTH_HOOK
                        Path or command to execute for the authentication
                        script (default: None)
 --manual-cleanup-hook MANUAL_CLEANUP_HOOK
                        Path or command to execute for the cleanup script
                        (default: None)
  --manual-public-ip-logging-ok
                        Automatically allows public IP logging (default: Ask)
nginx:
 Nginx Web Server plugin
 --nginx-server-root NGINX_SERVER_ROOT
                        Nginx server root directory. (default: /etc/nginx)
 --nginx-ctl NGINX_CTL
                        Path to the 'nginx' binary, used for 'configtest' and
                        retrieving nginx version number. (default: nginx)
null:
 Null Installer
standalone:
 Spin up a temporary webserver
webroot:
 Place files in webroot directory
 --webroot-path WEBROOT_PATH, -w WEBROOT_PATH
                        public_html / webroot path. This can be specified
                        multiple times to handle different domains; each
                        domain will have the webroot path that preceded it.
                        For instance: `-w /var/www/example -d example.com -d
                        www.example.com -w /var/www/thing -d thing.net -d
                        m.thing.net` (default: Ask)
 --webroot-map WEBROOT_MAP
                        JSON dictionary mapping domains to webroot paths; this
                        implies -d for each entry. You may need to escape this
                        from your shell. E.g.: --webroot-map
                        '{"egl.is,m.egl.is":"/www/eg1/", "eg2.is":"/www/eg2"}'
                        This option is merged with, but takes precedence over,
                        -w / -d entries. At present, if you put webroot-map in
                        a config file, it needs to be on a single line, like:
                        webroot-map = {"example.com":"/var/www"}. (default:
                        { } )
```

3.8 Getting help

If you're having problems, we recommend posting on the Let's Encrypt Community Forum.

You can also chat with us on IRC: (#letsencrypt @ freenode)

If you find a bug in the software, please do report it in our issue tracker. Remember to give us as much information as possible:

- copy and paste exact command line used and the output (though mind that the latter might include some personally identifiable information, including your email and domains)
- copy and paste logs from /var/log/letsencrypt (though mind they also might contain personally identifiable information)
- copy and paste certbot --version output
- your operating system, including specific version
- specify which installation method you've chosen

FOUR

DEVELOPER GUIDE

Table of Contents

- Getting Started
 - Running a local copy of the client
 - Find issues to work on
 - Testing
 - * Integration testing with the Boulder CA
- Code components and layout
 - Plugin-architecture
 - Authenticators
 - Installer
 - Installer Development
 - * Writing your own plugin
- Coding style
- Submitting a pull request
- Updating certbot-auto and letsencrypt-auto
 - Updating the scripts
 - Building letsencrypt-auto-source/letsencrypt-auto
 - Opening a PR
- Updating the documentation
- Running the client with Docker
- Notes on OS dependencies
 - Debian
 - FreeBSD

4.1 Getting Started

4.1.1 Running a local copy of the client

Running the client in developer mode from your local tree is a little different than running Certbot as a user. To get set up, clone our git repository by running:

```
git clone https://github.com/certbot/certbot
```

If you're on macOS, we recommend you skip the rest of this section and instead run Certbot in Docker. You can find instructions for how to do this *here*. If you're running on Linux, you can run the following commands to install dependencies and set up a virtual environment where you can run Certbot. You will need to repeat this when Certbot's dependencies change or when a new plugin is introduced.

```
cd certbot
./certbot-auto --os-packages-only
./tools/venv.sh
```

Then in each shell where you're working on the client, do:

```
source ./venv/bin/activate
export SERVER=https://acme-staging.api.letsencrypt.org/directory
source tests/integration/_common.sh
```

After that, your shell will be using the virtual environment, and you run the client by typing certbot or certbot_test. The latter is an alias that includes several flags useful for testing. For instance, it sets various output directories to point to /tmp/, and uses non-privileged ports for challenges, so root privileges are not required.

Activating a shell with venv/bin/activate sets environment variables so that Python pulls in the correct versions of various packages needed by Certbot. More information can be found in the virtualenv docs.

4.1.2 Find issues to work on

You can find the open issues in the github issue tracker. Comparatively easy ones are marked Good Volunteer Task. If you're starting work on something, post a comment to let others know and seek feedback on your plan where appropriate.

Once you've got a working branch, you can open a pull request. All changes in your pull request must have thorough unit test coverage, pass our tests, and be compliant with the *coding style*.

4.1.3 Testing

When you are working in a file foo.py, there should also be a file foo_test.py either in the same directory as foo.py or in the tests subdirectory (if there isn't, make one). While you are working on your code and tests, run python foo_test.py to run the relevant tests.

For debugging, we recommend putting import ipdb; ipdb.set_trace() statements inside the source code.

Once you are done with your code changes, and the tests in foo_test.py pass, run all of the unittests for Certbot with tox -e py27 (this uses Python 2.7).

Once all the unittests pass, check for sufficient test coverage using tox -e cover, and then check for code style with tox -e lint (all files) or pylint --rcfile=.pylintrc path/to/file.py (single file at a time).

Once all of the above is successful, you may run the full test suite, including integration tests, using tox. We recommend running the commands above first, because running all tests with tox is very slow, and the large amount

of tox output can make it hard to find specific failures when they happen. Also note that the full test suite will attempt to modify your system's Apache config if your user has sudo permissions, so it should not be run on a production Apache server.

If you have trouble getting the full tox suite to run locally, it is generally sufficient to open a pull request and let Github and Travis run integration tests for you.

Integration testing with the Boulder CA

To run integration tests locally, you need Docker and docker-compose installed and working. Fetch and start Boulder using:

```
./tests/boulder-fetch.sh
```

If you have problems with Docker, you may want to try removing all containers and volumes and making sure you have at least 1GB of memory.

Set up a certbot_test alias that enables easily running against the local Boulder:

```
export SERVER=http://localhost:4000/directory
source tests/integration/_common.sh
```

Run the integration tests using:

```
./tests/boulder-integration.sh
```

4.2 Code components and layout

acme contains all protocol specific code

certbot main client code

certbot-apache and certbot-nginx client code to configure specific web servers

certbot.egg-info configuration for packaging Certbot

4.2.1 Plugin-architecture

Certbot has a plugin architecture to facilitate support for different webservers, other TLS servers, and operating systems. The interfaces available for plugins to implement are defined in interfaces.py and plugins/common.py.

The main two plugin interfaces are <code>IAuthenticator</code>, which implements various ways of proving domain control to a certificate authority, and <code>IInstaller</code>, which configures a server to use a certificate once it is issued. Some plugins, like the built-in Apache and Nginx plugins, implement both interfaces and perform both tasks. Others, like the built-in Standalone authenticator, implement just one interface.

There are also IDisplay plugins, which can change how prompts are displayed to a user.

4.2.2 Authenticators

Authenticators are plugins that prove control of a domain name by solving a challenge provided by the ACME server. ACME currently defines three types of challenges: HTTP, TLS-SNI, and DNS, represented by classes in acme. challenges. An authenticator plugin should implement support for at least one challenge type.

An Authenticator indicates which challenges it supports by implementing get_chall_pref(domain) to return a sorted list of challenge types in preference order.

An Authenticator must also implement perform (achalls), which "performs" a list of challenges by, for instance, provisioning a file on an HTTP server, or setting a TXT record in DNS. Once all challenges have succeeded or failed, Certbot will call the plugin's cleanup (achalls) method to remove any files or DNS records that were needed only during authentication.

4.2.3 Installer

Installers plugins exist to actually setup the certificate in a server, possibly tweak the security configuration to make it more correct and secure (Fix some mixed content problems, turn on HSTS, redirect to HTTPS, etc). Installer plugins tell the main client about their abilities to do the latter via the <code>supported_enhancements()</code> call. We currently have two Installers in the tree, the <code>ApacheConfigurator</code> and the <code>NginxConfigurator</code>. External projects have made some progress toward support for IIS, Icecast and Plesk.

Installers and Authenticators will oftentimes be the same class/object (because for instance both tasks can be performed by a webserver like nginx) though this is not always the case (the standalone plugin is an authenticator that listens on port 443, but it cannot install certs; a postfix plugin would be an installer but not an authenticator).

Installers and Authenticators are kept separate because it should be possible to use the StandaloneAuthenticator (it sets up its own Python server to perform challenges) with a program that cannot solve challenges itself (Such as MTA installers).

4.2.4 Installer Development

There are a few existing classes that may be beneficial while developing a new <code>IInstaller</code>. Installers aimed to reconfigure UNIX servers may use Augeas for configuration parsing and can inherit from <code>AugeasConfigurator</code> class to handle much of the interface. Installers that are unable to use Augeas may still find the <code>Reverter</code> class helpful in handling configuration checkpoints and rollback.

Writing your own plugin

Certbot client supports dynamic discovery of plugins through the setuptools entry points using the certbot. plugins group. This way you can, for example, create a custom implementation of <code>IAuthenticator</code> or the <code>IInstaller</code> without having to merge it with the core upstream source code. An example is provided in <code>examples/plugins/directory</code>.

While developing, you can install your plugin into a Certbot development virtualenv like this:

```
. venv/bin/activate
. tests/integration/_common.sh
pip install -e examples/plugins/
certbot_test plugins
```

Your plugin should show up in the output of the last command. If not, it was not installed properly.

Once you've finished your plugin and published it, you can have your users install it system-wide with pip install. Note that this will only work for users who have Certbot installed from OS packages or via pip. Users who run certbot-auto are currently unable to use third-party plugins. It's technically possible to install third-party plugins into the virtualenv used by certbot-auto, but they will be wiped away when certbot-auto upgrades.

Warning: Please be aware though that as this client is still in a developer-preview stage, the API may undergo a few changes. If you believe the plugin will be beneficial to the community, please consider submitting a pull request to the repo and we will update it with any necessary API changes.

4.3 Coding style

Please:

- 1. Be consistent with the rest of the code.
- 2. Read PEP 8 Style Guide for Python Code.
- 3. Follow the Google Python Style Guide, with the exception that we use Sphinx-style documentation:

```
def foo(arg):
    """Short description.

    :param int arg: Some number.

    :returns: Argument
    :rtype: int

    """
    return arg
```

4. Remember to use pylint.

4.4 Submitting a pull request

Steps:

- 1. Write your code!
- 2. Make sure your environment is set up properly and that you're in your virtualenv. You can do this by running ./tools/venv.sh. (this is a **very important** step)
- 3. Run tox -e lint to check for pylint errors. Fix any errors.
- 4. Run tox --skip-missing-interpreters to run the entire test suite including coverage. The --skip-missing-interpreters argument ignores missing versions of Python needed for running the tests. Fix any errors.
- 5. If your code touches communication with an ACME server/Boulder, you should run the integration tests, see *integration*.
- 6. Submit the PR.
- 7. Did your tests pass on Travis? If they didn't, fix any errors.

4.3. Coding style 35

4.5 Updating certbot-auto and letsencrypt-auto

4.5.1 Updating the scripts

Developers should *not* modify the certbot-auto and letsencrypt-auto files in the root directory of the repository. Rather, modify the letsencrypt-auto.template and associated platform-specific shell scripts in the letsencrypt-auto-source and letsencrypt-auto-source/pieces/bootstrappers directory, respectively.

4.5.2 Building letsencrypt-auto-source/letsencrypt-auto

Once changes to any of the aforementioned files have been made, the letsencrypt-auto-source/letsencrypt-auto script should be updated. In lieu of manually updating this script, run the build script, which lives at letsencrypt-auto-source/build.py:

```
python letsencrypt-auto-source/build.py
```

Running build.py will update the letsencrypt-auto-source/letsencrypt-auto script. Note that the certbot-auto and letsencrypt-auto scripts in the root directory of the repository will remain **unchanged** after this script is run. Your changes will be propagated to these files during the next release of Certbot.

4.5.3 Opening a PR

When opening a PR, ensure that the following files are committed:

- 1. letsencrypt-auto-source/letsencrypt-auto.template
 letsencrypt-auto-source/pieces/bootstrappers/*
- 2. letsencrypt-auto-source/letsencrypt-auto (generated by build.py)

It might also be a good idea to double check that **no** changes were inadvertently made to the certbot-auto or letsencrypt-auto scripts in the root of the repository. These scripts will be updated by the core developers during the next release.

4.6 Updating the documentation

In order to generate the Sphinx documentation, run the following commands:

```
make -C docs clean html man
```

This should generate documentation in the docs/build/html directory.

4.7 Running the client with Docker

You can use Docker Compose to quickly set up an environment for running and testing Certbot. This is especially useful for macOS users. To install Docker Compose, follow the instructions at https://docs.docker.com/compose/install/.

and

Note: Linux users can simply run pip install docker-compose to get Docker Compose after installing Docker Engine and activating your shell as described in the *Getting Started* section.

Now you can develop on your host machine, but run Certbot and test your changes in Docker. When using docker-compose make sure you are inside your clone of the Certbot repository. As an example, you can run the following command to check for linting errors:

```
docker-compose run --rm --service-ports development bash -c 'tox -e lint'
```

You can also leave a terminal open running a shell in the Docker container and modify Certbot code in another window. The Certbot repo on your host machine is mounted inside of the container so any changes you make immediately take effect. To do this, run:

```
docker-compose run --rm --service-ports development bash
```

Now running the check for linting errors described above is as easy as:

```
tox -e lint
```

4.8 Notes on OS dependencies

OS-level dependencies can be installed like so:

```
letsencrypt-auto-source/letsencrypt-auto --os-packages-only
```

In general...

- sudo is required as a suggested way of running privileged process
- Python 2.6/2.7 is required
- Augeas is required for the Python bindings
- virtualenv and pip are used for managing other python library dependencies

4.8.1 Debian

For squeeze you will need to:

• Use virtualenv --no-site-packages -p python instead of -p python2.

4.8.2 FreeBSD

Packages can be installed on FreeBSD using pkg, or any other port-management tool (portupgrade, portmanager, etc.) from the pre-built package or can be built and installed from ports. Either way will ensure proper installation of all the dependencies required for the package.

FreeBSD by default uses tcsh. In order to activate virtualenv (see above), you will need a compatible shell, e.g. pkg install bash && bash.

CHAPTER

FIVE

PACKAGING GUIDE

5.1 Releases

We release packages and upload them to PyPI (wheels and source tarballs).

- https://pypi.python.org/pypi/acme
- https://pypi.python.org/pypi/certbot
- https://pypi.python.org/pypi/certbot-apache
- https://pypi.python.org/pypi/certbot-nginx
- https://pypi.python.org/pypi/certbot-dns-cloudflare
- https://pypi.python.org/pypi/certbot-dns-cloudxns
- https://pypi.python.org/pypi/certbot-dns-digitalocean
- https://pypi.python.org/pypi/certbot-dns-dnsimple
- https://pypi.python.org/pypi/certbot-dns-google
- https://pypi.python.org/pypi/certbot-dns-nsone
- https://pypi.python.org/pypi/certbot-dns-route53

The following scripts are used in the process:

• https://github.com/letsencrypt/letsencrypt/blob/master/tools/release.sh

We use git tags to identify releases, using Semantic Versioning. For example: v0.11.1.

5.2 Notes for package maintainers

- 0. Please use our tagged releases, not master!
- 1. Do not package certbot-compatibility-test or letshelp-certbot it's only used internally.
- 2. If you'd like to include automated renewal in your package certbot renew -q should be added to crontab or systemd timer. Additionally you should include a random per-machine time offset to avoid having a large number of your clients hit Let's Encrypt's servers simultaneously.
- 3. jws is an internal script for acme module and it doesn't have to be packaged it's mostly for debugging: you can use it as echo foo | jws sign | jws verify.
- 4. Do get in touch with us. We are happy to make any changes that will make packaging easier. If you need to apply some patches don't do it downstream make a PR here.

5.3 Already ongoing efforts

5.3.1 Arch

From our official releases:

- https://www.archlinux.org/packages/community/any/python-acme
- https://www.archlinux.org/packages/community/any/certbot
- https://www.archlinux.org/packages/community/any/certbot-apache
- https://www.archlinux.org/packages/community/any/certbot-nginx
- https://www.archlinux.org/packages/community/any/certbot-dns-cloudflare
- https://www.archlinux.org/packages/community/any/certbot-dns-cloudxns
- https://www.archlinux.org/packages/community/any/certbot-dns-digitalocean
- https://www.archlinux.org/packages/community/any/certbot-dns-dnsimple
- https://www.archlinux.org/packages/community/any/certbot-dns-google
- https://www.archlinux.org/packages/community/any/certbot-dns-nsone
- https://www.archlinux.org/packages/community/any/certbot-dns-route53

From master: https://aur.archlinux.org/packages/certbot-git

5.3.2 Debian (and its derivatives, including Ubuntu)

- https://packages.debian.org/sid/certbot
- https://packages.debian.org/sid/python-certbot
- https://packages.debian.org/sid/python-certbot-apache

5.3.3 Fedora

In Fedora 23+.

- https://admin.fedoraproject.org/pkgdb/package/certbot/
- https://admin.fedoraproject.org/pkgdb/package/python-acme/

5.3.4 FreeBSD

- https://www.freshports.org/security/py-acme/
- https://www.freshports.org/security/py-certbot/

5.3.5 Gentoo

Currently, all certbot related packages are in the testing branch:

- https://packages.gentoo.org/packages/app-crypt/certbot
- https://packages.gentoo.org/packages/app-crypt/certbot-apache

- https://packages.gentoo.org/packages/app-crypt/certbot-nginx
- https://packages.gentoo.org/packages/app-crypt/acme

5.3.6 GNU Guix

• https://www.gnu.org/software/guix/package-list.html#certbot

5.3.7 OpenBSD

• http://cvsweb.openbsd.org/cgi-bin/cvsweb/ports/security/letsencrypt/client/

CHAPTER

SIX

RESOURCES

Documentation: https://certbot.eff.org/docs

Software project: https://github.com/certbot/certbot

Notes for developers: https://certbot.eff.org/docs/contributing.html

Main Website: https://certbot.eff.org

Let's Encrypt Website: https://letsencrypt.org

IRC Channel: #letsencrypt on Freenode

Community: https://community.letsencrypt.org

ACME spec: http://ietf-wg-acme.github.io/acme/

ACME working area in github: https://github.com/ietf-wg-acme/acme

API DOCUMENTATION

7.1 certbot.account

Creates ACME accounts for server.

class certbot.account.Account (regr, key, meta=None)

Bases: object

ACME protocol registration.

Variables

- regr (RegistrationResource) Registration Resource
- **key** (JWK) Authorized Account Key
- Meta Account metadata
- id (str) Globally unique account identifier.

class Meta (**kwargs)

Bases: acme.jose.json_util.JSONObjectWithFields

Account metadata

Variables

- creation_dt (datetime.datetime) Creation date and time (UTC).
- **creation_host** (*str*) FQDN of host, where account has been created.

Note: creation_dt and creation_host are useful in cross-machine migration scenarios.

slug

Short account identification string, useful for UI.

```
certbot.account.report_new_account (config)
```

Informs the user about their new ACME account.

class certbot.account.AccountMemoryStorage (initial_accounts=None)

 $Bases: \ \textit{certbot.interfaces.AccountStorage}$

In-memory account storage.

class certbot.account.RegistrationResourceWithNewAuthzrURI (**kwargs)

Bases: acme.messages.RegistrationResource

A backwards-compatible RegistrationResource with a new-authz URI.

Hack: Certbot versions pre-0.11.1 expect to load new_authzr_uri as part of the account. Because people sometimes switch between old and new versions, we will continue to write out this field for some time so older clients don't crash in that scenario.

```
class certbot.account.AccountFileStorage (config)
    Bases: certbot.interfaces.AccountStorage
Accounts file storage.

    Variables config(IConfig) - Client configuration

save_regr (account, acme)
    Save the registration resource.

    Parameters account (Account) - account whose regr should be saved

delete (account_id)
    Delete registration info from disk

Parameters account_id - id of account which should be deleted
```

7.2 certbot.achallenges

Client annotated ACME challenges.

Please use names such as achall to distinguish from variables "of type" acme.challenges.Challenge (denoted by chall) and ChallengeBody (denoted by challb):

```
from acme import challenges
from acme import messages
from certbot import achallenges

chall = challenges.DNS(token='foo')
challb = messages.ChallengeBody(chall=chall)
achall = achallenges.DNS(chall=challb, domain='example.com')
```

Note, that all annotated challenges act as a proxy objects:

```
class certbot.achallenges.AnnotatedChallenge(**kwargs)
    Bases: acme.jose.util.ImmutableMap
    Client annotated challenge.
    Wraps around server provided challenge and annotates with data useful for the client.
    Variables challb - Wrapped ChallengeBody.

class certbot.achallenges.KeyAuthorizationAnnotatedChallenge(**kwargs)
    Bases: certbot.achallenges.AnnotatedChallenge
    Client annotated KeyAuthorizationChallenge challenge.
    response_and_validation(*args, **kwargs)
        Generate response and validation.

class certbot.achallenges.DNS(**kwargs)
    Bases: certbot.achallenges.AnnotatedChallenge
    Client annotated "dns" ACME challenge.
```

acme_type

alias of DNS

7.3 certbot.auth handler

ACME AuthHandler.

 ${\bf class} \; {\tt certbot.auth_handler.AuthHandler} \; ({\it auth, acme, account, pref_challs})$

Bases: object

ACME Authorization Handler for a client.

Variables

- auth Authenticator capable of solving Challenge types
- acme (acme.client.Client) ACME client API.
- account Client's Account
- authzr(dict) ACME Authorization Resource dict where keys are domains and values are acme.messages.AuthorizationResource
- achalls (list) DV challenges in the form of certbot.achallenges.

 AnnotatedChallenge
- pref_challs (list) sorted user specified preferred challenges type strings with the
 most preferred challenge listed first

get_authorizations (domains, best_effort=False)

Retrieve all authorizations for challenges.

Parameters

- domains (list) Domains for authorization
- **best_effort** (bool) Whether or not all authorizations are required (this is useful in renewal)

Returns List of authorization resources

Return type list

Raises AuthorizationError – If unable to retrieve all authorizations

choose challenges (domains)

Retrieve necessary challenges to satisfy server.

_solve_challenges()

Get Responses for challenges from authenticators.

_respond(resp, best_effort)

Send/Receive confirmation of all challenges.

Note: This method also cleans up the auth_handler state.

_send_responses (achalls, resps, chall_update)

Send responses and make sure errors are handled.

Parameters chall_update (dict) – parameter that is updated to hold authzr -> list of outstanding solved annotated challenges

 $\verb|_poll_challenges| (chall_update, best_effort, min_sleep=3, max_rounds=15)|$

Wait for all challenge results to be determined.

_handle_check (domain, achalls)

Returns tuple of ('completed', 'failed').

_find_updated_challb(authzr, achall)

Find updated challenge body within Authorization Resource.

Warning: This assumes only one instance of type of challenge in each challenge resource.

Parameters

- authzr (AuthorizationResource) Authorization Resource
- achall (AnnotatedChallenge) Annotated challenge for which to get status

_get_chall_pref(domain)

Return list of challenge preferences.

Parameters domain (str) – domain for which you are requesting preferences

_cleanup_challenges (achall_list=None)

Cleanup challenges.

If achall_list is not provided, cleanup all achallenges.

verify_authzr_complete()

Verifies that all authorizations have been decided.

Returns Whether all authzr are complete

Return type bool

challenge factory(domain, path)

Construct Namedtuple Challenges

Parameters

- domain (str) domain of the enrollee
- path (list) List of indices from challenges.

Returns achalls, list of challenge type certbot.achallenges.Indexed

Return type list

Raises errors. Error – if challenge type is not recognized

certbot.auth_handler.challb_to_achall (challb, account_key, domain)

Converts a ChallengeBody object to an AnnotatedChallenge.

Parameters

- challb (ChallengeBody) ChallengeBody
- account_key (JWK) Authorized Account Key
- **domain** (str) Domain of the challb

Returns Appropriate AnnotatedChallenge

Return type certbot.achallenges.AnnotatedChallenge

certbot.auth_handler.gen_challenge_path (challbs, preferences, combinations)
Generate a plan to get authority over the identity.

Todo

This can be possibly be rewritten to use resolved_combinations.

Parameters

- challbs (tuple) A tuple of challenges (acme.messages.Challenge) from acme.messages.AuthorizationResource to be fulfilled by the client in order to prove possession of the identifier.
- preferences (list) List of challenge preferences for domain (acme. challenges.Challenge subclasses)
- **combinations** (*tuple*) A collection of sets of challenges from acme.messages. Challenge, each of which would be sufficient to prove possession of the identifier.

Returns tuple of indices from challenges.

Return type tuple

Raises certbot.errors.AuthorizationError – If a path cannot be created that satisfies the CA given the preferences and combinations.

certbot.auth_handler._**find_smart_path** (challbs, preferences, combinations) Find challenge path with server hints.

Can be called if combinations is included. Function uses a simple ranking system to choose the combo with the lowest cost.

 $\verb|certbot.auth_handler._find_dumb_path| (\textit{challbs}, \textit{preferences})$

Find challenge path without server hints.

Should be called if the combinations hint is not included by the server. This function either returns a path containing all challenges provided by the CA or raises an exception.

certbot.auth_handler._report_no_chall_path()
Logs and raises an error that no satisfiable chall path exists.

certbot.auth_handler._report_failed_challs (failed_achalls)
Notifies the user about failed challenges.

Parameters failed_achalls (set) - A set of failed certbot.achallenges.
AnnotatedChallenge.

certbot.auth_handler._generate_failed_chall_msg (failed_achalls)

Creates a user friendly error message about failed challenges.

Parameters failed_achalls (list) - A list of failed certbot.achallenges.
AnnotatedChallenge with the same error type.

Returns A formatted error message for the client.

Return type str

7.4 certbot client

Certbot client API.

```
certbot.client.acme_from_config_key(config, key)
Wrangle ACME client construction
```

```
certbot.client.determine_user_agent (config)
```

Set a user_agent string in the config based on the choice of plugins. (this wasn't knowable at construction time)

Returns the client's User-Agent string

Return type str

```
certbot.client.ua_flags(config)
```

Turn some very important CLI flags into clues in the user agent.

```
{\bf class}\; {\tt certbot.client.DummyConfig}
```

Bases: object

Shim for computing a sample user agent.

```
certbot.client.sample_user_agent()
```

Document what this Certbot's user agent string will be like.

```
certbot.client.register(config, account_storage, tos_cb=None)
```

Register new account with an ACME CA.

This function takes care of generating fresh private key, registering the account, optionally accepting CA Terms of Service and finally saving the account. It should be called prior to initialization of Client, unless account has already been created.

Parameters

- config (IConfig) Client configuration.
- account_storage (AccountStorage) Account storage where newly registered account will be saved to. Save happens only after TOS acceptance step, so any account private keys or RegistrationResource will not be persisted if tos_cb returns False.
- tos_cb If ACME CA requires the user to accept a Terms of Service before registering account, client action is necessary. For example, a CLI tool would prompt the user acceptance. tos_cb must be a callable that should accept RegistrationResource and return a bool: True iff the Terms of Service present in the contained Registration. terms_of_service is accepted by the client, and False otherwise. tos_cb will be called only if the client action is necessary, i.e. when terms_of_service is not None. This argument is optional, if not supplied it will default to automatic acceptance!

Raises

- certbot.errors.Error In case of any client problems, in particular registration failure, or unaccepted Terms of Service.
- acme.errors.Error In case of any protocol problems.

Returns Newly registered and saved account, as well as protocol API handle (should be used in *Client* initialization).

Return type tuple of ${\it Account}$ and ${\it acme.client.Client}$

```
certbot.client.perform_registration(acme, config)
```

Actually register new account, trying repeatedly if there are email problems

- **config** (IConfig) Client configuration.
- client (acme.client.Client) ACME client object.

Returns Registration Resource.

Return type acme.messages.RegistrationResource

class certbot.client.Client(config, account_, auth, installer, acme=None)

Bases: object

Certbot's client.

Variables

- config (IConfig) Client configuration.
- account (Account) Account registered with register.
- auth_handler (AuthHandler) Authorizations handler that will dispatch DV challenges to appropriate authenticators (providing IAuthenticator interface).
- auth (IAuthenticator) Prepared (IAuthenticator.prepare) authenticator that can solve ACME challenges.
- installer (IInstaller) Installer.
- acme (acme.client.Client) Optional ACME client API handle. You might already have one from register.

obtain_certificate_from_csr(domains, csr, authzr=None)

Obtain certificate.

Internal function with precondition that domains are consistent with identifiers present in the csr.

Parameters

- domains (list) Domain names.
- csr (util.CSR) PEM-encoded Certificate Signing Request. The key used to generate this CSR can be different than authkey.
- authzr (list) List of acme.messages.AuthorizationResource

Returns CertificateResource and certificate chain (as returned by fetch_chain).

Return type tuple

obtain certificate(domains)

Obtains a certificate from the ACME server.

register must be called before obtain certificate

Parameters domains (list) – domains to get a certificate

Returns CertificateResource, certificate chain (as returned by fetch_chain), and newly generated private key (util.Key) and DER-encoded Certificate Signing Request (util.CSR).

Return type tuple

obtain_and_enroll_certificate (domains, certname)

Obtain and enroll certificate.

Get a new certificate for the specified domains using the specified authenticator and installer, and then create a new renewable lineage containing it.

Parameters

7.4. certbot.client 51

- **domains** (list) Domains to request.
- plugins A PluginsFactory object.
- certname (str) Name of new cert

Returns A new *certbot.storage.RenewableCert* instance referred to the enrolled cert lineage, False if the cert could not be obtained, or None if doing a successful dry run.

save_certificate (certr, chain_cert, cert_path, chain_path, fullchain_path)
Saves the certificate received from the ACME server.

Parameters

- certr (acme.messages.Certificate) ACME "certificate" resource.
- chain_cert (list)-
- **cert_path** (*str*) Candidate path to a certificate.
- **chain_path** (*str*) Candidate path to a certificate chain.
- **fullchain_path** (str) Candidate path to a full cert chain.

Returns cert_path, chain_path, and fullchain_path as absolute paths to the actual files

Return type tuple of str

Raises IOError – If unable to find room to write the cert files

Parameters

- **domains** (list) list of domains to install the certificate
- **privkey_path** (str) path to certificate private key
- cert_path (str) certificate file path (optional)
- chain_path (str) chain file path

enhance_config (domains, chain_path)

Enhance the configuration.

Parameters

- domains (list) list of domains to configure
- chain_path (str or None) chain file path

Raises errors. Error – if no installer is specified in the client.

apply_enhancement (domains, enhancement, options=None) Applies an enhancement on all domains.

Parameters

- domains (list) list of ssl_vhosts (as strings)
- enhancement (str) name of enhancement, e.g. ensure-http-header
- options (str) options to enhancement, e.g. Strict-Transport-Security

Note: When more options are needed, make options a list.

Raises *errors.PluginError* – If Enhancement is not supported, or if there is any other problem with the enhancement.

```
_recovery_routine_with_msg(success_msg)
```

Calls the installer's recovery routine and prints success_msg

Parameters $success_msg(str)$ - message to show on successful recovery

```
_rollback_and_restart (success_msg)
```

Rollback the most recent checkpoint and restart the webserver

Parameters $success_msg(str)$ - message to show on successful rollback

```
certbot.client.validate_key_csr(privkey, csr=None)
```

Validate Key and CSR files.

Verifies that the client key and csr arguments are valid and correspond to one another. This does not currently check the names in the CSR due to the inability to read SANs from CSRs in python crypto libraries.

If csr is left as None, only the key will be validated.

Parameters

- privkey (certbot.util.Key) Key associated with CSR
- csr (util.CSR) CSR

Raises errors. Error - when validation fails

certbot.client.rollback (default_installer, checkpoints, config, plugins)

Revert configuration the specified number of checkpoints.

Parameters

- **checkpoints** (*int*) Number of checkpoints to revert.
- config (certbot.interfaces.IConfig) Configuration.

```
certbot.client.view_config_changes(config, num=None)
```

View checkpoints and associated configuration changes.

Note: This assumes that the installation is using a Reverter object.

Parameters config (certbot.interfaces.IConfig) - Configuration.

```
certbot.client._open_pem_file (cli_arg_path, pem_path)
Open a pem file.
```

If cli_arg_path was set by the client, open that. Otherwise, uniquify the file path.

Parameters

- cli_arg_path (str) the cli arg name, e.g. cert_path
- **pem_path** (str) the pem file path to open

Returns a tuple of file object and its absolute file path

```
\verb|certbot.client._save_chain| (\textit{chain\_pem}, \textit{chain\_file})
```

Saves chain_pem at a unique path based on chain_path.

Parameters

• chain_pem (str) - certificate chain in PEM format

7.4. certbot.client 53

• chain_file (str) - chain file object

7.5 certbot.configuration

Certbot user-supplied configuration.

class certbot.configuration.NamespaceConfig(namespace)
 Bases: object

Configuration wrapper around argparse. Namespace.

For more documentation, including available attributes, please see <code>certbot.interfaces.IConfig</code>. However, note that the following attributes are dynamically resolved using <code>work_dir</code> and relative paths defined in <code>certbot.constants</code>:

- accounts_dir
- csr_dir
- in_progress_dir
- key_dir
- temp_checkpoint_dir

And the following paths are dynamically resolved using $config_dir$ and relative paths defined in certbot. constants:

- default_archive_dir
- live_dir
- renewal_configs_dir

Variables namespace - Namespace typically produced by argparse.ArgumentParser. parse_args().

server path

File path based on server.

certbot.configuration.check_config_sanity(config)

Validate command line options and display error message if requirements are not met.

Parameters config – IConfig instance holding user configuration

7.6 certbot.constants

Certbot constants.

```
certbot.constants.SETUPTOOLS_PLUGINS_ENTRY_POINT = 'certbot.plugins'
Setuptools entry point group name for plugins.
```

```
certbot.constants.OLD_SETUPTOOLS_PLUGINS_ENTRY_POINT = 'letsencrypt.plugins'
Plugins Setuptools entry point before rename.
```

certbot.constants.REVOCATION_REASONS = {'keycompromise': 1, 'affiliationchanged': 3, 'superseded': 4, 'unspecified Defaults for CLI flags and IConfig attributes.

```
certbot.constants.QUIET_LOGGING_LEVEL = 30 Logging level to use in quiet mode.
```

```
certbot.constants.RENEWER_DEFAULTS = {'renew_before_expiry': '30 days', 'deploy_before_expiry': '99 years', 'renew_before_expiry': '90 years', 'renew_before_expiry': '30 days', 'deploy_before_expiry': '99 years', 'renew_before_expiry': '30 days', 'deploy_before_expiry': '30 days', 'deploy_expiry': '30 days', 'deploy_before_expiry': '30 days', 'deploy_before_expiry
           Defaults for renewer script.
certbot.constants.ENHANCEMENTS = ['redirect', 'http-header', 'ocsp-stapling', 'spdy']
           List of possible certbot.interfaces.IInstaller enhancements.
           List of expected options parameters: - redirect: None - http-header: TODO - ocsp-stapling: certificate chain file
           path - spdy: TODO
certbot.constants.ARCHIVE DIR = 'archive'
           Archive directory, relative to IConfig.config_dir.
certbot.constants.CONFIG_DIRS_MODE = 493
           Directory mode for .IConfig.config_dir et al.
certbot.constants.ACCOUNTS_DIR = 'accounts'
           Directory where all accounts are saved.
certbot.constants.BACKUP_DIR = 'backups'
           Directory (relative to IConfig.work_dir) where backups are kept.
certbot.constants.CSR DIR = 'csr'
           See IConfig.csr_dir.
certbot.constants.IN_PROGRESS_DIR = 'IN_PROGRESS'
           Directory used before a permanent checkpoint is finalized (relative to IConfig.work_dir).
certbot.constants.KEY DIR = 'keys'
           Directory (relative to IConfig.config_dir) where keys are saved.
certbot.constants.LIVE DIR = 'live'
           Live directory, relative to IConfig.config_dir.
certbot.constants.TEMP_CHECKPOINT_DIR = 'temp_checkpoint'
           Temporary checkpoint directory (relative to IConfig.work_dir).
certbot.constants.RENEWAL_CONFIGS_DIR = 'renewal'
           Renewal configs directory, relative to IConfig.config_dir.
certbot.constants.FORCE_INTERACTIVE_FLAG = '-force-interactive'
           Flag to disable TTY checking in IDisplay.
certbot.constants.EFF_SUBSCRIBE_URI = 'https://supporters.eff.org/subscribe/certbot'
           EFF URI used to submit the e-mail address of users who opt-in.
```

7.7 certbot.crypto_util

Certbot client crypto utility functions.

Todo

Make the transition to use PSS rather than PKCS1_v1_5 when the server is capable of handling the signatures.

```
certbot.crypto_util.init_save_key (key_size, key_dir, keyname='key-certbot.pem')
Initializes and saves a privkey.
```

Inits key and saves it in PEM format on the filesystem.

Note: keyname is the attempted filename, it may be different if a file already exists at the path.

Parameters

- **key_size** (*int*) RSA key size in bits
- **key_dir** (*str*) Key save directory.
- **keyname** (str) Filename of key

Returns Key

Return type certbot.util.Key

Raises ValueError – If unable to generate the key given key_size.

certbot.crypto_util.init_save_csr(privkey, names, path)

Initialize a CSR with the given private key.

Parameters

- privkey (certbot.util.Key) Key to include in the CSR
- names (set) str names to include in the CSR
- path (str) Certificate save directory.

Returns CSR

Return type certbot.util.CSR

certbot.crypto_util.valid_csr(csr)

Validate CSR.

Check if csr is a valid CSR for the given domains.

Parameters csr(str) - CSR in PEM.

Returns Validity of CSR.

Return type bool

certbot.crypto_util.csr_matches_pubkey(csr, privkey)

Does private key correspond to the subject public key in the CSR?

Parameters

- csr (str) CSR in PEM.
- **privkey** (str) Private key file contents (PEM)

Returns Correspondence of private key to CSR subject public key.

Return type bool

certbot.crypto_util.import_csr_file(csrfile, data)

Import a CSR file, which can be either PEM or DER.

Parameters

- csrfile (str) CSR filename
- data (str) contents of the CSR file

Returns (OpenSSL.crypto.FILETYPE_PEM, util.CSR object representing the CSR, list of domains requested in the CSR)

Return type tuple certbot.crypto_util.make_key(bits) Generate PEM encoded RSA key. **Parameters** bits (int) – Number of bits, at least 1024. **Returns** new RSA key in PEM form with specified number of bits Return type str certbot.crypto_util.valid_privkey(privkey) Is valid RSA private key? **Parameters** privkey (str) – Private key file contents in PEM **Returns** Validity of private key. Return type bool certbot.crypto_util.verify_renewable_cert (renewable_cert) For checking that your certs were not corrupted on disk. Several things are checked: 1. Signature verification for the cert. 2. That fullchain matches cert and chain when concatenated. 3. Check that the private key matches the certificate. Parameters renewable_cert (storage.RenewableCert) - cert to verify Raises errors. Error – If verification fails. certbot.crypto_util.verify_renewable_cert_sig(renewable_cert) Verifies the signature of a storage. RenewableCert object. Parameters renewable_cert (storage.RenewableCert) - cert to verify **Raises** *errors*. *Error* – If signature verification fails. certbot.crypto_util.verify_cert_matches_priv_key(renewable_cert) Verifies that the private key and cert match. Parameters renewable cert (storage.RenewableCert) - cert to verify Raises errors. Error – If they don't match. certbot.crypto_util.verify_fullchain(renewable_cert) Verifies that fullchain is indeed cert concatenated with chain. Parameters renewable cert (storage.RenewableCert) - cert to verify Raises errors. Error – If cert and chain do not combine to fullchain. certbot.crypto_util.pyopenssl_load_certificate(data) Load PEM/DER certificate. Raises errors. Error -

Parameters

• **cert** (str) – Certificate (encoded).

certbot.crypto_util.get_sans_from_cert (cert, typ=1)
Get a list of Subject Alternative Names from a certificate.

```
    typ - OpenSSL.crypto.FILETYPE_PEM or OpenSSL.crypto.
FILETYPE ASN1
```

Returns A list of Subject Alternative Names.

Return type list

```
certbot.crypto_util.get_names_from_cert (csr, typ=1)
```

Get a list of domains from a cert, including the CN if it is set.

Parameters

- **cert** (*str*) Certificate (encoded).
- typ OpenSSL.crypto.FILETYPE_PEM or OpenSSL.crypto. FILETYPE_ASN1

Returns A list of domain names.

Return type list

```
certbot.crypto_util.dump_pyopenssl_chain(chain, filetype=1)
```

Dump certificate chain into a bundle.

Parameters chain (list) - List of OpenSSL.crypto.X509 (or wrapped in acme.jose. ComparableX509).

certbot.crypto_util.notBefore(cert_path)

When does the cert at cert_path start being valid?

Parameters cert_path (str) - path to a cert in PEM format

Returns the notBefore value from the cert at cert_path

Return type datetime.datetime

certbot.crypto_util.notAfter(cert_path)

When does the cert at cert_path stop being valid?

Parameters cert_path (str) - path to a cert in PEM format

Returns the notAfter value from the cert at cert_path

Return type datetime.datetime

certbot.crypto_util._notAfterBefore(cert_path, method)

Internal helper function for finding notbefore/notafter.

Parameters

- cert path (str) path to a cert in PEM format
- method (function) one of OpenSSL.crypto.X509.get_notBefore or OpenSSL.crypto.X509.get_notAfter

Returns the notBefore or notAfter value from the cert at cert_path

Return type datetime.datetime

certbot.crypto_util.sha256sum(filename)

Compute a sha256sum of a file.

Parameters filename (str) – path to the file whose hash will be computed

Returns sha256 digest of the file in hexadecimal

Return type str

7.8 certbot.display

Certbot display utilities.

7.8.1 certbot.display.util

```
Certbot display.
```

```
certbot.display.util.OK = 'ok'
```

Display exit code indicating user acceptance.

```
certbot.display.util.CANCEL = 'cancel'
```

Display exit code for a user canceling the display.

```
certbot.display.util.HELP = 'help'
```

Display exit code when for when the user requests more help.

```
certbot.display.util.ESC = 'esc'
```

Display exit code when the user hits Escape

```
certbot.display.util._wrap_lines(msg)
```

Format lines nicely to 80 chars.

Parameters msg(str) – Original message

Returns Formatted message respecting newlines in message

Return type str

```
certbot.display.util.input_with_timeout (prompt=None, timeout=36000.0)
```

Get user input with a timeout.

Behaves the same as six.moves.input, however, an error is raised if a user doesn't answer after timeout seconds. The default timeout value was chosen to place it just under 12 hours for users following our advice and running Certbot twice a day.

Parameters

- **prompt** (str) prompt to provide for input
- timeout (float) maximum number of seconds to wait for input

Returns user response

Return type str

:raises errors.Error if no answer is given before the timeout

```
class certbot.display.util.FileDisplay(outfile, force_interactive)
```

Bases: object

File-based display.

notification (message, pause=True, wrap=True, force_interactive=False)

Displays a notification and waits for user acceptance.

- message (str) Message to display
- pause (bool) Whether or not the program should pause for the user's confirmation
- wrap (bool) Whether or not the application should wrap text

• **force_interactive** (bool) – True if it's safe to prompt the user because it won't cause any workflow regressions

menu (message, choices, ok_label='', cancel_label='', help_label='', default=None, cli_flag=None, force_interactive=False, **unused_kwargs)

Display a menu.

Todo

This doesn't enable the help label/button (I wasn't sold on any interface I came up with for this). It would be a nice feature

Parameters

- message (str) title of menu
- **choices** (list of tuples (tag, item) or list of descriptions (tags will be enumerated)) Menu lines, len must be > 0
- **default** default value to return (if one exists)
- cli_flag (str) option used to set this value with the CLI
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

Returns tuple of (code, index) where code - str display exit code index - int index of the user's selection

Return type tuple

Parameters

- **message** (str) message to display to the user
- **default** default value to return (if one exists)
- cli_flag(str) option used to set this value with the CLI
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

Returns tuple of (code, *input*) where code - str display exit code *input* - str of the user's input

Return type tuple

Yes and No label must begin with different letters, and must contain at least one letter each.

- message(str) question for the user
- yes_label (str) Label of the "Yes" parameter
- no_label (str) Label of the "No" parameter

- **default** default value to return (if one exists)
- cli_flag (str) option used to set this value with the CLI
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

Returns True for "Yes", False for "No"

Return type bool

Parameters

- message (str) Message to display to user
- tags (list) str tags to select, len(tags) > 0
- default_status (bool) Not used for FileDisplay
- **default** default value to return (if one exists)
- cli_flag (str) option used to set this value with the CLI
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

Returns tuple of (code, tags) where code - str display exit code tags - list of selected tags

Return type tuple

_return_default (prompt, default, cli_flag, force_interactive)

Should we return the default instead of prompting the user?

Parameters

- **prompt** (*str*) prompt for the user
- **default** default answer to prompt
- ${\tt cli_flag}\,({\tt str})$ command line option for setting an answer to this question
- **force_interactive** (bool) if interactivity is forced by the IDisplay call

Returns True if we should return the default without prompting

Return type bool

can interact (force interactive)

Can we safely interact with the user?

Parameters force_interactive (bool) – if interactivity is forced by the IDisplay call

Returns True if the display can interact with the user

Return type bool

- message (str) prompt to give the user
- **default** default value to return (if one exists)

- cli_flag (str) option used to set this value with the CLI
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

Returns tuple of the form (code, string) where code - display exit code string - input entered by the user

_scrub_checklist_input (indices, tags)

Validate input and transform indices to appropriate tags.

Parameters

- indices (list) input
- tags (list) Original tags of the checklist

Returns valid tags the user selected

Return type list of str

_print_menu (message, choices)

Print a menu on the screen.

Parameters

- message (str) title of menu
- **choices** (list of tuples (tag, item) or list of descriptions (tags will be enumerated)) Menu lines

```
_get_valid_int_ans(max_)
```

Get a numerical selection.

Parameters max (int) - The maximum entry (len of choices), must be positive

Returns tuple of the form (code, selection) where code - str display exit code ('ok' or cancel') selection - int user's selection

Return type tuple

certbot.display.util.assert_valid_call (prompt, default, cli_flag, force_interactive) Verify that provided arguments is a valid IDisplay call.

Parameters

- **prompt** (*str*) prompt for the user
- **default** default answer to prompt
- cli flag (str) command line option for setting an answer to this question
- **force_interactive** (bool) if interactivity is forced by the IDisplay call

Bases: object

An iDisplay implementation that never asks for interactive user input

```
_interaction_fail (message, cli_flag, extra='')
```

Error out in case of an attempt to interact in noninteractive mode

notification (message, pause=False, wrap=True, **unused_kwargs)

Displays a notification without waiting for user acceptance.

- message (str) Message to display to stdout
- pause (bool) The Noninteractive Display waits for no keyboard
- wrap (bool) Whether or not the application should wrap text

menu (message, choices, ok_label=None, cancel_label=None, help_label=None, default=None, cli_flag=None, **unused_kwargs)
Avoid displaying a menu.

Parameters

- message (str) title of menu
- **choices** (list of tuples (tag, item) or list of descriptions (tags will be enumerated))—Menu lines, len must be > 0
- **default** (*int*) the default choice
- **kwargs** (dict) absorbs various irrelevant labelling arguments

Returns tuple of (code, index) where code - str display exit code index - int index of the user's selection

Return type tuple

Raises errors. MissingCommandlineFlag – if there was no default

input (message, default=None, cli_flag=None, **unused_kwargs)
Accept input from the user.

Parameters message (str) – message to display to the user

Returns tuple of (code, *input*) where code - str display exit code *input* - str of the user's input

Return type tuple

Raises errors. MissingCommandlineFlag - if there was no default

yesno (message, yes_label=None, no_label=None, default=None, cli_flag=None, **unused_kwargs)

Decide Yes or No, without asking anybody

Parameters

- message (str) question for the user
- **kwargs** (dict) absorbs yes_label, no_label

Raises errors. MissingCommandlineFlag - if there was no default

Returns True for "Yes". False for "No"

Return type bool

checklist (*message*, *tags*, *default=None*, *cli_flag=None*, **unused_kwargs)

Display a checklist.

Parameters

- **message** (str) Message to display to user
- tags (list) str tags to select, len(tags) > 0
- **kwargs** (dict) absorbs default_status arg

 $\textbf{Returns} \ \ \text{tuple of (code, tags) where code - str display exit code tags - list of selected tags}$

Return type tuple

```
directory_select (message, default=None, cli_flag=None, **unused_kwargs)
Simulate prompting the user for a directory.
```

This function returns default if it is not None, otherwise, an exception is raised explaining the problem. If cli_flag is not None, the error message will include the flag that can be used to set this value with the CLI.

Parameters

- **message** (str) prompt to give the user
- **default** default value to return (if one exists)
- cli_flag(str) option used to set this value with the CLI

Returns tuple of the form (code, string) where code - int display exit code string - input entered by the user

```
certbot.display.util.separate_list_input(input_)
```

Separate a comma or space separated list.

Parameters input (str) – input from the user

Returns strings

Return type list

```
certbot.display.util._parens_around_char(label)
```

Place parens around first character of label.

Parameters label (str) – Must contain at least one character

7.8.2 certbot.display.ops

Contains UI methods for LE user operations.

```
certbot.display.ops.get_email (invalid=False, optional=True)
Prompt for valid email address.
```

Parameters

- invalid (bool) True if an invalid address was provided by the user
- **optional** (bool) True if the user can use –register-unsafely-without-email to avoid providing an e-mail

Returns e-mail address

Return type str

```
Raises errors. Error – if the user cancels
```

```
certbot.display.ops.choose_account (accounts)
```

Choose an account.

Parameters accounts (list) - Containing at least one Account

```
certbot.display.ops.choose_names (installer)
```

Display screen to select domains to validate.

```
Parameters installer (certbot.interfaces.IInstaller) - An installer object
```

Returns List of selected names

Return type list of str

```
certbot.display.ops.get_valid_domains(domains)
```

Helper method for choose_names that implements basic checks on domain names

Parameters domains (list) – Domain names to validate

Returns List of valid domains

Return type list

certbot.display.ops._sort_names(FQDNs)

Sort FQDNs by SLD (and if many, by their subdomains)

Parameters FQDNs (list) – list of domain names

Returns Sorted list of domain names

Return type list

certbot.display.ops._filter_names (names)

Determine which names the user would like to select from a list.

Parameters names (list) - domain names

Returns tuple of the form (code, names) where code - str display exit code names - list of names selected

Return type tuple

certbot.display.ops._choose_names_manually(prompt_prefix='')

Manually input names for those without an installer.

Parameters prompt_prefix (str) – string to prepend to prompt for domains

Returns list of provided names

Return type list of str

certbot.display.ops.success_installation(domains)

Display a box confirming the installation of HTTPS.

Parameters domains (list) – domain names which were enabled

certbot.display.ops.success_renewal(domains)

Display a box confirming the renewal of an existing certificate.

Parameters domains (list) – domain names which were renewed

certbot.display.ops.success_revocation(cert_path)

Display a box confirming a certificate has been revoked.

Parameters cert path (list) – path to certificate which was revoked.

 $\verb|certbot.display.ops._gen_ssl_lab_urls| (\textit{domains})$

Returns a list of urls.

Parameters domains (list) - Each domain is a 'str'

certbot.display.ops._gen_https_names(domains)

Returns a string of the https domains.

Domains are formatted nicely with https:// prepended to each.

Parameters domains (list) - Each domain is a 'str'

certbot.display.ops.validated_input(validator, *args, **kwargs)

Like *input*, but with validation.

- **validator** (*callable*) A method which will be called on the supplied input. If the method raises a errors. Error, its text will be displayed and the user will be reprompted.
- *args (list) Arguments to be passed to input.
- **kwargs (dict) Arguments to be passed to input.

Returns as input

Return type tuple

certbot.display.ops.validated_directory(validator, *args, **kwargs)
Like directory_select, but with validation.

Parameters

- **validator** (*callable*) A method which will be called on the supplied input. If the method raises a errors. Error, its text will be displayed and the user will be reprompted.
- *args (list) Arguments to be passed to directory_select.
- **kwargs (dict) Arguments to be passed to directory_select.

Returns as directory_select

Return type tuple

7.8.3 certbot.display.enhancements

Certbot Enhancement Display

 $\verb|certbot.display.enhancements.ask| (enhancement)$

Display the enhancement to the user.

Parameters enhancement (str) - One of the certbot. CONFIG. ENHANCEMENTS enhancements

Returns True if feature is desired, False otherwise

Return type bool

Raises errors. Error – if the enhancement provided is not supported

certbot.display.enhancements.redirect_by_default()

Determines whether the user would like to redirect to HTTPS.

Returns True if redirect is desired. False otherwise

Return type bool

7.9 certbot errors

Certbot client errors.

```
exception certbot.errors.Error

Bases: exceptions.Exception
```

Generic Certbot client error.

```
exception certbot.errors.AccountStorageError
    Bases: certbot.errors.Error
    Generic Account Storage error.
exception certbot.errors.AccountNotFound
    Bases: certbot.errors.AccountStorageError
    Account not found error.
exception certbot.errors.ReverterError
    Bases: certbot.errors.Error
    Certbot Reverter error.
exception certbot.errors.SubprocessError
    Bases: certbot.errors.Error
    Subprocess handling error.
exception certbot.errors.CertStorageError
    Bases: certbot.errors.Error
    Generic CertStorage error.
exception certbot.errors.HookCommandNotFound
    Bases: certbot.errors.Error
    Failed to find a hook command in the PATH.
exception certbot.errors.SignalExit
    Bases: certbot.errors.Error
    A Unix signal was received while in the ErrorHandler context manager.
exception certbot.errors.LockError
    Bases: certbot.errors.Error
    File locking error.
exception certbot.errors.AuthorizationError
    Bases: certbot.errors.Error
     Authorization error.
exception certbot.errors.FailedChallenges (failed achalls)
    Bases: certbot.errors.AuthorizationError
    Failed challenges error.
         Variables failed achalls (set) - Failed AnnotatedChallenge instances.
exception certbot.errors.PluginError
    Bases: cert.bot.errors.Error
    Certbot Plugin error.
exception certbot.errors.PluginEnhancementAlreadyPresent
    Bases: certbot.errors.Error
    Enhancement was already set
exception certbot.errors.PluginSelectionError
    Bases: certbot.errors.Error
    A problem with plugin/configurator selection or setup
```

7.9. certbot.errors 67

```
exception certbot.errors.NoInstallationError
    Bases: certbot.errors.PluginError
    Certbot No Installation error.
exception certbot.errors.MisconfigurationError
    Bases: certbot.errors.PluginError
    Certbot Misconfiguration error.
exception certbot.errors.NotSupportedError
    Bases: certbot.errors.PluginError
    Certbot Plugin function not supported error.
exception certbot.errors.StandaloneBindError(socket_error, port)
    Bases: certbot.errors.Error
    Standalone plugin bind error.
exception certbot.errors.ConfigurationError
    Bases: certbot.errors.Error
    Configuration sanity error.
exception certbot.errors.MissingCommandlineFlag
    Bases: certbot.errors.Error
    A command line argument was missing in noninteractive usage
```

7.10 certbot

Certbot client.

7.11 certbot interfaces

```
Certbot client interfaces.
```

```
class certbot.interfaces.AccountStorage
```

Bases: object

Accounts storage interface.

find_all()

Find all accounts.

Returns All found accounts.

Return type list

load(account_id)

Load an account by its id.

Raises

- Account Not Found if account could not be found
- AccountStorageError if account could not be loaded

save (account, client)

Save account.

Raises AccountStorageError - if account could not be saved

Objects providing this interface will be called without satisfying any entry point "extras" (extra dependencies) you might have defined for your plugin, e.g (excerpt from setup.py script):

Therefore, make sure such objects are importable and usable without extras. This is necessary, because CLI does the following operations (in order):

- · loads an entry point,
- calls inject_parser_options,
- · requires an entry point,
- creates plugin instance (__call__).

description

Short plugin description

```
__call__(config, name)
Create new IPlugin.
```

Parameters

- config (IConfig) Configuration.
- name (str) Unique plugin name.

inject_parser_options (parser, name)

Inject argument parser options (flags).

- 1. Be nice and prepend all options and destinations with option_namespace and dest_namespace.
- 2. Inject options (flags) only. Positional arguments are not allowed, as this would break the CLI.

Parameters

- parser (ArgumentParser) (Almost) top-level CLI parser.
- name (str) Unique plugin name.

```
interface certbot.interfaces.IPlugin
```

Certbot plugin.

prepare()

Prepare the plugin.

Finish up any additional initialization.

Raises

- *PluginError* when full initialization cannot be completed.
- *MisconfigurationError* when full initialization cannot be completed. Plugin will be displayed on a list of available plugins.
- **NoInstallationError** when the necessary programs/files cannot be located. Plugin will NOT be displayed on a list of available plugins.
- **NotSupportedError** when the installation is recognized, but the version is not currently supported.

more_info()

Human-readable string to help the user.

Should describe the steps taken and any relevant info to help the user decide which plugin to use.

Rtype str

interface certbot.interfaces.IAuthenticator

Extends: certbot.interfaces.IPlugin

Generic Certbot Authenticator.

Class represents all possible tools processes that have the ability to perform challenges and attain a certificate.

get_chall_pref(domain)

Return collections. Iterable of challenge preferences.

Parameters domain (str) – Domain for which challenge preferences are sought.

Returns collections. Iterable of challenge types (subclasses of acme. challenges. Challenge) with the most preferred challenges first. If a type is not specified, it means the Authenticator cannot perform the challenge.

Return type collections. Iterable

perform(achalls)

Perform the given challenge.

Parameters achalls (list) – Non-empty (guaranteed) list of AnnotatedChallenge instances, such that it contains types found within get_chall_pref() only.

Returns

collections. Iterable of ACME Challenge Response instances or if the Challenge cannot be fulfilled then:

None Authenticator can perform challenge, but not at this time.

False Authenticator will never be able to perform (error).

Return type collections. Iterable of acme.challenges.

ChallengeResponse, where responses are required to be returned in the same order as corresponding input challenges

Raises PluginError – If challenges cannot be performed

cleanup(achalls)

Revert changes and shutdown after challenges complete.

This method should be able to revert all changes made by perform, even if perform exited abnormally.

Parameters achalls (list) – Non-empty (guaranteed) list of AnnotatedChallenge instances, a subset of those previously passed to perform().

Raises PluginError – if original configuration cannot be restored

interface certbot.interfaces.IConfig

Certbot user-supplied configuration.

Warning: The values stored in the configuration have not been filtered, stripped or sanitized.

server

ACME Directory Resource URI.

email

Email used for registration and recovery contact. (default: Ask)

rsa_key_size

Size of the RSA key.

must staple

Adds the OCSP Must Staple extension to the certificate. Autoconfigures OCSP Stapling for supported setups (Apache version \geq 2.3.3).

config dir

Configuration directory.

work dir

Working directory.

accounts_dir

Directory where all account information is stored.

backup_dir

Configuration backups directory.

csr_dir

Directory where newly generated Certificate Signing Requests (CSRs) are saved.

in_progress_dir

Directory used before a permanent checkpoint is finalized.

key_dir

Keys storage.

temp_checkpoint_dir

Temporary checkpoint directory.

no verify ssl

Disable verification of the ACME server's certificate.

tls_sni_01_port

Port used during tls-sni-01 challenge. This only affects the port Certbot listens on. A conforming ACME server will still attempt to connect on port 443.

tls_sni_01_address

The address the server listens to during tls-sni-01 challenge.

http01_port

Port used in the http-01 challenge. This only affects the port Certbot listens on. A conforming ACME server will still attempt to connect on port 80.

http01 address

The address the server listens to during http-01 challenge.

pref challs

Sorted user specified preferred challengestype strings with the most preferred challenge listed first

allow subset of names

When performing domain validation, do not consider it a failure if authorizations can not be obtained for a strict subset of the requested domains. This may be useful for allowing renewals for multiple domains to succeed even if some domains no longer point at this system. This is a boolean

strict_permissions

Require that all configuration files are owned by the current user; only needed if your config is somewhere unsafe like /tmp/.This is a boolean

interface certbot.interfaces.IInstaller

Extends: certbot.interfaces.IPlugin

Generic Certbot Installer Interface.

Represents any server that an X509 certificate can be placed.

It is assumed that <code>save()</code> is the only method that finalizes a checkpoint. This is important to ensure that checkpoints are restored in a consistent manner if requested by the user or in case of an error.

Using certbot.reverter.Reverter to implement checkpoints, rollback, and recovery can dramatically simplify plugin development.

get_all_names()

Returns all names that may be authenticated.

Return type collections. Iterable of str

deploy_cert (domain, cert_path, key_path, chain_path, fullchain_path)
 Deploy certificate.

Parameters

- domain (str) domain to deploy certificate file
- **cert_path** (*str*) absolute path to the certificate file
- **key_path** (str) absolute path to the private key file
- **chain_path** (str) absolute path to the certificate chain file
- fullchain_path (str) absolute path to the certificate fullchain file (cert plus chain)

Raises *PluginError* – when cert cannot be deployed

enhance (domain, enhancement, options=None)

Perform a configuration enhancement.

Parameters

- domain (str) domain for which to provide enhancement
- enhancement (str) An enhancement as defined in ENHANCEMENTS
- **options** Flexible options parameter for enhancement. Check documentation of *ENHANCEMENTS* for expected options for each enhancement.

Raises *PluginError* – If Enhancement is not supported, or if an error occurs during the enhancement.

supported enhancements()

Returns a collections. Iterable of supported enhancements.

Returns supported enhancements which should be a subset of *ENHANCEMENTS*

Return type collections. Iterable of str

```
save (title=None, temporary=False)
```

Saves all changes to the configuration files.

Both title and temporary are needed because a save may be intended to be permanent, but the save is not ready to be a full checkpoint.

It is assumed that at most one checkpoint is finalized by this method. Additionally, if an exception is raised, it is assumed a new checkpoint was not finalized.

Parameters

- **title** (*str*) The title of the save. If a title is given, the configuration will be saved as a new checkpoint and put in a timestamped directory. title has no effect if temporary is true.
- **temporary** (bool) Indicates whether the changes made will be quickly reversed in the future (challenges)

Raises PluginError - when save is unsuccessful

rollback_checkpoints(rollback=1)

Revert rollback number of configuration checkpoints.

Raises PluginError – when configuration cannot be fully reverted

```
recovery_routine()
```

Revert configuration to most recent finalized checkpoint.

Remove all changes (temporary and permanent) that have not been finalized. This is useful to protect against crashes and other execution interruptions.

Raises errors.PluginError - If unable to recover the configuration

view_config_changes()

Display all of the LE config changes.

Raises PluginError – when config changes cannot be parsed

```
config_test()
```

Make sure the configuration is valid.

Raises MisconfigurationError – when the config is not in a usable state

restart()

Restart or refresh the server content.

Raises PluginError – when server cannot be restarted

```
interface certbot.interfaces.IDisplay
```

Generic display.

notification (message, pause, wrap=True, force_interactive=False)

Displays a string message

- message (str) Message to display
- **pause** (bool) Whether or not the application should pause for confirmation (if available)
- wrap (bool) Whether or not the application should wrap text
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

menu (message, choices, ok_label='OK', cancel_label='Cancel', help_label='', default=None, cli_flag=None, force_interactive=False)

Displays a generic menu.

When not setting force_interactive=True, you must provide a default value.

Parameters

- message (str) message to display
- choices (list of tuple () or str) choices
- ok label (str) label for OK button
- cancel_label (str) label for Cancel button
- **help_label** (str) label for Help button
- **default** (*int*) default (non-interactive) choice from the menu
- cli_flag (str) to automate choice from the menu, eg "-keep"
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

Returns tuple of (code, index) where code - str display exit code index - int index of the user's selection

Raises errors.MissingCommandlineFlag – if called in non-interactive mode without a default set

input (message, default=None, cli_args=None, force_interactive=False)
 Accept input from the user.

When not setting force_interactive=True, you must provide a default value.

Parameters

- **message** (str) message to display to the user
- **default** (str) default (non-interactive) response to prompt
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

Returns tuple of (code, *input*) where code - str display exit code *input* - str of the user's input

Return type tuple

Raises errors.MissingCommandlineFlag – if called in non-interactive mode without a default set

Yes and No label must begin with different letters.

When not setting force_interactive=True, you must provide a default value.

- message (str) question for the user
- **default** (str) default (non-interactive) choice from the menu
- cli_flag (str) to automate choice from the menu, eg "-redirect / -no-redirect"

• **force_interactive** (bool) – True if it's safe to prompt the user because it won't cause any workflow regressions

Returns True for "Yes", False for "No"

Return type bool

Raises errors.MissingCommandlineFlag – if called in non-interactive mode without a default set

checklist (message, tags, default_state, default=None, cli_args=None, force_interactive=False) Allow for multiple selections from a menu.

When not setting force_interactive=True, you must provide a default value.

Parameters

- **message** (str) message to display to the user
- tags (list) where each is of type str len(tags) > 0
- **default_status** (bool) If True, items are in a selected state by default.
- **default** (str) default (non-interactive) state of the checklist
- cli_flag (str) to automate choice from the menu, eg "-domains"
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

Returns tuple of the form (code, list_tags) where code - int display exit code list_tags - list of str tags selected by the user

Return type tuple

Raises errors.MissingCommandlineFlag – if called in non-interactive mode without a default set

directory_select (self, message, default=None, cli_flag=None, force_interactive=False)
 Display a directory selection screen.

When not setting force_interactive=True, you must provide a default value.

Parameters

- message(str) prompt to give the user
- **default** the default value to return, if one exists, when using the NoninteractiveDisplay
- cli_flag (str) option used to set this value with the CLI, if one exists, to be included in error messages given by NoninteractiveDisplay
- **force_interactive** (bool) True if it's safe to prompt the user because it won't cause any workflow regressions

Returns tuple of the form (code, string) where code - int display exit code string - input entered by the user

interface certbot.interfaces.IValidator

Configuration validator.

certificate (cert, name, alt_host=None, port=443)

Verifies the certificate presented at name is cert

- cert (OpenSSL.crypto.X509) Expected certificate
- name (str) Server's domain name
- alt_host (bytes) Host to connect to instead of the IP address of host
- port (int) Port to connect to

Returns True if the certificate was verified successfully

Return type bool

redirect (name, port=80, headers=None)

Verify redirect to HTTPS

Parameters

- name (str) Server's domain name
- port (int) Port to connect to
- headers (dict) HTTP headers to include in request

Returns True if redirect is successfully enabled

Return type bool

hsts (name)

Verify HSTS header is enabled

Parameters name (str) – Server's domain name

Returns True if HSTS header is successfully enabled

Return type bool

ocsp_stapling(name)

Verify ocsp stapling for domain

Parameters name (str) – Server's domain name

Returns True if ocsp stapling is successfully enabled

Return type bool

interface certbot.interfaces.IReporter

Interface to collect and display information to the user.

HIGH PRIORITY

Used to denote high priority messages

MEDIUM PRIORITY

Used to denote medium priority messages

LOW_PRIORITY

Used to denote low priority messages

add_message (self, msg, priority, on_crash=True)

Adds msg to the list of messages to be printed.

- msg(str) Message to be displayed to the user.
- priority (int) One of HIGH_PRIORITY, MEDIUM_PRIORITY, or LOW_PRIORITY.

• on_crash (bool) - Whether or not the message should be printed if the program exits abnormally.

print_messages (self)

Prints messages to the user and clears the message queue.

7.12 certbot.plugins.common

```
Plugin common functions.
```

```
Certbot.plugins.common.option_namespace (name)
ArgumentParser options namespace (prefix of all options).

Certbot.plugins.common.dest_namespace (name)
ArgumentParser dest namespace (prefix of all destinations).

class certbot.plugins.common.Plugin (config, name)
Bases: object
Generic plugin.
```

classmethod add_parser_arguments (add)

Add plugin arguments to the CLI argument parser.

NOTE: If some of your flags interact with others, you can use cli.report_config_interaction to register this to ensure values are correctly saved/overridable during renewal.

Parameters add (callable) - Function that proxies calls to argparse. ArgumentParser.add_argument prepending options with unique plugin name prefix.

classmethod inject_parser_options (parser, name)

Inject parser options.

See inject_parser_options for docs.

option_namespace

ArgumentParser options namespace (prefix of all options).

option_name (name)

Option name (include plugin namespace).

dest_namespace

ArgumentParser dest namespace (prefix of all destinations).

dest (var)

Find a destination for given variable var.

conf (var

Find a configuration value for variable var.

```
class certbot.plugins.common.Addr(tup, ipv6=False)
```

Bases: object

Represents an virtual host address.

- addr (str) addr part of vhost address
- port (str) port number or *, or ""

```
classmethod fromstring (str_addr)
          Initialize Addr from string.
     normalized_tuple()
          Normalized representation of addr/port tuple
     get addr()
          Return addr part of Addr object.
     get port()
          Return port.
     get_addr_obj(port)
          Return new address object with same addr and new port.
     _normalize_ipv6(addr)
          Return IPv6 address in normalized form, helper function
     get_ipv6_exploded()
          Return IPv6 in normalized form
     explode ipv6(addr)
          Explode IPv6 address for comparison
class certbot.plugins.common.TLSSNIO1(configurator)
     Bases: object
     Abstract base for TLS-SNI-01 challenge performers
     add_chall (achall, idx=None)
          Add challenge to TLSSNI01 object to perform at once.
              Parameters
                  • achall (KeyAuthorizationAnnotatedChallenge) - Annotated TLSSNI01
                    challenge.
                  • idx (int) – index to challenge in a larger array
     get_cert_path(achall)
          Returns standardized name for challenge certificate.
              Parameters achall (KeyAuthorizationAnnotatedChallenge) - Annotated tls-sni-
                  01 challenge.
              Returns certificate file name
              Return type str
     get_key_path (achall)
          Get standardized path to challenge key.
     _setup_challenge_cert (achall, cert_key=None)
          Generate and write out challenge certificate.
certbot.plugins.common.install_ssl_options_conf(options_ssl,
                                                                                 options_ssl_digest,
                                                               mod_ssl_conf_src,
                                                               all_ssl_options_hashes)
     Copy Certbot's SSL options file into the system's config dir if required.
          Parameters
                • options_ssl (str) – destination path for file containing ssl options
                • options_ssl_digest (str) - path to save a digest of options_ssl in
```

- mod_ssl_conf_src (str) path to file containing ssl options found in distribution
- all_ssl_options_hashes (list) hashes of every released version of options_ssl

certbot.plugins.common.dir_setup(test_dir, pkg)

Setup the directories necessary for the configurator.

7.13 certbot.plugins.disco

Utilities for plugins discovery and selection.

class certbot.plugins.disco.PluginEntryPoint(entry_point)

Bases: object

Plugin entry point.

PREFIX_FREE_DISTRIBUTIONS = ['certbot', 'certbot-apache', 'certbot-dns-cloudflare', 'certbot-dns-cloudxns', 'certbot-dns-cloudxns', 'certbot-d

classmethod entry_point_to_plugin_name (entry_point)

Unique plugin name for an entry_point

description

Description of the plugin.

description_with_name

Description with name. Handy for UI.

long_description

Long description of the plugin.

hidden

Should this plugin be hidden from UI?

ifaces (*ifaces_groups)

Does plugin implements specified interface groups?

initialized

Has the plugin been initialized already?

init (config=None)

Memoized plugin initialization.

verify (ifaces)

Verify that the plugin conforms to the specified interfaces.

prepared

Has the plugin been prepared already?

prepare()

Memoized plugin preparation.

misconfigured

Is plugin misconfigured?

problem

Return the Exception raised during plugin setup, or None if all is well

available

Is plugin available, i.e. prepared or misconfigured?

```
class certbot.plugins.disco.PluginsRegistry (plugins)
     Bases: _abcoll.Mapping
     Plugins registry.
     classmethod find all()
          Find plugins using setuptools entry points.
     init (config)
          Initialize all plugins in the registry.
     filter(pred)
          Filter plugins based on predicate.
     visible()
          Filter plugins based on visibility.
     ifaces (*ifaces_groups)
          Filter plugins based on interfaces.
     verify (ifaces)
          Filter plugins based on verification.
     prepare()
          Prepare all plugins in the registry.
     available()
          Filter plugins based on availability.
     find_init (plugin)
          Find an initialized plugin.
          This is particularly useful for finding a name for the plugin (although IPluginFactory.__call__
          takes name as one of the arguments, IPlugin. name is not part of the interface):
          # plugin is an instance providing IPlugin, initialized
          # somewhere else in the code
```

Returns None if plugin is not found in the registry.

plugin_registry.find_init(plugin).name

7.14 certbot.plugins.dns_common

Common code for DNS Authenticator Plugins.

```
class certbot.plugins.dns_common.DNSAuthenticator (config, name)
    Bases: certbot.plugins.common.Plugin

Base class for DNS Authenticators

_setup_credentials()
    Establish credentials, prompting if necessary.

_perform(domain, validation_domain_name, validation)
    Performs a dns-01 challenge by creating a DNS TXT record.
```

- domain (str) The domain being validated.
- validation_domain_name (str) The validation record domain name.

• **validation** (*str*) – The validation record content.

Raises errors.PluginError – If the challenge cannot be performed

_cleanup (domain, validation_domain_name, validation)

Deletes the DNS TXT record which would have been created by _perform_achall.

Fails gracefully if no such record exists.

Parameters

- **domain** (str) The domain being validated.
- validation_domain_name (str) The validation record domain name.
- **validation** (*str*) The validation record content.

_configure (key, label)

Ensure that a configuration value is available.

If necessary, prompts the user and stores the result.

Parameters

- **key** (str) The configuration key.
- label (str) The user-friendly label for this piece of information.

```
_configure_file (key, label, validator=None)
```

Ensure that a configuration value is available for a path.

If necessary, prompts the user and stores the result.

Parameters

- **key** (str) The configuration key.
- label (str) The user-friendly label for this piece of information.

```
_configure_credentials (key, label, required_variables=None)
```

As _configure_file, but for a credential configuration file.

If necessary, prompts the user and stores the result.

Always stores absolute paths to avoid issues during renewal.

Parameters

- **key** (str) The configuration key.
- label (str) The user-friendly label for this piece of information.
- required_variables (dict) Map of variable which must be present to error to display.

```
static _prompt_for_data (label)
```

Prompt the user for a piece of information.

Parameters label (str) – The user-friendly label for this piece of information.

Returns The user's response (guaranteed non-empty).

Return type str

static _prompt_for_file (label, validator=None)

Prompt the user for a path.

- label (str) The user-friendly label for the file.
- **validator** (*callable*) A method which will be called to validate the supplied input after it has been validated to be a non-empty path to an existing file. Should throw a *PluginError* to indicate any issue.

Returns The user's response (guaranteed to exist).

```
Return type str
```

```
class certbot.plugins.dns_common.CredentialsConfiguration(filename, mapper=<function <lambda> at\ 0x65316e0>)
```

Bases: object

Represents a user-supplied filed which stores API credentials.

```
require (required_variables)
```

Ensures that the supplied set of variables are all present in the file.

Parameters required_variables (dict) – Map of variable which must be present to error to display.

Raises errors.PluginError – If one or more are missing.

```
conf (var)
```

Find a configuration value for variable var, as transformed by mapper.

Parameters var(str) – The variable to get.

Returns The value of the variable.

Return type str

```
certbot.plugins.dns_common.validate_file (filename)
```

Ensure that the specified file exists.

```
certbot.plugins.dns_common.validate_file_permissions(filename)
```

Ensure that the specified file exists and warn about unsafe permissions.

```
certbot.plugins.dns common.base domain name quesses (domain)
```

Return a list of progressively less-specific domain names.

One of these will probably be the domain name known to the DNS provider.

Example

Parameters domain (str) – The domain for which to return guesses.

Returns The a list of less specific domain names.

Return type list

7.15 certbot.plugins.dns_common_lexicon

Common code for DNS Authenticator Plugins built on Lexicon.

```
class certbot.plugins.dns_common_lexicon.LexiconClient
```

Bases: object

Encapsulates all communication with a DNS provider via Lexicon.

add_txt_record (domain, record_name, record_content)

Add a TXT record using the supplied information.

Parameters

- **domain** (str) The domain to use to look up the managed zone.
- record_name (str) The record name (typically beginning with '_acme-challenge.').
- **record_content** (*str*) The record content (typically the challenge validation).

Raises errors.PluginError – if an error occurs communicating with the DNS Provider API

del_txt_record (domain, record_name, record_content)

Delete a TXT record using the supplied information.

Parameters

- **domain** (str) The domain to use to look up the managed zone.
- record_name (str) The record name (typically beginning with '_acme-challenge.').
- record_content (str) The record content (typically the challenge validation).

Raises errors.PluginError – if an error occurs communicating with the DNS Provider API

```
_find_domain_id(domain)
```

Find the domain_id for a given domain.

Parameters domain (str) – The domain for which to find the domain_id.

Raises errors.PluginError – if the domain_id cannot be found.

7.16 certbot.plugins.manual

Manual authenticator plugin

```
class certbot.plugins.manual.Authenticator(*args, **kwargs)
    Bases: certbot.plugins.common.Plugin
```

Manual authenticator

This plugin allows the user to perform the domain validation challenge(s) themselves. This either be done manually by the user or through shell scripts provided to Certbot.

7.17 certbot.plugins.standalone

Standalone Authenticator.

```
class certbot.plugins.standalone.ServerManager(certs, http_01_resources)
     Bases: object
```

Standalone servers manager.

Manager for ACMEServer and ACMETLSServer instances.

certs and http_01_resources correspond to acme.crypto_util.SSLSocket.certs and acme.crypto_util.SSLSocket.http_01_resources respectively. All created servers share the same certificates and resources, so if you're running both TLS and non-TLS instances, HTTP01 handlers will serve the same URLs!

```
run (port, challenge_type, listenaddr='')
```

Run ACME server on specified port.

This method is idempotent, i.e. all calls with the same pair of (port, challenge_type) will reuse the same server.

Parameters

- **port** (*int*) Port to run the server on.
- challenge_type Subclass of acme.challenges.Challenge, either acme. challenge.HTTP01 or acme.challenges.TLSSNI01.
- **listenaddr** (str) (optional) The address to listen on. Defaults to all addrs.

Returns DualNetworkedServers instance.

Return type ACMEServerMixin

```
stop (port)
```

Stop ACME server running on the specified port.

```
Parameters port (int) -
```

running()

Return all running instances.

Once the server is stopped using stop, it will not be returned.

Returns Mapping from port to servers.

Return type tuple

```
{\bf class} \; {\tt certbot.plugins.standalone.SupportedChallengesAction} \; ({\it option\_strings},
```

dest, nargs=None, const=None, default=None, type=None, choices=None, required=False, help=None, metavar=None)

Bases: argparse.Action

Action class for parsing standalone_supported_challenges.

```
_convert_and_validate(data)
```

Validate the value of supported challenges provided by the user.

References to "dvsni" are automatically converted to "tls-sni-01".

Parameters data (str) – comma delimited list of challenge types

Returns validated and converted list of challenge types

Return type str

```
class certbot.plugins.standalone.Authenticator(*args, **kwargs)
```

Bases: certbot.plugins.common.Plugin

Standalone Authenticator.

This authenticator creates its own ephemeral TCP listener on the necessary port in order to respond to incoming tls-sni-01 and http-01 challenges from the certificate authority. Therefore, it does not rely on any existing server program.

supported_challenges

Challenges supported by this plugin.

7.18 certbot.plugins.util

```
Plugin utilities.
```

```
certbot.plugins.util.path_surgery (cmd)
Attempt to perform PATH surgery to find cmd
Mitigates https://github.com/certbot/certbot/issues/1833
```

Parameters cmd(str) – the command that is being searched for in the PATH

Returns True if the operation succeeded, False otherwise

7.19 certbot.plugins.webroot

```
Webroot plugin.
```

```
class certbot.plugins.webroot.Authenticator(*args, **kwargs)
     Bases: certbot.plugins.common.Plugin
     Webroot Authenticator.
class certbot.plugins.webroot._WebrootMapAction(option_strings,
                                                                         dest,
                                                                                 nargs=None,
                                                         const=None, default=None, type=None,
                                                         choices=None.
                                                                               required=False,
                                                         help=None, metavar=None)
     Bases: argparse. Action
     Action class for parsing webroot_map.
class certbot.plugins.webroot._WebrootPathAction(*args, **kwargs)
     Bases: argparse. Action
     Action class for parsing webroot_path.
certbot.plugins.webroot._validate_webroot(webroot_path)
     Validates and returns the absolute path of webroot_path.
         Parameters webroot_path (str) - path to the webroot directory
         Returns absolute path of webroot_path
         Return type str
```

7.20 certbot.reporter

Collects and displays information to the user.

```
class certbot.reporter.Reporter(config)
    Bases: object
```

Collects and displays information to the user.

Variables messages (queue.PriorityQueue) - Messages to be displayed to the user.

HIGH PRIORITY = 0

High priority constant. See add_message.

MEDIUM PRIORITY = 1

Medium priority constant. See add_message.

LOW PRIORITY = 2

Low priority constant. See add_message.

_msg_type

alias of ReporterMsg

add_message (msg, priority, on_crash=True)

Adds msg to the list of messages to be printed.

Parameters

- msg(str) Message to be displayed to the user.
- priority (int) One of HIGH_PRIORITY, MEDIUM_PRIORITY, or LOW PRIORITY.
- on_crash (bool) Whether or not the message should be printed if the program exits abnormally.

print_messages()

Prints messages to the user and clears the message queue.

If there is an unhandled exception, only messages for which on_crash is True are printed.

7.21 certbot.reverter

Reverter class saves configuration checkpoints and allows for recovery.

```
class certbot.reverter.Reverter(config)
    Bases: object
```

Reverter Class - save and revert configuration checkpoints.

This class can be used by the plugins, especially Installers, to undo changes made to the user's system. Modifications to files and commands to do undo actions taken by the plugin should be registered with this class before the action is taken.

Once a change has been registered with this class, there are three states the change can be in. First, the change can be a temporary change. This should be used for changes that will soon be reverted, such as config changes for the purpose of solving a challenge. Changes are added to this state through calls to add_to_temp_checkpoint() and reverted when revert_temporary_config() or recovery_routine() is called.

The second state a change can be in is in progress. These changes are not temporary, however, they also have not been finalized in a checkpoint. A change must become in progress before it can be finalized. Changes are added to this state through calls to <code>add_to_checkpoint()</code> and reverted when <code>recovery_routine()</code> is called.

The last state a change can be in is finalized in a checkpoint. A change is put into this state by first becoming an in progress change and then calling <code>finalize_checkpoint()</code>. Changes in this state can be reverted through calls to <code>rollback checkpoints()</code>.

As a final note, creating new files and registering undo commands are handled specially and use the methods $register_file_creation()$ and $register_undo_command()$ respectively. Both of these methods can be used to create either temporary or in progress changes.

Note: Consider moving everything over to CSV format.

Parameters config (certbot.interfaces.IConfig) - Configuration.

revert_temporary_config()

Reload users original configuration files after a temporary save.

This function should reinstall the users original configuration files for all saves with temporary=True

Raises ReverterError – when unable to revert config

```
rollback_checkpoints(rollback=1)
```

Revert 'rollback' number of configuration checkpoints.

Parameters rollback (*int*) – Number of checkpoints to reverse. A str num will be cast to an integer. So "2" is also acceptable.

Raises *ReverterError* – if there is a problem with the input or if the function is unable to correctly revert the configuration checkpoints

view_config_changes (for_logging=False, num=None)

Displays all saved checkpoints.

All checkpoints are printed by certbot.interfaces.IDisplay.notification().

Todo

Decide on a policy for error handling, OSError IOError...

Raises errors.ReverterError – If invalid directory structure.

add_to_temp_checkpoint (save_files, save_notes)

Add files to temporary checkpoint.

Parameters

- **save_files** (set) set of filepaths to save
- **save_notes** (str) notes about changes during the save

add_to_checkpoint (save_files, save_notes)

Add files to a permanent checkpoint.

Parameters

- **save_files** (*set*) set of filepaths to save
- **save_notes** (str) notes about changes during the save

_add_to_checkpoint_dir(cp_dir, save_files, save_notes)

Add save files to checkpoint directory.

Parameters

- cp_dir (str) Checkpoint directory filepath
- save_files (set) set of files to save
- **save_notes** (str) notes about changes made during the save

Raises

- **IOError** if unable to open cp dir + FILEPATHS file
- ReverterError if unable to add checkpoint

_read_and_append(filepath)

Reads the file lines and returns a file obj.

Read the file returning the lines, and a pointer to the end of the file.

```
_recover_checkpoint(cp_dir)
```

Recover a specific checkpoint.

Recover a specific checkpoint provided by cp_dir Note: this function does not reload augeas.

```
Parameters cp_dir(str) – checkpoint directory file path
```

Raises errors. ReverterError - If unable to recover checkpoint

```
_run_undo_commands (filepath)
```

Run all commands in a file.

```
_check_tempfile_saves(save_files)
```

Verify save isn't overwriting any temporary files.

Parameters save_files (set) – Set of files about to be saved.

Raises certbot.errors.ReverterError – when save is attempting to overwrite a temporary file.

```
register_file_creation (temporary, *files)
```

Register the creation of all files during certbot execution.

Call this method before writing to the file to make sure that the file will be cleaned up if the program exits unexpectedly. (Before a save occurs)

Parameters

- **temporary** (bool) If the file creation registry is for a temp or permanent save.
- *files file paths (str) to be registered

Raises *certbot*. *errors*. *ReverterError* – If call does not contain necessary parameters or if the file creation is unable to be registered.

$\verb"register_undo_command" (\textit{temporary}, \textit{command})$

Register a command to be run to undo actions taken.

Warning: This function does not enforce order of operations in terms of file modification vs. command registration. All undo commands are run first before all normal files are reverted to their previous state. If you need to maintain strict order, you may create checkpoints before and after the the command registration. This function may be improved in the future based on demand.

- **temporary** (bool) Whether the command should be saved in the IN_PROGRESS or TEMPORARY checkpoints.
- command (list of str) Command to be run.

```
_get_cp_dir(temporary)
```

Return the proper reverter directory.

recovery_routine()

Revert configuration to most recent finalized checkpoint.

Remove all changes (temporary and permanent) that have not been finalized. This is useful to protect against crashes and other execution interruptions.

Raises errors. ReverterError – If unable to recover the configuration

```
_remove_contained_files(file_list)
```

Erase all files contained within file_list.

Parameters file_list (str) – file containing list of file paths to be deleted

Returns Success

Return type bool

Raises certbot.errors.ReverterError - If all files within file_list cannot be removed

finalize_checkpoint (title)

Finalize the checkpoint.

Timestamps and permanently saves all changes made through the use of $add_to_checkpoint()$ and $register_file_creation()$

Parameters title (str) – Title describing checkpoint

Raises certbot.errors.ReverterError — when the checkpoint is not able to be finalized.

_checkpoint_timestamp()

Determine the timestamp of the checkpoint, enforcing monotonicity.

_timestamp_progress_dir()

Timestamp the checkpoint.

7.22 certbot.storage

Renewable certificates storage.

```
\verb|certbot.storage.renewal_conf_files| (config)|\\
```

Build a list of all renewal configuration files.

Parameters config (certbot.interfaces.IConfig) - Configuration object

Returns list of renewal configuration files

Return type list of str

```
certbot.storage.renewal_file_for_certname(config, certname)
```

Return /path/to/certname.conf in the renewal conf directory

```
certbot.storage.config_with_defaults(config=None)
```

Merge supplied config, if provided, on top of builtin defaults.

certbot.storage.add_time_interval(base_time, interval, textparser=<parsedatetime.Calendar object at 0x5337690>)

Parse the time specified time interval, and add it to the base_time

The interval can be in the English-language format understood by parsedatetime, e.g., '10 days', '3 weeks', '6 months', '9 hours', or a sequence of such intervals like '6 months 1 week' or '3 days 12 hours'. If an integer is found with no associated unit, it is interpreted by default as a number of days.

Parameters

- base_time (datetime.datetime) The time to be added with the interval.
- **interval** (*str*) The time interval to parse.

Returns The base_time plus the interpretation of the time interval.

Return type datetime.datetime

certbot.storage.write_renewal_config(o_filename, n_filename, archive_dir, target, relevant data)

Writes a renewal config file with the specified name and values.

Parameters

- o_filename (str) Absolute path to the previous version of config file
- n_filename (str) Absolute path to the new destination of config file
- archive_dir(str) Absolute path to the archive directory
- target (dict) Maps ALL_FOUR to their symlink paths
- relevant_data (dict) Renewal configuration options to save

Returns Configuration object for the new config file

Return type configobj.ConfigObj

certbot.storage.rename_renewal_config (prev_name, new_name, cli_config)
Renames cli_config.certname's config to cli_config.new_certname.

Parameters cli_config (NamespaceConfig) - parsed command line arguments

certbot.storage.update_configuration(lineagename, archive_dir, target, cli_config)
Modifies lineagename's config to contain the specified values.

Parameters

- lineagename (str) Name of the lineage being modified
- **archive dir** (str) Absolute path to the archive directory
- target (dict) Maps ALL_FOUR to their symlink paths
- cli_config (NamespaceConfig) parsed command line arguments

Returns Configuration object for the updated config file

Return type configobj.ConfigObj

```
certbot.storage.get_link_target(link)
```

Get an absolute path to the target of link.

Parameters link (str) - Path to a symbolic link

Returns Absolute path to the target of link

Return type str

```
certbot.storage. relevant (option)
```

Is this option one that could be restored for future renewal purposes? :param str option: the name of the option

Return type bool

```
certbot.storage.relevant_values(all_values)
```

Return a new dict containing only items relevant for renewal.

Parameters all_values (dict) – The original values.

Returns A new dictionary containing items that can be used in renewal.

Rtype dict

```
\verb|certbot.storage.lineagename_for_filename| (config_filename)|\\
```

Returns the lineagename for a configuration filename.

```
certbot.storage.renewal_filename_for_lineagename(config, lineagename)
```

Returns the lineagename for a configuration filename.

```
certbot.storage._relpath_from_file(archive_dir, from_file)
```

Path to a directory from a file

```
certbot.storage._full_archive_path(config_obj, cli_config, lineagename)
```

Returns the full archive path for a lineagename

Uses cli_config to determine archive path if not available from config_obj.

Parameters

- config obj (configobj.ConfigObj) Renewal conf file contents (can be None)
- cli_config (configuration.NamespaceConfig) Main config file
- lineagename (str) Certificate name

```
certbot.storage._full_live_path(cli_config, lineagename)
```

Returns the full default live path for a lineagename

```
certbot.storage.delete_files(config, certname)
```

Delete all files related to the certificate.

If some files are not found, ignore them and continue.

```
class certbot.storage.RenewableCert (config_filename, cli_config, update_symlinks=False)
```

Bases: object

Renewable certificate.

Represents a lineage of certificates that is under the management of Certbot, indicated by the existence of an associated renewal configuration file.

Note that the notion of "current version" for a lineage is maintained on disk in the structure of symbolic links, and is not explicitly stored in any instance variable in this object. The RenewableCert object is able to determine information about the current (or other) version by accessing data on disk, but does not inherently know any of this information except by examining the symbolic links as needed. The instance variables mentioned below point to symlinks that reflect the notion of "current version" of each managed object, and it is these paths that should be used when configuring servers to use the certificate managed in a lineage. These paths are normally within the "live" directory, and their symlink targets – the actual cert files – are normally found within the "archive" directory.

Variables

• **cert** (*str*) – The path to the symlink representing the current version of the certificate managed by this lineage.

- **privkey** (str) The path to the symlink representing the current version of the private key managed by this lineage.
- **chain** (str) The path to the symlink representing the current version of the chain managed by this lineage.
- **fullchain** (*str*) The path to the symlink representing the current version of the fullchain (combined chain and cert) managed by this lineage.
- **configuration** (configobj.ConfigObj) The renewal configuration options associated with this lineage, obtained from parsing the renewal configuration file and/or systemwide defaults.

key_path

Duck type for self.privkey

cert_path

Duck type for self.cert

chain_path

Duck type for self.chain

fullchain_path

Duck type for self.fullchain

target_expiry

The current target certificate's expiration datetime

Returns Expiration datetime of the current target certificate

Return type datetime.datetime

archive_dir

Returns the default or specified archive directory

relative_archive_dir (from_file)

Returns the default or specified archive directory as a relative path

Used for creating symbolic links.

is_test_cert

Returns true if this is a test cert from a staging server.

_check_symlinks()

Raises an exception if a symlink doesn't exist

_update_symlinks()

Updates symlinks to use archive_dir

consistent()

Are the files associated with this lineage self-consistent?

Returns Whether the files stored in connection with this lineage appear to be correct and consistent with one another.

Return type bool

fix()

Attempt to fix defects or inconsistencies in this lineage.

Todo

Currently unimplemented.

_previous_symlinks()

Returns the kind and path of all symlinks used in recovery.

Returns list of (kind, symlink) tuples

Return type list

fix symlinks()

Fixes symlinks in the event of an incomplete version update.

If there is no problem with the current symlinks, this function has no effect.

current_target (kind)

Returns full path to which the specified item currently points.

Parameters kind (str) - the lineage member item ("cert", "privkey", "chain", or "fullchain")

Returns The path to the current version of the specified member.

Return type str or None

current_version (kind)

Returns numerical version of the specified item.

For example, if kind is "chain" and the current chain link points to a file named "chain7.pem", returns the integer 7.

Parameters kind (str) - the lineage member item ("cert", "privkey", "chain", or "fullchain")

Returns the current version of the specified member.

Return type int

version (kind, version)

The filename that corresponds to the specified version and kind.

Warning: The specified version may not exist in this lineage. There is no guarantee that the file path returned by this method actually exists.

Parameters

- kind (str) the lineage member item ("cert", "privkey", "chain", or "fullchain")
- **version** (*int*) the desired version

Returns The path to the specified version of the specified member.

Return type str

available_versions (kind)

Which alternative versions of the specified kind of item exist?

The archive directory where the current version is stored is consulted to obtain the list of alternatives.

Parameters kind (str) - the lineage member item (cert, privkey, chain, or fullchain)

Returns all of the version numbers that currently exist

Return type list of int

newest_available_version(kind)

Newest available version of the specified kind of item?

Parameters kind (str) - the lineage member item (cert, privkey, chain, or fullchain)

Returns the newest available version of this member

Return type int

latest_common_version()

Newest version for which all items are available?

Returns the newest available version for which all members (cert, ``privkey, chain, and fullchain) exist

Return type int

next_free_version()

Smallest version newer than all full or partial versions?

Returns the smallest version number that is larger than any version of any item currently stored in this lineage

Return type int

ensure_deployed()

Make sure we've deployed the latest version.

Returns False if a change was needed, True otherwise

Return type bool

May need to recover from rare interrupted / crashed states.

has_pending_deployment()

Is there a later version of all of the managed items?

Returns True if there is a complete version of this lineage with a larger version number than the current version, and False otherwise

Return type bool

_update_link_to(kind, version)

Make the specified item point at the specified version.

(Note that this method doesn't verify that the specified version exists.)

Parameters

- kind (str) the lineage member item ("cert", "privkey", "chain", or "fullchain")
- **version** (*int*) the desired version

update_all_links_to(version)

Change all member objects to point to the specified version.

Parameters version (int) – the desired version

names (version=None)

What are the subject names of this certificate?

(If no version is specified, use the current version.)

Parameters version (int) – the desired version number

Returns the subject names

Return type list of str

Raises *CertStorageError* – if could not find cert file.

autodeployment is enabled()

Is automatic deployment enabled for this cert?

If autodeploy is not specified, defaults to True.

Returns True if automatic deployment is enabled

Return type bool

should_autodeploy (interactive=False)

Should this lineage now automatically deploy a newer version?

This is a policy question and does not only depend on whether there is a newer version of the cert. (This considers whether autodeployment is enabled, whether a relevant newer version exists, and whether the time interval for autodeployment has been reached.)

Parameters interactive (bool) – set to True to examine the question regardless of whether the renewal configuration allows automated deployment (for interactive use). Default False.

Returns whether the lineage now ought to autodeploy an existing newer cert version

Return type bool

ocsp_revoked (version=None)

Is the specified cert version revoked according to OCSP?

Also returns True if the cert version is declared as intended to be revoked according to Let's Encrypt OCSP extensions. (If no version is specified, uses the current version.)

This method is not yet implemented and currently always returns False.

Parameters version (int) – the desired version number

Returns whether the certificate is or will be revoked

Return type bool

autorenewal_is_enabled()

Is automatic renewal enabled for this cert?

If autorenew is not specified, defaults to True.

Returns True if automatic renewal is enabled

Return type bool

should_autorenew (interactive=False)

Should we now try to autorenew the most recent cert version?

This is a policy question and does not only depend on whether the cert is expired. (This considers whether autorenewal is enabled, whether the cert is revoked, and whether the time interval for autorenewal has been reached.)

Note that this examines the numerically most recent cert version, not the currently deployed version.

Parameters interactive (bool) – set to True to examine the question regardless of whether the renewal configuration allows automated renewal (for interactive use). Default False.

Returns whether an attempt should now be made to autorenew the most current cert version in this lineage

Return type bool

classmethod new_lineage (lineagename, cert, privkey, chain, cli_config)

Create a new certificate lineage.

Attempts to create a certificate lineage – enrolled for potential future renewal – with the (suggested) lineage name lineagename, and the associated cert, privkey, and chain (the associated fullchain will be created automatically). Optional configurator and renewalparams record the configuration that was originally used to obtain this cert, so that it can be reused later during automated renewal.

Returns a new RenewableCert object referring to the created lineage. (The actual lineage name, as well as all the relevant file paths, will be available within this object.)

Parameters

- **lineagename** (str) the suggested name for this lineage (normally the current cert's first subject DNS name)
- cert (str) the initial certificate version in PEM format
- **privkey** (str) the private key in PEM format
- chain (str) the certificate chain in PEM format
- cli_config (NamespaceConfig) parsed command line arguments

Returns the newly-created RenewalCert object

Return type storage.renewableCert

save_successor (prior_version, new_cert, new_privkey, new_chain, cli_config)

Save new cert and chain as a successor of a prior version.

Returns the new version number that was created.

Note: this function does NOT update links to deploy this version

Parameters

- **prior_version** (*int*) the old version to which this version is regarded as a successor (used to choose a privkey, if the key has not changed, but otherwise this information is not permanently recorded anywhere)
- new_cert (bytes) the new certificate, in PEM format
- new_privkey (bytes) the new private key, in PEM format, or None, if the private key has not changed
- new_chain (bytes) the new chain, in PEM format
- cli_config (NamespaceConfig) parsed command line arguments

Returns the new version number that was created

Return type int

7.23 certbot.util

```
Utilities for all Certbot.
```

```
class certbot.util.Key (file, pem)
    Bases: tuple
    _asdict()
```

Return a new OrderedDict which maps field names to their values

```
classmethod _make (iterable, new=<built-in method __new__ of type object at 0x8a9340>, len=<built-
                          in function len>)
          Make a new Key object from a sequence or iterable
     replace ( self, **kwds)
          Return a new Key object replacing specified fields with new values
          Alias for field number 0
     pem
          Alias for field number 1
class certbot.util.CSR (file, data, form)
     Bases: tuple
      asdict()
          Return a new OrderedDict which maps field names to their values
     classmethod _make (iterable, new=<built-in method __new__ of type object at 0x8a9340>, len=<built-
                          in function len>)
          Make a new CSR object from a sequence or iterable
     _replace(_self, **kwds)
          Return a new CSR object replacing specified fields with new values
     data
          Alias for field number 1
     file
          Alias for field number 0
     form
          Alias for field number 2
certbot.util.run_script (params, log=<bound method Logger.error of <logging.Logger object at
                                 0x4909e10 >> )
     Run the script with the given params.
          Parameters
                 • params (list) - List of parameters to pass to Popen
                 • log (logging.Logger) – Logger to use for errors
certbot.util.exe exists(exe)
     Determine whether path/name refers to an executable.
          Parameters exe (str) – Executable path or name
          Returns If exe is a valid executable
          Return type bool
certbot.util.lock_dir_until_exit (dir_path)
     Lock the directory at dir_path until program exit.
          Parameters dir_path (str) – path to directory
          Raises errors. LockError – if the lock is held by another process
certbot.util.set_up_core_dir(directory, mode, uid, strict)
     Ensure directory exists with proper permissions and is locked.
          Parameters
```

7.23. certbot.util 97

- **directory** (*str*) Path to a directory.
- mode (int) Directory mode.
- **uid** (*int*) Directory owner.
- **strict** (bool) require directory to be owned by current user

Raises

- errors. LockError if the directory cannot be locked
- errors. Error if the directory cannot be made or verified

certbot.util.make_or_verify_dir(directory, mode=493, uid=0, strict=False)
Make sure directory exists with proper permissions.

Parameters

- **directory** (str) Path to a directory.
- mode (int) Directory mode.
- **uid** (*int*) Directory owner.
- **strict** (bool) require directory to be owned by current user

Raises

- errors. Error if a directory already exists, but has wrong permissions or owner
- **OSETTOT** if invalid or inaccessible file names and paths, or other arguments that have the correct type, but are not accepted by the operating system.

certbot.util.check_permissions (filepath, mode, uid=0) Check file or directory permissions.

Parameters

- **filepath** (*str*) Path to the tested file (or directory).
- mode (int) Expected file mode.
- **uid** (*int*) Expected file owner.

Returns True if mode and uid match, False otherwise.

Return type bool

certbot.util.safe_open (path, mode='w', chmod=None, buffering=None) Safely open a file.

Parameters

- path (str) Path to a file.
- mode (str) Same os mode for open.
- **chmod** (int) Same as mode for os.open, uses Python defaults if None.
- buffering (int) Same as bufsize for os.fdopen, uses Python defaults if None.

certbot.util.unique_file (path, chmod=511, mode='w') Safely finds a unique file.

- path (str) path/filename.ext
- chmod (int) File mode

```
certbot.util.unique_lineage_name (path, filename, chmod=420, mode='w')
     Safely finds a unique file using lineage convention.
          Parameters
                • path (str) - directory path
                • filename (str) – proposed filename
                • chmod (int) - file mode
                • mode (str) – open mode
          Returns tuple of file object and file name (which may be modified from the requested one by ap-
              pending digits to ensure uniqueness)
          Raises OSError – if writing files fails for an unanticipated reason, such as a full disk or a lack of
              permission to write to specified location.
certbot.util.safely_remove(path)
     Remove a file that may not exist.
certbot.util.get_filtered_names (all_names)
     Removes names that aren't considered valid by Let's Encrypt.
          Parameters all names (set) – all names found in the configuration
          Returns all found names that are considered valid by LE
          Return type set
certbot.util.get_os_info(filepath='/etc/os-release')
     Get OS name and version
          Parameters filepath (str) – File path of os-release file
          Returns (os_name, os_version)
          Return type tuple of str
certbot.util.get os info ua(filepath='/etc/os-release')
     Get OS name and version string for User Agent
          Parameters filepath (str) – File path of os-release file
          Returns os_ua
          Return type str
certbot.util.get_systemd_os_info(filepath='/etc/os-release')
     Parse systemd /etc/os-release for distribution information
          Parameters filepath (str) – File path of os-release file
          Returns (os_name, os_version)
          Return type tuple of str
certbot.util.get_systemd_os_like(filepath='/etc/os-release')
```

Get a list of strings that indicate the distribution likeness to other distributions.

Parameters filepath (str) – File path of os-release file

Returns List of distribution acronyms

• mode (str) – Open mode

Returns tuple of file object and file name

7.23. certbot.util 99

```
Return type list of str
certbot.util._get_systemd_os_release_var(varname, filepath='/etc/os-release')
     Get single value from systemd /etc/os-release
          Parameters
                • varname (str) - Name of variable to fetch
                • filepath (str) – File path of os-release file
          Returns requested value
          Return type str
certbot.util. normalize string(orig)
```

Helper function for _get_systemd_os_release_var() to remove quotes and whitespaces

```
certbot.util.get_python_os_info()
```

Get Operating System type/distribution and major version using python platform module

Returns (os_name, os_version)

Return type tuple of str

```
certbot.util.safe_email(email)
```

Scrub email address before using it.

class certbot.util._ShowWarning(option_strings, dest, nargs=None, const=None, default=None, type=None. choices=None. required=False, help=None. *metavar=None*)

Bases: argparse. Action

Action to log a warning when an argument is used.

```
certbot.util.add_deprecated_argument (add_argument, argument_name, nargs)
```

Adds a deprecated argument with the name argument name.

Deprecated arguments are not shown in the help. If they are used on the command line, a warning is shown stating that the argument is deprecated and no other action is taken.

Parameters

- add_argument (callable) Function that adds arguments to an argument parser/group.
- **argument_name** (*str*) Name of deprecated argument.
- **nargs** Value for nargs when adding the argument to argparse.

```
certbot.util.enforce_le_validity(domain)
```

Checks that Let's Encrypt will consider domain to be valid.

```
Parameters domain (str or unicode) - FQDN to check
```

Returns The domain cast to str, with ASCII-only contents

Return type str

Raises ConfigurationError – for invalid domains and cases where Let's Encrypt currently will not issue certificates

```
certbot.util.enforce domain sanity(domain)
```

Method which validates domain value and errors out if the requirements are not met.

Parameters domain (str or unicode) - Domain to check

Raises ConfigurationError – for invalid domains and cases where Let's Encrypt currently will not issue certificates

Returns The domain cast to str, with ASCII-only contents

Return type str

```
certbot.util.get_strict_version(normalized)
```

Converts a normalized version to a strict version.

Parameters normalized (str) – normalized version string

Returns An equivalent strict version

Return type distutils.version.StrictVersion

```
certbot.util.is_staging(srv)
```

Determine whether a given ACME server is a known test / staging server.

Parameters srv (str) - the URI for the ACME server

Returns True iff srv is a known test / staging server

Rtype bool

```
certbot.util.atexit_register(func, *args, **kwargs)
```

Sets func to be called before the program exits.

Special care is taken to ensure func is only called when the process that first imports this module exits rather than any child processes.

Parameters func (function) – function to be called in case of an error

7.23. certbot.util

CHAPTER

EIGHT

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

С

```
certbot, 68
certbot.account, 45
certbot.achallenges, 46
certbot.auth_handler,47
certbot.client, 50
certbot.configuration, 54
certbot.constants, 54
certbot.crypto_util,55
certbot.display, 59
\operatorname{certbot.display.enhancements}, 66
certbot.display.ops, 64
certbot.display.util,59
certbot.errors,66
certbot.interfaces, 68
certbot.plugins.common,77
certbot.plugins.disco,79
certbot.plugins.dns_common, 80
certbot.plugins.dns_common_lexicon,82
certbot.plugins.manual, 83
certbot.plugins.standalone,83
certbot.plugins.util,85
certbot.plugins.webroot,85
certbot.reporter,85
certbot.reverter,86
certbot.storage, 89
certbot.util,96
```

106 Python Module Index

INDEX

Symbols	_explode_ipv6() (certbot.plugins.common.Addr method),
_ShowWarning (class in certbot.util), 100	78
	_filter_names() (in module certbot.display.ops), 65 _find_domain_id() (cert-
_WebrootPathAction (class in certbot.plugins.webroot),	bot.plugins.dns_common_lexicon.LexiconClient method), 83
call() (certbot.interfaces.IPluginFactory method), 69 _add_to_checkpoint_dir() (certbot.reverter.Reverter	_find_dumb_path() (in module certbot.auth_handler), 49 _find_smart_path() (in module certbot.auth_handler), 49 _find_updated_challb() (cert- bot.auth_handler.AuthHandler method),
_asdict() (certbot.util.Key method), 96	48
_can_interact() (certbot.display.util.FileDisplay method), 61	_fix() (certbot.storage.RenewableCert method), 92 _fix_symlinks() (certbot.storage.RenewableCert method),
_challenge_factory() (certbot.auth_handler.AuthHandler method), 48	93 _full_archive_path() (in module certbot.storage), 91
_check_symlinks()	_full_live_path() (in module certbot.storage), 91 _gen_https_names() (in module certbot.display.ops), 65
_check_tempfile_saves()	_gen_ssl_lab_urls() (in module certbot.display.ops), 65 _generate_failed_chall_msg() (in module cert-
_checkpoint_timestamp() (certbot.reverter.Reverter method), 89	bot.auth_handler), 49 _get_chall_pref() (certbot.auth_handler.AuthHandler
_choose_challenges() (certbot.auth_handler.AuthHandler	method), 48
method), 47	_get_cp_dir() (certbot.reverter.Reverter method), 89
_choose_names_manually() (in module cert- bot.display.ops), 65	_get_systemd_os_release_var() (in module certbot.util), 100
_cleanup() (certbot.plugins.dns_common.DNSAuthenticate method), 81	or-get_valid_int_ans() (certbot.display.util.FileDisplay method), 62
_cleanup_challenges() (cert-	_handle_check() (certbot.auth_handler.AuthHandler method), 48
bot.auth_handler.AuthHandler method),	_interaction_fail() (cert-
48 _configure() (certbot.plugins.dns_common.DNSAuthentica	bot.display.util.NoninteractiveDisplay method),
method), 81	62
_configure_credentials() (cert-	_make() (certbot.util.CSR class method), 97
bot.plugins.dns_common.DNSAuthenticator	_make() (certbot.util.Key class method), 96
method), 81	_msg_type (certbot.reporter.Reporter attribute), 86
_configure_file() (certbot.plugins.dns_common.DNSAuthe method), 81	nticator alize_ipv6() (certbot.plugins.common.Addr method), 78
_consistent() (certbot.storage.RenewableCert method), 92	_normalize_string() (in module certbot.util), 100
convert and validate() (cert-	_notAfterBefore() (in module certbot.crypto_util), 58
bot.plugins.standalone.SupportedChallengesActi	onopen_pem_file() (in module certbot.client), 53
method), 84	_parens_around_char() (in module certbot.display.util),
	64

_perform() (certbot.plugins.dns_common.DNSAuthenticate method), 80	or_update_link_to() (certbot.storage.RenewableCert method), 94
_poll_challenges() (certbot.auth_handler.AuthHandler method), 47	_update_symlinks() (certbot.storage.RenewableCert method), 92
	_validate_webroot() (in module certbot.plugins.webroot),
_print_menu() (certbot.display.util.FileDisplay method),	_wrap_lines() (in module certbot.display.util), 59
_prompt_for_data() (cert-	A
bot.plugins.dns_common.DNSAuthenticator	Account (class in certbot.account), 45
static method), 81	Account.Meta (class in certbot.account), 45
_prompt_for_file() (cert-	AccountFileStorage (class in certbot.account), 46
bot.plugins.dns_common.DNSAuthenticator	AccountMemoryStorage (class in certbot.account), 45
static method), 81	AccountNotFound, 67
_read_and_append() (certbot.reverter.Reverter method),	accounts_dir (certbot.interfaces.IConfig attribute), 71
88	ACCOUNTS_DIR (in module certbot.constants), 55
_recover_checkpoint() (certbot.reverter.Reverter	AccountStorage (class in certbot.interfaces), 68
method), 88	AccountStorageError, 66
_recovery_routine_with_msg() (certbot.client.Client	acme_from_config_key() (in module certbot.client), 50
method), 53 _relevant() (in module certbot.storage), 90	acme_type (certbot.achallenges.DNS attribute), 46
_relpath_from_file() (in module certbot.storage), 90	add_chall() (certbot.plugins.common.TLSSNI01
_remove_contained_files() (certbot.reverter.Reverter	method), 78
method), 89	add_deprecated_argument() (in module certbot.util), 100
_replace() (certbot.util.CSR method), 97	add_message() (certbot.interfaces.IReporter method), 76 add_message() (certbot.reporter.Reporter method), 86
_replace() (certbot.util.Key method), 97	add_parser_arguments() (certbot.plugins.common.Plugin
_report_failed_challs() (in module certbot.auth_handler),	class method), 77
49	add_time_interval() (in module certbot.storage), 89
_report_no_chall_path() (in module cert-	add_to_checkpoint() (certbot.reverter.Reverter method),
bot.auth_handler), 49	87
_respond() (certbot.auth_handler.AuthHandler method),	add_to_temp_checkpoint() (certbot.reverter.Reverter
47	method), 87
_return_default() (certbot.display.util.FileDisplay method), 61	add_txt_record() (certbot.plugins.dns_common_lexicon.LexiconClier method), 83
_rollback_and_restart() (certbot.client.Client method), 53	Addr (class in certbot.plugins.common), 77
_run_undo_commands() (certbot.reverter.Reverter	allow_subset_of_names (certbot.interfaces.IConfig
method), 88	attribute), 71
_save_chain() (in module certbot.client), 53	AnnotatedChallenge (class in certbot.achallenges), 46
_scrub_checklist_input() (certbot.display.util.FileDisplay	apply_enhancement() (certbot.client.Client method), 52
method), 62	archive_dir (certbot.storage.RenewableCert attribute), 92
_send_responses() (certbot.auth_handler.AuthHandler	ARCHIVE_DIR (in module certbot.constants), 55
method), 47 _setup_challenge_cert() (cert-	ask() (in module certbot.display.enhancements), 66
bot.plugins.common.TLSSNI01 method),	assert_valid_call() (in module certbot.display.util), 62
78	atexit_register() (in module certbot.util), 101
_setup_credentials() (cert-	Authenticator (class in certbot.plugins.manual), 83 Authenticator (class in certbot.plugins.standalone), 84
bot.plugins.dns_common.DNSAuthenticator	Authenticator (class in certbot.plugins.standarone), 85
method), 80	AuthHandler (class in certbot.puglis.webroot), 63
_solve_challenges() (certbot.auth_handler.AuthHandler	AuthorizationError, 67
method), 47	autodeployment_is_enabled() (cert-
_sort_names() (in module certbot.display.ops), 65	bot.storage.RenewableCert method), 94
_timestamp_progress_dir() (certbot.reverter.Reverter	autorenewal_is_enabled() (cert-
method), 89	bot.storage.RenewableCert method), 95

available (certbot.plugins.disco.PluginEntryPoint at-	choose_names() (in module certbot.display.ops), 64
tribute), 79 available() (certbot.plugins.disco.PluginsRegistry	cleanup() (certbot.interfaces.IAuthenticator method), 70 Client (class in certbot.client), 51
method), 80	conf() (certbot.plugins.common.Plugin method), 77
available_versions() (certbot.storage.RenewableCert method), 93	conf() (certbot.plugins.dns_common.CredentialsConfiguration method), 82
	config_dir (certbot.interfaces.IConfig attribute), 71
В	CONFIG_DIRS_MODE (in module certbot.constants),
backup_dir (certbot.interfaces.IConfig attribute), 71	55
BACKUP_DIR (in module certbot.constants), 55	config_test() (certbot.interfaces.IInstaller method), 73
base_domain_name_guesses() (in module cert-	config_with_defaults() (in module certbot.storage), 89
bot.plugins.dns_common), 82	ConfigurationError, 68
	CredentialsConfiguration (class in cert-
C	bot.plugins.dns_common), 82
CANCEL (in module certbot.display.util), 59	CSR (class in certbot.util), 97
cert_path (certbot.storage.RenewableCert attribute), 92	csr_dir (certbot.interfaces.IConfig attribute), 71
certbot (module), 68	CSR_DIR (in module certbot.constants), 55
certbot.account (module), 45	csr_matches_pubkey() (in module certbot.crypto_util), 56
certbot.achallenges (module), 46	current_target() (certbot.storage.RenewableCert method),
certbot.auth_handler (module), 47	current_version() (certbot.storage.RenewableCert
certbot.client (module), 50	method), 93
certbot.configuration (module), 54	method), 93
certbot.constants (module), 54	D
certbot.crypto_util (module), 55	data (certbot.util.CSR attribute), 97
certbot.display (module), 59	del_txt_record() (certbot.plugins.dns_common_lexicon.LexiconClien
certbot.display.enhancements (module), 66	method), 83
certbot.display.ops (module), 64	delete() (certbot.account.AccountFileStorage method), 46
certbot.display.util (module), 59	delete_files() (in module certbot.storage), 91
certbot.errors (module), 66	deploy_cert() (certbot.interfaces.IInstaller method), 72
certbot.interfaces (module), 68 certbot.plugins.common (module), 77	deploy_certificate() (certbot.client.Client method), 52
certbot.plugins.common (module), 77	description (certbot.interfaces.IPluginFactory attribute),
certbot.plugins.disco (module), 79 certbot.plugins.dns_common (module), 80	69
certbot.plugins.dns_common_lexicon (module), 82	description (certbot.plugins.disco.PluginEntryPoint at-
certbot.plugins.manual (module), 83	tribute), 79
certbot.plugins.standalone (module), 83	description_with_name (cert-
certbot.plugins.util (module), 85	bot.plugins.disco.PluginEntryPoint attribute),
certbot.plugins.webroot (module), 85	79
certbot.reporter (module), 85	dest() (certbot.plugins.common.Plugin method), 77
certbot.reverter (module), 86	dest_namespace (certbot.plugins.common.Plugin at-
certbot.storage (module), 89	tribute), 77
certbot.util (module), 96	dest_namespace() (in module certbot.plugins.common),
certificate() (certbot.interfaces.IValidator method), 75	77
CertStorageError, 67	determine_user_agent() (in module certbot.client), 50
chain_path (certbot.storage.RenewableCert attribute), 92	dir_setup() (in module certbot.plugins.common), 79
challb_to_achall() (in module certbot.auth_handler), 48	directory_select() (certbot.display.util.FileDisplay
check_config_sanity() (in module certbot.configuration),	method), 61
54	directory_select() (cert-
check_permissions() (in module certbot.util), 98	bot.display.util.NoninteractiveDisplay method), 63
checklist() (certbot.display.util.FileDisplay method), 61	directory_select() (certbot.interfaces.IDisplay method),
checklist() (certbot.display.util.NoninteractiveDisplay	75
method), 63	DNS (class in certbot.achallenges), 46
checklist() (certbot.interfaces.IDisplay method), 75	21.5 (Tubb in certoonachanengeb), 10

choose_account() (in module certbot.display.ops), 64

DNSAuther bo		(class ns_common),	in 80	cert-	get_authorizations() (certbot.auth_handler.AuthHandler method), 47
dump_pyop	enssl_chain	certbot.client () (in module		o_util),	get_cert_path() (certbot.plugins.common.TLSSNI01 method), 78
58	8				get_chall_pref() (certbot.interfaces.IAuthenticator method), 70
E					get_email() (in module certbot.display.ops), 64
EFF_SUBS	CRIBE_UR	I (in module	certbot.cons	stants),	get_filtered_names() (in module certbot.util), 99
55					get_ipv6_exploded() (certbot.plugins.common.Addr
		s.IConfig attril			method), 78
		() (in module		100	get_key_path() (certbot.plugins.common.TLSSNI01
	•	n module certh faces.Hnstalle			method), 78 get_link_target() (in module certbot.storage), 90
		ot.client.Clien			get_names_from_cert() (in module certbot.crypto_util),
	_	module certb			58
ensure_depl			rage.Renewal		get_os_info() (in module certbot.util), 99
m	ethod), 94				get_os_info_ua() (in module certbot.util), 99
	_to_plugin_			(cert-	get_port() (certbot.plugins.common.Addr method), 78
		isco.PluginEnt	ryPoint	class	get_python_os_info() (in module certbot.util), 100
m Error, 66	ethod), 79				get_sans_from_cert() (in module certbot.crypto_util), 57 get_strict_version() (in module certbot.util), 101
	dule certbot	.display.util),	59		get_systemd_os_info() (in module certbot.util), 99
		certbot.util),			get_systemd_os_like() (in module certbot.util), 99
	(get_valid_domains() (in module certbot.display.ops), 64
F					11
FailedChall	-				Н
	.util.CSR at				has_pending_deployment() (cert-
	.util.Key att		50		bot.storage.RenewableCert method), 94
		rtbot.display.u s.disco.Plugins		athod)	HELP (in module certbot.display.util), 59 hidden (certbot.plugins.disco.PluginEntryPoint attribute),
8(s.disco.r iugilis	skegistiy iit	stilou),	79
		certbot.reverte	r.Reverter me	ethod),	HIGH_PRIORITY (certbot.interfaces.IReporter at-
- 89	_			,,	tribute), 76
		faces.Accounts	-	od), 68	HIGH_PRIORITY (certbot.reporter.Reporter attribute),
	_	gins.disco.Plu	ginsRegistry	class	86
	ethod), 80		DI ' D		HookCommandNotFound, 67
find_init()	cert) ethod), 80	tbot.plugins.di	sco.PluginsR	egistry	hsts() (certbot.interfaces.IValidator method), 76 http01_address (certbot.interfaces.IConfig attribute), 71
	TERACTIV	/E_FLAG(in module	cert-	http01_port (certbot.interfaces.IConfig attribute), 71
			in module	CCIT	mopor_port (cortectimetrial coming attailed), 71
	ot.constants	1, 33			_
	ot.constants) ot.util.CSR	attribute), 97			I
form (certbo fromstring()	ot.util.CSR (certbo		mon.Addr	class	IAuthenticator (interface in certbot.interfaces), 70
form (certbo fromstring() m	ot.util.CSR (certbonethod), 77	attribute), 97 ot.plugins.com			IConfig (interface in certbot.interfaces), 70
form (certbo fromstring() m fullchain_pa	ot.util.CSR (certbonethod), 77 ath (certbot.	attribute), 97			IConfig (interface in certbot.interfaces), 70 IDisplay (interface in certbot.interfaces), 73
form (certbo fromstring() m	ot.util.CSR (certbonethod), 77 ath (certbot.	attribute), 97 ot.plugins.com			IConfig (interface in certbot.interfaces), 70 IDisplay (interface in certbot.interfaces), 73 ifaces() (certbot.plugins.disco.PluginEntryPoint method),
form (certbo fromstring() m fullchain_pa	ot.util.CSR (certbonethod), 77 ath (certbot.	attribute), 97 ot.plugins.com			IConfig (interface in certbot.interfaces), 70 IDisplay (interface in certbot.interfaces), 73 ifaces() (certbot.plugins.disco.PluginEntryPoint method), 79
form (certbo fromstring() m fullchain_pa 92	ot.util.CSR (certbo) (certbo), 77 ath (certbot.	attribute), 97 ot.plugins.com .storage.Renev	vableCert attr	ribute),	IConfig (interface in certbot.interfaces), 70 IDisplay (interface in certbot.interfaces), 73 ifaces() (certbot.plugins.disco.PluginEntryPoint method),
form (certbo fromstring() m fullchain_pa 92	ot.util.CSR (a) (certboutethod), 77 ath (certbot.)	attribute), 97 ot.plugins.com	vableCert attr	ribute),	IConfig (interface in certbot.interfaces), 70 IDisplay (interface in certbot.interfaces), 73 ifaces() (certbot.plugins.disco.PluginEntryPoint method), 79 ifaces() (certbot.plugins.disco.PluginsRegistry method),
form (certbo fromstring() m fullchain_pa 92 G gen_challen 48 get_addr() (ot.util.CSR (a) (certbot ethod), 77 ath (certbot.) age_path() (8) (certbot.plug	attribute), 97 ot.plugins.com .storage.Renev (in module ce	vableCert attr rtbot.auth_ha	ribute), andler),	IConfig (interface in certbot.interfaces), 70 IDisplay (interface in certbot.interfaces), 73 ifaces() (certbot.plugins.disco.PluginEntryPoint method), 79 ifaces() (certbot.plugins.disco.PluginsRegistry method), 80
form (certbo fromstring() m fullchain_pa 92 G gen_challen 48 get_addr() (get_addr_ob	ot.util.CSR (a) (certbot ethod), 77 ath (certbot.) age_path() (a) (certbot.plug bj() (certbot.	attribute), 97 ot.plugins.com storage.Renev	vableCert attr rtbot.auth_ha	ribute), andler),	IConfig (interface in certbot.interfaces), 70 IDisplay (interface in certbot.interfaces), 73 ifaces() (certbot.plugins.disco.PluginEntryPoint method), 79 ifaces() (certbot.plugins.disco.PluginsRegistry method), 80 IInstaller (interface in certbot.interfaces), 72 import_csr_file() (in module certbot.crypto_util), 56 in_progress_dir (certbot.interfaces.IConfig attribute), 71
form (certbo fromstring() m fullchain_pa 92 G gen_challen 48 get_addr() (get_addr_ob	ot.util.CSR (a) (certbot ethod), 77 ath (certbot.) age_path() (a) (certbot.plug bj() (certbot.)	attribute), 97 ot.plugins.com .storage.Renev (in module ce	vableCert attr rtbot.auth_ha Addr method) non.Addr mo	endler), 1, 78 ethod),	IConfig (interface in certbot.interfaces), 70 IDisplay (interface in certbot.interfaces), 73 ifaces() (certbot.plugins.disco.PluginEntryPoint method), 79 ifaces() (certbot.plugins.disco.PluginsRegistry method), 80 IInstaller (interface in certbot.interfaces), 72 import_csr_file() (in module certbot.crypto_util), 56

init() (certbot.plugins.disco.PluginsRegistry method), 80	MEDIUM_PRIORITY (certbot.reporter.Reporter at-
init_save_csr() (in module certbot.crypto_util), 56	tribute), 86
init_save_key() (in module certbot.crypto_util), 55	menu() (certbot.display.util.FileDisplay method), 60
initialized (certbot.plugins.disco.PluginEntryPoint	menu() (certbot.display.util.NoninteractiveDisplay
attribute), 79	method), 63
inject_parser_options() (certbot.interfaces.IPluginFactory method), 69	menu() (certbot.interfaces.IDisplay method), 73 MisconfigurationError, 68
inject_parser_options() (certbot.plugins.common.Plugin class method), 77	misconfigured (certbot.plugins.disco.PluginEntryPoint attribute), 79
input() (certbot.display.util.FileDisplay method), 60	MissingCommandlineFlag, 68
input() (certbot.display.util.NoninteractiveDisplay	more_info() (certbot.interfaces.IPlugin method), 70
method), 63	must_staple (certbot.interfaces.IConfig attribute), 71
input() (certbot.interfaces.IDisplay method), 74	N
input_with_timeout() (in module certbot.display.util), 59	
install_ssl_options_conf() (in module cert-	names() (certbot.storage.RenewableCert method), 94
bot.plugins.common), 78	NamespaceConfig (class in certbot.configuration), 54
IPlugin (interface in certbot.interfaces), 69 IPluginFactory (interface in certbot.interfaces), 69	new_lineage() (certbot.storage.RenewableCert class method), 95
IReporter (interface in certbot.interfaces), 76	newest_available_version() (cert-
is_staging() (in module certbot.util), 101	bot.storage.RenewableCert method), 93
is_test_cert (certbot.storage.RenewableCert attribute), 92	next_free_version() (certbot.storage.RenewableCert
IValidator (interface in certbot.interfaces), 75	method), 94
K	no_verify_ssl (certbot.interfaces.IConfig attribute), 71
	NoInstallationError, 67
Key (class in certbot.util), 96 key_dir (certbot.interfaces.IConfig attribute), 71	NoninteractiveDisplay (class in certbot.display.util), 62 normalized_tuple() (certbot.plugins.common.Addr
KEY_DIR (in module certbot.constants), 55	method), 78
key_path (certbot.storage.RenewableCert attribute), 92	notAfter() (in module certbot.crypto_util), 58
KeyAuthorizationAnnotatedChallenge (class in cert-	notBefore() (in module certbot.crypto_util), 58
bot.achallenges), 46	notification() (certbot.display.util.FileDisplay method),
	59
L	notification () (certbot. display. util. Noninteractive Display
latest_common_version() (cert-	method), 62
bot.storage.RenewableCert method), 94	notification() (certbot.interfaces.IDisplay method), 73
LexiconClient (class in cert-	NotSupportedError, 68
bot.plugins.dns_common_lexicon), 82	0
lineagename_for_filename() (in module certbot.storage),	
91 LIVE_DIR (in module certbot.constants), 55	obtain_and_enroll_certificate() (certbot.client.Client method), 51
load() (certbot.interfaces.AccountStorage method), 68	obtain_certificate() (certbot.client.Client method), 51
lock_dir_until_exit() (in module certbot.util), 97	obtain_certificate_from_csr() (certbot.client.Client
LockError, 67	method), 51
long_description (certbot.plugins.disco.PluginEntryPoint attribute), 79	ocsp_revoked() (certbot.storage.RenewableCert method), 95
LOW_PRIORITY (certbot.interfaces.IReporter attribute),	ocsp_stapling() (certbot.interfaces.IValidator method), 76
76	OK (in module certbot.display.util), 59
LOW_PRIORITY (certbot.reporter.Reporter attribute),	OLD_SETUPTOOLS_PLUGINS_ENTRY_POINT (in
86	module certbot.constants), 54
M	option_name() (certbot.plugins.common.Plugin method),
	77
make_key() (in module certbot.crypto_util), 57	option_namespace (certbot.plugins.common.Plugin at-
make_or_verify_dir() (in module certbot.util), 98 MEDIUM_PRIORITY (certbot.interfaces.IReporter at-	tribute), 77 option_namespace() (in module cert-
tribute), 76	bot.plugins.common), 77

P	renewal_conf_files() (in module certbot.storage), 89
path_surgery() (in module certbot.plugins.util), 85	RENEWAL_CONFIGS_DIR (in module cert-
pem (certbot.util.Key attribute), 97	bot.constants), 55
perform() (certbot.interfaces.IAuthenticator method), 70	renewal_file_for_certname() (in module certbot.storage), 89
perform_registration() (in module certbot.client), 50	renewal_filename_for_lineagename() (in module cert-
Plugin (class in certbot.plugins.common), 77 PluginEnhancementAlreadyPresent, 67	bot.storage), 91
PluginEntryPoint (class in certbot.plugins.disco), 79	RENEWER_DEFAULTS (in module certbot.constants),
PluginError, 67	55
PluginSelectionError, 67	report_new_account() (in module certbot.account), 45
PluginsRegistry (class in certbot.plugins.disco), 79	Reporter (class in certbot.reporter), 85
pref_challs (certbot.interfaces.IConfig attribute), 71	require() (certbot.plugins.dns_common.CredentialsConfiguration method), 82
PREFIX_FREE_DISTRIBUTIONS (cert-bot.plugins.disco.PluginEntryPoint attribute),	response_and_validation() (cert-
79	bot.achallenges.KeyAuthorizationAnnotatedChallenge
prepare() (certbot.interfaces.IPlugin method), 69	method), 46
prepare() (certbot.plugins.disco.PluginEntryPoint	restart() (certbot.interfaces.IInstaller method), 73
method), 79	revert_temporary_config() (certbot.reverter.Reverter
prepare() (certbot.plugins.disco.PluginsRegistry method),	method), 87
80	Reverter (class in certbot.reverter), 86 ReverterError, 67
prepared (certbot.plugins.disco.PluginEntryPoint attribute), 79	REVOCATION_REASONS (in module cert-
print_messages() (certbot.interfaces.IReporter method),	bot.constants), 54
77	rollback() (in module certbot.client), 53
print_messages() (certbot.reporter.Reporter method), 86	rollback_checkpoints() (certbot.interfaces.IInstaller
problem (certbot.plugins.disco.PluginEntryPoint at-	method), 73
tribute), 79	rollback_checkpoints() (certbot.reverter.Reverter method), 87
pyopenssl_load_certificate() (in module cert-	rsa_key_size (certbot.interfaces.IConfig attribute), 71
bot.crypto_util), 57	run() (certbot.plugins.standalone.ServerManager
Q	method), 84
QUIET_LOGGING_LEVEL (in module cert-	run_script() (in module certbot.util), 97
bot.constants), 54	running() (certbot.plugins.standalone.ServerManager
П	method), 84
R	S
recovery_routine() (certbot.interfaces.IInstaller method),	safe_email() (in module certbot.util), 100
recovery_routine() (certbot.reverter.Reverter method), 89	safe_open() (in module certbot.util), 98
redirect() (certbot.interfaces.IValidator method), 76	safely_remove() (in module certbot.util), 99
redirect_by_default() (in module cert-	sample_user_agent() (in module certbot.client), 50
bot.display.enhancements), 66	save() (certbot.interfaces.AccountStorage method), 68
register() (in module certbot.client), 50	save() (certbot.interfaces.IInstaller method), 72 save_certificate() (certbot.client.Client method), 52
register_file_creation() (certbot.reverter.Reverter method), 88	save_regr() (certbot.account.AccountFileStorage method), 46
register_undo_command() (certbot.reverter.Reverter method), 88	save_successor() (certbot.storage.RenewableCert
$Registration Resource With New Authzr URI\ (class\ in\ cert-$	method), 96 separate_list_input() (in module certbot.display.util), 64
bot.account), 45	server (certbot.interfaces.IConfig attribute), 71
relative_archive_dir() (certbot.storage.RenewableCert	server_path (certbot.configuration.NamespaceConfig at-
method), 92 relevant_values() (in module certbot.storage), 91	tribute), 54
rename_renewal_config() (in module certbot.storage), 90	ServerManager (class in certbot.plugins.standalone), 83
RenewableCert (class in certbot.storage), 91	set_up_core_dir() (in module certbot.util), 97

```
SETUPTOOLS PLUGINS ENTRY POINT (in module
                                                           validated directory() (in module certbot.display.ops), 66
                                                           validated input() (in module certbot.display.ops), 65
          certbot.constants), 54
sha256sum() (in module certbot.crypto util), 58
                                                           verify() (certbot.plugins.disco.PluginEntryPoint method),
should autodeploy()
                         (certbot.storage.RenewableCert
         method), 95
                                                           verify() (certbot.plugins.disco.PluginsRegistry method),
should autorenew()
                         (certbot.storage.RenewableCert
         method), 95
                                                           verify authzr complete()
                                                                                                              (cert-
                                                                     bot.auth handler.AuthHandler
SignalExit, 67
                                                                                                           method),
slug (certbot.account.Account attribute), 45
StandaloneBindError, 68
                                                           verify_cert_matches_priv_key()
                                                                                              (in
                                                                                                    module
                                                                                                               cert-
stop()
              (certbot.plugins.standalone.ServerManager
                                                                     bot.crypto_util), 57
          method), 84
                                                           verify_fullchain() (in module certbot.crypto_util), 57
strict_permissions (certbot.interfaces.IConfig attribute),
                                                           verify renewable cert() (in module certbot.crypto util),
                                                                     57
          72.
SubprocessError, 67
                                                           verify_renewable_cert_sig()
                                                                                           (in
                                                                                                   module
                                                                                                               cert-
success_installation() (in module certbot.display.ops), 65
                                                                     bot.crypto_util), 57
success_renewal() (in module certbot.display.ops), 65
                                                           version() (certbot.storage.RenewableCert method), 93
success revocation() (in module certbot.display.ops), 65
                                                           view config changes()
                                                                                        (certbot.interfaces.IInstaller
supported challenges
                                                                     method), 73
                                                   (cert-
         bot.plugins.standalone.Authenticator attribute),
                                                           view config changes()
                                                                                           (certbot.reverter.Reverter
                                                                     method), 87
supported_enhancements() (certbot.interfaces.IInstaller
                                                           view config changes() (in module certbot.client), 53
          method), 72
                                                           visible() (certbot.plugins.disco.PluginsRegistry method),
SupportedChallengesAction
                                 (class
                                            in
                                                    cert-
                                                                     80
         bot.plugins.standalone), 84
                                                           W
Т
                                                           work dir (certbot.interfaces.IConfig attribute), 71
                                                           write renewal config() (in module certbot.storage), 90
target_expiry (certbot.storage.RenewableCert attribute),
                                                           Υ
temp_checkpoint_dir
                        (certbot.interfaces.IConfig
                                                     at-
         tribute), 71
                                                           yesno() (certbot.display.util.FileDisplay method), 60
TEMP_CHECKPOINT_DIR
                                                                         (certbot.display.util.NoninteractiveDisplay
                                 (in
                                        module
                                                    cert-
                                                           vesno()
          bot.constants), 55
                                                                     method), 63
tls sni 01 address (certbot.interfaces.IConfig attribute),
                                                           yesno() (certbot.interfaces.IDisplay method), 74
tls sni 01 port (certbot.interfaces.IConfig attribute), 71
TLSSNI01 (class in certbot.plugins.common), 78
U
ua flags() (in module certbot.client), 50
unique file() (in module certbot.util), 98
unique lineage name() (in module certbot.util), 99
update_all_links_to()
                         (certbot.storage.RenewableCert
          method), 94
update_configuration() (in module certbot.storage), 90
valid_csr() (in module certbot.crypto_util), 56
valid privkey() (in module certbot.crypto util), 57
validate_file() (in module certbot.plugins.dns_common),
validate_file_permissions()
                               (in
                                       module
                                                    cert-
         bot.plugins.dns common), 82
validate key csr() (in module certbot.client), 53
```