Troubleshooting a network service

Bert Van Vreckem

Abstract

A checklist for troubleshooting a network service running on RHEL/CentOS 7. Basic knowledge of TCP/IP is assumed (addressing, port numbers, main protocols, etc.)

Contents

1	TL;DR Checklist	2
2	General guidelines	2
	2.1 A bottom-up approach	2
3	Link layer	3
4	Network layer	3
	4.1 IP address	3
	4.2 Default gateway	4
	4.3 DNS server	4
	4.4 Check LAN connection	4
5	Transport layer	5
	5.1 Service and port	5
	5.2 Firewall setting	5
6	Application layer	5
	6.1 Log files	6
	6.2 Configuration files	6
	6.3 Availability	6
7	Troubleshooting VirtualBox networking	6
	7.1 Network interfaces	6
	7.2 NAT interface	6
	7.3 Host-only interface	7
	7.2.1. Charaldish.	_

1 TL;DR Checklist

- 1. Link layer
 - · Check the cable/port LEDs
- 2. Network layer
 - ip a
 - ip r (+ ping default gw)
 - cat /etc/resolv.conf (+ dig www.google.com @a.b.c.d +short)
- 3. Transport layer
 - sudo systemctl status SERVICE.service
 - sudo systemctl start SERVICE.service
 - sudo systemctl enable SERVICE.service
 - sudo firewall-cmd —list-all
 - sudo firewall-cmd -add-service=SERVICE -permanent
 - sudo firewall-cmd -add-port=PORT/tcp -permanent
 - sudo systemctl restart firewalld
- 4. Application layer
 - sudo journalctl -f -u SERVICE.service
 - sudo systemctl restart SERVICE.service (after each config file change)

2 General guidelines

A few best practices when setting up and troubleshooting network services

- Automate your tests or at least use a checklist (Shell script, Ansible playbook, Serverspec, etc.)
- Keep your checklist **up-to-date** as you learn new things
- Be thorough, don't skip steps (e.g checking the cables)
- Error messages usually give a clue of where to look. Google them.
- Work in **small steps** and verify every step.
- Don't assume. Test.
- Keep a **backup** copy of the original configuration, and the latest working version.
- Always validate the syntax of config files before applying them
- Know what logs to look at
- Open a separate terminal that shows the logs in realtime (journalctl -f)

2.1 A bottom-up approach

In this troubleshooting guide, we propose a **bottom-up** approach following the layers of the TCP/IP protocol stack:

- 1. Link layer: cables, network ports, etc.
- 2. Internet layer: ip address configuration, routing and DNS
- 3. Transport layer: service, network ports, firewall settings
- 4. Application layer: configuration, etc.

It is important to follow the same procedure systematically. When you skip steps, or start to troubleshoot too high up in the stack, you may miss the cause of the fault.

3 Link layer

In this phase, we check the network hardware, specifically network cables and ports.

- · Is the power on?
- · Is the network cable plugged in?
 - In VirtualBox, go to the VM settings, Network, select the active interfaces, click "Advanced" and make sure the checkbox "Cable connected" is checked.
- Are the Ethernet port LEDs on, both on the machine and on the switch?
 - If not, test the cable
 - Some switches have a different color for e.g. FastEthernet (100Mbps) and Gigabit Ethernet. Check whether you see the expected color.
- Use the command ip link
 - UP: ok, the interface is connected
 - NO-CARRIER: no signal on this interface

4 Network layer

The network layer is responsible for being able to communicate with other hosts on the network. In order to be able to communicate, each host should have three settings configured correctly:

- 1. The network interface should have an IP address assigned
- 2. A default gateway should be set
- 3. A **DNS server** should be set

Before "reaching out" to other hosts, first check local settings.

4.1 IP address

The IP address may have been set automatically (DHCP), or manually. Check this in /etc/sysconfig/network-scripts/ifcfg-IFACE, with IFACE the name of the network interface.

Use the command ip address (or shortcut ip a) to list the IP addresses for each interface.

You should know the expected value, if not the exact IP, at least the network range or network IP and network mask.

- Many home routers have an IP range of 192.168.0.0/24, 192.168.1.0/24
- On a VirtualBox NAT interface, the IP address of the VM should be 10.0.2.15/8
- On a VirtualBox host-only interface, the IP address of the VM depends on how you configured this network. The default host only network has IP range 192.168.56.0/24, with a DHCP server handing out addresses starting at 192.168.56.101.

Possible problems and causes (automatic IP assignment with DHCP):

- No IP
 - The DHCP server is unreachable
 - The DHCP server won't give an IP to this host
- IP looking like 169.254.x.x
 - No DHCP server could be reached, and a "link-local" address was assigned

- IP not in the expected range
 - You may have accidentally set a fixed IP previously, and forgot to set it to DHCP again...

Possible problems and causes (manual IP setting):

- IP not in the expected range
 - Mistake in IP address assignment, check the configuration file
- · Correct IP, but "network unreachable"
 - Check the network mask, this should be identical for all hosts on the LAN

4.2 Default gateway

Usually, a host is connected to a LAN through a switch. Network traffic to the outside world goes through a router, connected to the same LAN. Every host on the LAN should know this router, the "default gateway".

Use the command ip route (or shortcut ip r). There should be a line starting with default via x.y.z.w.

Possible problems and causes (automatic IP assignment with DHCP):

- · No default gateway set
 - there is most probably also a problem with the IP address of this host, fix this first
 - If you manage the DHCP server, maybe it's configured badly?
- · Unexpected default gateway address
 - You may have accidentally set the default gateway manually previously and forgot to set it to DHCP again
 - If you manage the DHCP server, maybe it's configured badly?

4.3 DNS server

In order to be able to resolve host names to IP addresses, every host should be able to contact a DNS server. View the file /etc/resolv.conf. It usually has a header that mentions it was generated automatically, and should have one or more lines starting with nameserver.

Generated by NetworkManager

Possible problems and causes are equivalent to those with the default gateway setting.

4.4 Check LAN connection

If the previous settings are correct, you can check whether other hosts on the LAN can be reached.

- Ping the default gateway: ping a.b.c.d
- Ping another known host on the LAN
- Check DNS name resolution: dig www.google.com @e.f.g.h +short

Be aware that ping (and other network troubleshooting tools like the traceroute family) may not always work. Some system administrators will block ICMP traffic on routers, rendering the results useless. A command like ping www.google.com (for some the first command they try in case of network connection problems) is not very suitable, in that it depends on too many things to work at once:

- · the host's network settings should be correct
- · routing should work
- · DNS should be available
- no router between this host and the target should block ICMP
- ..

5 Transport layer

In the transport layer, we'll check whether the network service is actually running, what port it uses, and whether the firewall allows traffic on that port. An example for httpd is given, but this can be applied to other services.

5.1 Service and port

- Is the service running? sudo systemctl status httpd.service
 - Expected output: active (running)
 - If the output contains: inactive (dead), start the service, and if necessary, make sure it starts automatically on boot

```
sudo systemctl start httpd.service
sudo systemctl enable httpd.service
```

- What port is the service using? sudo ss -tlnp (list TCP (-t) server (-l) port numbers (-n) with the process behind them (-p). The -p option requires root, hence the sudo)
 - The expected output depends on the service and on how you configured it. The httpd service usually listens on port 80 (HTTP) or 443 (HTTPS), but the port number may have been set to a non-standard. Check /etc/services for standard port numbers for well-known network services.

5.2 Firewall setting

Does the firewall allow traffic on the service? sudo firewall-cmd —list-all.

```
$ sudo firewall-cmd --list-all
[sudo] password for USER:
public (default, active)
  interfaces: enp0s3 enp0s8
  sources:
  services: dhcpv6-client mdns samba-client ssh http https
  ports:
  masquerade: no
  forward-ports:
  icmp-blocks:
  rich rules:
```

Check the output for the following items:

- The network interface that the service listens on is listed
- · The service name is listed.
 - The value should be one listed by firewall-cmd —get-services.
 - Remark that the service name for firewalld is not necessarily equal to the service name for systemd. E.g. BIND is called named.service by systemd, while it is referred to as dns by firewalld.
- If the service name is not present, the port numbers used by the service should be listed (e.g. when using a non-standard port, or a service not known by firewalld)

6 Application layer

On this phase, we check whether the application is configured correctly, and whether it is available to clients and responds correctly to requests.

6.1 Log files

Check the log, either using journalctl, or by looking at the log file in /var/log. The former is standard, the latter may be needed for services that keep a log file not managed/recognized by systemd.

Open a separate terminal with the relevant logs opened and watching for changes (-f option): - sudo journalctl -f -u httpd.service - sudo tail -f /var/log/httpd/error_log

6.2 Configuration files

Check the configuration file, somewhere in /etc/, e.g. /etc/httpd/httpd.conf. First, create a backup of the current configuration file(s), and if possible the default one (as created when installing the service)

- Check the configuration file for errors (depends on the service, read the man-page or documentation)
- · Validate the syntax of the configuration file. Most services have a command that does this.
 - e.g. for httpd: apachectl configtest
- · After making changes, restart the service
 - sudo systemctl restart httpd.service

6.3 Availability

You can start checking availability on the loopback interface, but it is important to repeat this from another host. The loopback interface is not firewalled, while physical network interfaces are.

- Do a port scan from another host on the lan, e.g.
 - sudo nmap -sS -p 80,443 HOST (perform a TCP SYN scan on port 80 and 443)
- Use a test tool or client software to check availability of the service, e.g.
 - wget http://HOST/, wget https://HOST/
 - curl http://HOST/, curl https://HOST/

7 Troubleshooting VirtualBox networking

7.1 Network interfaces

In a VirtualBox VM with EL7, the network interfaces are usually named as follows:

- Adapter 1: enp0s3
- Adapter 2: enp0s8
- Adapter 3: enp0s9
- Adapter 4: enp0s10

7.2 NAT interface

The VirtualBox NAT adapter is the default way of allowing your VM to access the Internet. However, it is normally not possible to access your VM from the host system over the network.

The network settings of your VM are predictable. Any VM with a NAT interface has:

• IP Address: 10.0.2.15/24

• Default gateway: 10.0.2.2

• Name server: 10.0.2.3 (potentially supplemented with the name servers assigned to your host system)

You can ping the gateway and name server from the VM, but pinging 10.0.2.15 from your host system will never work. Generally, if your host system has Internet, your VM also should have Internet. One possible exception is when you switch your host system from a wired to wireless connection, or vice versa, while your VM is running.

7.3 Host-only interface

The VirtualBox host-only adapter allows you to access a VM over the network. A virtual Ethernet interface is created that is also visible on your host system. You can create multiple host-only adapters and configure network settings from the main window by opening File > Preferences > Network > Host-only Networks.

A host-only interface is named:

• On Linux: vboxnet0, vboxnet1, ...

• On Windows: "VirtualBox Host-only Ethernet Interface". "VirtualBox Host-only Ethernet Interface #2", ...

The **default settings** for a host-only interface are:

Adapter

- IPv4 Address: 192.168.56.1 (= the IP-address assigned to your host system)

- IPv4 Network Mask: 255.255.255.0

· DHCP-server: enabled

- server address: 192.168.56.100 (= the IP address of a virtual DHCP server)

Server Mask: 255.255.255.0Lower bound: 192.168.56.101Upper bound: 192.168.56.254

If a VM is configured to get an IP address automatically (i.e. via DHCP), it will probably get 192.168.56.101 (if it's the first VM on this host-only network). If you want to assign static IP addresses to VMs on this network, take one from the range 2-99.

I suggest to leave the default host-only interface as is, and create new interfaces as needed. It may be needed to shut down all VMs and restart VirtualBox for configuration changes to come into effect, especially after creating a new interface.

7.3.1 Checklist:

- 1. Check host-only network configuration: VirtualBox main window > File > Preferences > Network > Host-only Networks
 - Does the host system have an IP address in the form 192.168.NNN.1?
 - Is the DHCP server activated and configured consistently with the IP address of the host system?
- 2. Check whether the host system actually has the expected IP address
- 3. Check the VM network adapters (VM Settings > Network)
 - Is the adapter enabled?
 - Is the cable connected (hidden setting under "advanced")
 - Is it attached to the correct host-only network?
- 4. In the VM, check the IP address of the adapter connected to the host-only network
 - Is it e.g. 192.168.56.101 (default host-only network, first IP address assigned by DHCP)
 - Is it e.g. 192.168.56.NN (with 2 \leq NN \leq 99, if you assigned a fixed IP address)
- 5. On your VM, ping the IP of the host system (192.168.56.1) and vice versa.