

QGIS Server 3.22 User Guide

QGIS Project

CONTENTS

1	Intro	duction	1
2	Getti	ng Starte	ed 3
	2.1	Installat	ion on Debian-based systems
		2.1.1	Apache HTTP Server
		2.1.2	NGINX HTTP Server
		2.1.3	Xvfb
	2.2		ion on Windows
	2.3		project
	2.4		re your project
		2.4.1	WMS capabilities
		2.4.2	WFS capabilities
		2.4.3	WCS capabilities
		2.4.4	Fine tuning your OWS
	2.5		ion with third parties
	2.3	2.5.1	1
		2.5.1	
		2.5.2	
		2.3.3	Integration with QWC2
3	Servi	ces	19
	3.1	Basics .	
		3.1.1	SERVICE
		3.1.2	REQUEST
		3.1.3	MAP
		3.1.4	FILE_NAME
		3.1.5	Short name
	3.2		ap Service (WMS)
	3.2	3.2.1	GetCapabilities
		3.2.2	GetMap
		3.2.3	GetFeatureInfo
		3.2.3	GetLegendGraphics
		3.2.4	
			GetStyle(s)
		3.2.6	DescribeLayer
		3.2.8	GetProjectSettings
		3.2.9	GetSchemaExtension
		3.2.10	External WMS layers
		3.2.11	Redlining
	3.3		ature Service (WFS)
		3.3.1	GetCapabilities
		3.3.2	GetFeature
		3.3.3	DescribeFeatureType
		3.3.4	Transaction
	3.4	Web Co	verage Service (WCS)

		3.4.1 GetCapabilities			 	 		 	 		 63
		3.4.2 DescribeCoverage .			 	 		 	 		 64
		3.4.3 GetCoverage			 	 		 	 		 66
	3.5	Web Map Tile Service (WMT	S)		 	 		 	 		 67
		3.5.1 GetCapabilities			 	 		 	 		 67
		3.5.2 GetTile			 	 		 	 		 68
		3.5.3 GetFeatureInfo									69
	3.6	OGC API Features			 	 		 	 		 70
		3.6.1 Resource representat									71
		3.6.2 Endpoints									71
		3.6.3 Pagination									75
		3.6.4 Feature filtering									75
		3.6.5 Feature sorting									76
		3.6.6 Attribute selection .									76
		3.6.7 Customize the HTM									77
		5.0.7 Custoffize the IIIIvi	z pages .		 	 	• • •	 	 	• •	 , ,
4	Catal	log									79
5	Plugi										83
	5.1	List of plugins									83
	5.2	Location of plugins			 	 		 	 		 83
	5.3	Installation									83
		5.3.1 Manually with a ZIP									83
		5.3.2 With a command line									84
	5.4	HTTP Server configuration .									84
		5.4.1 Apache			 	 		 	 		 84
	5.5	How to use a plugin			 	 		 	 		 85
6	A dwo	nood configuration									87
6		nced configuration									
	6.1	Logging									87
	6.2	Environment variables									87
	6.3	Settings summary									89
	6.4	Connection to service file									90
	6.5	Add fonts to your linux server		• • •	 	 		 	 		 90
7	Devel	lopment Server									91
		· ·									
8		ainerized deployment									93
	8.1	Simple docker images			 	 		 	 		 93
		8.1.1 First run			 	 		 	 		 94
		8.1.2 Usable sample			 	 		 	 		 95
		8.1.3 Cleanup			 	 		 	 		 96
	8.2	Docker stacks			 	 		 	 		 96
		8.2.1 Swarm/docker-comp	ose		 	 		 	 		 96
		8.2.2 Kubernetes			 	 		 	 		 97
	8.3	Cloud deployment			 	 		 	 		 100
		8.3.1 AWS usecase			 	 		 	 		 101
9	Frequ	uently Asked Question									103

CHAPTER

ONE

INTRODUCTION

QGIS Server is an open source WMS, WFS, OGC API for Features 1.0 (WFS3) and WCS implementation that, in addition, implements advanced cartographic features for thematic mapping. QGIS Server is a FastCGI/CGI (Common Gateway Interface) application written in C++ that works together with a web server (e.g., Apache, Nginx). It has Python plugin support allowing for fast and efficient development and deployment of new features.

QGIS Server uses QGIS as back end for the GIS logic and for map rendering. Furthermore, the Qt library is used for graphics and for platform-independent C++ programming. In contrast to other WMS software, the QGIS Server uses cartographic rules as a configuration language, both for the server configuration and for the user-defined cartographic rules.

As QGIS desktop and QGIS Server use the same visualization libraries, the maps that are published on the web look the same as in desktop GIS.

In the following sections, we will provide a sample configuration to set up a QGIS Server on Linux (Debian, Ubuntu and derivatives) and on Windows. For more information about server plugin development, please read server_plugins.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts.

A copy of the license is included in the section gnu_fdl.

CHAPTER

TWO

GETTING STARTED

2.1 Installation on Debian-based systems

We will give a short and simple installation how-to for a minimal working configuration on Debian based systems (including Ubuntu and derivatives). However, many other distributions and OSs provide packages for QGIS Server.

Note: In Ubuntu you can use your regular user, prepending sudo to commands requiring admin permissions. In Debian you can work as admin (root), without using sudo.

Requirements and steps to add official QGIS repositories to install QGIS Server on a Debian based system are provided in QGIS installers page. You may want to install at least the latest Long Term Release.

Once the target version repository is configured and QGIS Server installed, you can test the installation with:

```
/usr/lib/cgi-bin/qgis_mapserv.fcgi
```

If you get the following output, the server is correctly installed.

Note: Depending on the version of QGIS, you might see slightly different output reported when you run $qgis_mapserv.fcgi$.

Note: As seen below, QGIS reports a Status 400 code, which correctly identifies the request has failed because there is no active http session. This is not a bug and indicates the server is functioning properly.

```
Application path not initialized
Application path not initialized
Warning 1: Unable to find driver ECW to unload from GDAL_SKIP environment variable.
```

(continues on next page)

(continued from previous page)

```
Warning 1: Unable to find driver ECW to unload from GDAL_SKIP environment variable.
Warning 1: Unable to find driver JP2ECW to unload from GDAL_SKIP environment_
"Loading native module /usr/lib/qgis/server/libdummy.so"
"Loading native module /usr/lib/qgis/server/liblandingpage.so"
"Loading native module /usr/lib/qgis/server/libwcs.so"
"Loading native module /usr/lib/qgis/server/libwfs.so"
"Loading native module /usr/lib/qgis/server/libwfs3.so"
"Loading native module /usr/lib/qgis/server/libwms.so"
"Loading native module /usr/lib/qgis/server/libwmts.so"
QFSFileEngine::open: No file name specified
Content-Length: 102
Content-Type: application/json
Server: QGIS FCGI server - QGIS version 3.22.6-Białowieża
        400
[{"code": "Bad request error", "description": "Requested URI does not match any_
→registered API handler"}]
```

Let's add a sample project. You can use your own, or one from Training demo data:

```
mkdir /home/qgis/projects/
cd /home/qgis/projects/
wget https://github.com/qgis/QGIS-Training-Data/archive/release_3.22.zip
unzip release_3.22.zip
mv QGIS-Training-Data-release_3.22/exercise_data/qgis-server-tutorial-data/world.

qgs .
mv QGIS-Training-Data-release_3.22/exercise_data/qgis-server-tutorial-data/

naturalearth.sqlite .
```

Of course, you can use your favorite GIS software to open this file and take a look at the configuration and available layers.

To properly deploy QGIS server you need a HTTP server. Recommended choices are Apache or NGINX.

2.1.1 Apache HTTP Server

Note: In the following, please replace qgis.demo with the name or IP address of your server.

1. Install Apache and mod_fcgid:

```
apt install apache2 libapache2-mod-fcgid
```

- 2. You can run QGIS Server on your default website, but let's configure a virtualhost specifically for this, as follows.
 - 1. In the /etc/apache2/sites-available directory, create a file called qgis.demo.conf, with this content:

```
<VirtualHost *:80>
    ServerAdmin webmaster@localhost
    ServerName qgis.demo

DocumentRoot /var/www/html

# Apache logs (different than QGIS Server log)
    ErrorLog ${APACHE_LOG_DIR}/qgis.demo.error.log
    CustomLog ${APACHE_LOG_DIR}/qgis.demo.access.log combined

(continues on next page)
```

(continues on next page)

(continued from previous page)

```
# Longer timeout for WPS... default = 40
 FcgidIOTimeout 120
 FcgidInitialEnv LC_ALL "en_US.UTF-8"
 FcgidInitialEnv PYTHONIOENCODING UTF-8
 FcgidInitialEnv LANG "en_US.UTF-8"
 # QGIS log
 FcgidInitialEnv QGIS_SERVER_LOG_STDERR 1
 FcgidInitialEnv QGIS_SERVER_LOG_LEVEL 0
 # default QGIS project
 SetEnv QGIS_PROJECT_FILE /home/qgis/projects/world.qgs
 # QGIS_AUTH_DB_DIR_PATH must lead to a directory writeable by the Server
→'s FCGI process user
 FcgidInitialEnv QGIS_AUTH_DB_DIR_PATH "/home/qgis/qgisserverdb/"
 FcgidInitialEnv QGIS_AUTH_PASSWORD_FILE "/home/qgis/qgisserverdb/qgis-
→auth.db"
 # Set pg access via pg_service file
 SetEnv PGSERVICEFILE /home/qgis/.pg_service.conf
 FcgidInitialEnv PGPASSFILE "/home/qgis/.pgpass"
 # if qgis-server is installed from packages in debian based distros this.
→is usually /usr/lib/cgi-bin/
 # run "locate qgis_mapserv.fcgi" if you don't know where qgis_mapserv.
⊶fcgi is
 ScriptAlias /cgi-bin/ /usr/lib/cgi-bin/
 <Directory "/usr/lib/cgi-bin/">
   AllowOverride None
   Options +ExecCGI -MultiViews -SymLinksIfOwnerMatch
   Require all granted
 </Directory>
 <IfModule mod_fcgid.c>
 FcgidMaxRequestLen 26214400
 FcgidConnectTimeout 60
 </IfModule>
</VirtualHost>
```

Note: Some of the above configuration options are explained in the Server *environment variables* and pg_service file sections.

2. Let's now create the directories that will store the QGIS Server logs and the authentication database:

```
mkdir -p /var/log/qgis/
chown www-data:www-data /var/log/qgis
mkdir -p /home/qgis/qgisserverdb
chown www-data:www-data /home/qgis/qgisserverdb
```

Note: www-data is the Apache user on Debian based systems and we need Apache to have access to those locations or files. The chown www-data... commands change the owner of the respective directories and files to www-data.

3. We can now enable the virtual host and the fcgid mod if it's not already done:

```
a2enmod fcgid
a2ensite qgis.demo
```

4. Now restart Apache for the new configuration to be taken into account:

```
systemctl restart apache2
```

5. Now that Apache knows that he should answer requests to http://qgis.demo we also need to setup the client system so that it knows who qgis.demo is. We do that by adding 127.0.0.1 qgis.demo in the hosts file.

```
# Replace 127.0.0.1 with the IP of your server.
sh -c "echo '127.0.0.1 qgis.demo' >> /etc/hosts"``.
```

Important: Remember that both the qgis.demo.conf and /etc/hosts files should be configured for your setup to work. You can also test the access to your QGIS Server from other clients on the network (e.g. Windows or macos machines) by going to their /etc/hosts file and point the qgis.demo name to whatever IP the server machine has on the network (not 127.0.0.1 as it is the local IP, only accessible from the local machine). On *nix machines the hosts file is located in /etc, while on Windows it's under the C:\Windows\System32\drivers\etc directory. Under Windows you need to start your text editor with administrator privileges before opening the hosts file.

QGIS Server is now available at http://qgis.demo. To check, type in a browser, as in the simple case:

```
http://qgis.demo/cgi-bin/qgis_mapserv.fcgi?SERVICE=WMS&VERSION=1.3.0&
→REQUEST=GetCapabilities
```

2.1.2 NGINX HTTP Server

Note: In the following, please replace qgis.demo with the name or IP address of your server.

You can also use QGIS Server with NGINX. Unlike Apache, NGINX does not automatically spawn FastCGI processes. The FastCGI processes are to be started by something else.

Install NGINX:

```
apt install nginx
```

- As a first option, you can use **spawn-fcgi** or **fcgiwrap** to start and manage the QGIS Server processes. Official Debian packages exist for both. When you have no X server running and you need, for example, printing, you can use *xvfb*.
- Another option is to rely on Systemd, the init system for GNU/Linux that most Linux distributions use today.
 One of the advantages of this method is that it requires no other components or processes. It's meant to be simple, yet robust and efficient for production deployments.

NGINX Configuration

The **include fastcgi_params**; used in the previous configuration is important, as it adds the parameters from /etc/nginx/fastcgi_params:

```
fastcgi_param QUERY_STRING
                                $query_string;
fastcgi_param REQUEST_METHOD
                                $request_method;
fastcgi_param CONTENT_TYPE
                                $content_type;
fastcgi_param CONTENT_LENGTH
                                $content_length;
fastcgi_param SCRIPT_NAME
                                $fastcgi_script_name;
fastcgi_param REQUEST_URI
                                $request_uri;
fastcgi_param DOCUMENT_URI
                                $document_uri;
fastcgi_param DOCUMENT_ROOT
                                $document_root;
fastcgi_param SERVER_PROTOCOL
                                $server_protocol;
fastcgi_param REQUEST_SCHEME
                                $scheme;
                                $https if_not_empty;
fastcgi_param HTTPS
fastcgi_param GATEWAY_INTERFACE CGI/1.1;
fastcgi_param SERVER_SOFTWARE
                                nginx/$nginx_version;
fastcgi_param REMOTE_ADDR
                               $remote_addr;
fastcgi_param REMOTE_PORT
                               $remote_port;
fastcgi_param SERVER_ADDR
                               $server_addr;
fastcgi_param SERVER_PORT
                                $server_port;
fastcgi_param SERVER_NAME
                               $server_name;
# PHP only, required if PHP was built with --enable-force-cgi-redirect
fastcgi_param REDIRECT_STATUS
                                200;
```

Moreover, you can use some *Environment variables* to configure QGIS Server. In the NGINX configuration file, /etc/nginx/nginx.conf, you have to use fastcgi_param instruction to define these variables as shown below:

```
location /qgisserver {
    gzip         off;
    include         fastcgi_params;
    fastcgi_param    QGIS_SERVER_LOG_STDERR   1;
    fastcgi_param    QGIS_SERVER_LOG_LEVEL   0;
    fastcgi_pass         unix:/var/run/qgisserver.socket;
}
```

FastCGI wrappers

Warning: fcgiwrap is easier to set up than spawn-fcgi, because it's already wrapped in a Systemd service. But it also leads to a solution that is much slower than using spawn-fcgi. With fcgiwrap, a new QGIS Server process is created on each request, meaning that the QGIS Server initialization process, which includes reading and parsing the QGIS project file, is done on each request. With spawn-fcgi, the QGIS Server process remains alive between requests, resulting in much better performance. For that reason, spawn-fcgi is recommended for production use.

spawn-fcgi

If you want to use spawn-fcgi:

1. The first step is to install the package:

```
apt install spawn-fcgi
```

2. Then, introduce the following block in your NGINX server configuration:

```
location /qgisserver {
    gzip          off;
    include          fastcgi_params;
    fastcgi_pass          unix:/var/run/qgisserver.socket;
}
```

3. And restart NGINX to take into account the new configuration:

```
systemctl restart nginx
```

4. Finally, considering that there is no default service file for spawn-fcgi, you have to manually start QGIS Server in your terminal:

QGIS Server is now available at http://qgis.demo/qgisserver.

Note: When using spawn-fcgi, you may directly define environment variables before running the server. For example: export QGIS_SERVER_LOG_STDERR=1

Of course, you can add an init script to start QGIS Server at boot time or whenever you want. For example with **systemd**:

1. Edit the file /etc/systemd/system/qgis-server.service with this content:

```
[Unit]
Description=QGIS server
After=network.target
[Service]
;; set env var as needed
;Environment="LANG=en_EN.UTF-8"
; Environment="QGIS_SERVER_PARALLEL_RENDERING=1"
; Environment="QGIS_SERVER_MAX_THREADS=12"
; Environment="QGIS_SERVER_LOG_LEVEL=0"
; Environment="QGIS_SERVER_LOG_STDERR=1"
;; or use a file:
; EnvironmentFile=/etc/qqis-server/env
ExecStart=spawn-fcgi -s /var/run/qgisserver.socket -U www-data -G www-data -n /
→usr/lib/cgi-bin/qgis_mapserv.fcgi
[Install]
WantedBy=multi-user.target
```

2. Then enable and start the service:

```
systemctl enable --now qgis-server
```

Warning: With the above commands spawn-fcgi spawns only one QGIS Server process.

fcgiwrap

Using fcgiwrap is much easier to setup than **spawn-fcgi** but it's much slower.

1. You first have to install the corresponding package:

```
apt install fcgiwrap
```

2. Then, introduce the following block in your NGINX server configuration:

3. Finally, restart NGINX and **fcgiwrap** to take into account the new configuration:

```
systemctl restart nginx
systemctl restart fcgiwrap
```

QGIS Server is now available at http://qgis.demo/qgisserver.

Systemd

QGIS Server needs a running X Server to be fully usable, in particular for printing. In the case you already have a running X Server, you can use systemd services.

This method, to deploy QGIS Server, relies on two Systemd units to configure: a Socket unit and a Service unit.

1. The QGIS Server Socket unit defines and creates a file system socket, used by NGINX to start and communicate with QGIS Server. The Socket unit has to be configured with Accept=false, meaning that the calls to the accept() system call are delegated to the process created by the Service unit. It is located in /etc/systemd/system/qgis-server@.socket, which is actually a template:

```
[Unit]
Description=QGIS Server Listen Socket (instance %i)

[Socket]
Accept=false
ListenStream=/var/run/qgis-server-%i.sock
SocketUser=www-data
SocketGroup=www-data
SocketMode=0600

[Install]
WantedBy=sockets.target
```

2. Now enable and start sockets:

```
for i in 1 2 3 4; do systemctl enable --now qgis-server@$i.socket; done
```

3. The QGIS Server Service unit defines and starts the QGIS Server process. The important part is that the Service process' standard input is connected to the socket defined by the Socket unit. This has to be configured using StandardInput=socket in the Service unit configuration located in /etc/systemd/system/ qgis-server@.service:

```
[Unit]
Description=QGIS Server Service (instance %i)
```

(continues on next page)

(continued from previous page)

```
[Service]
User=www-data
Group=www-data
StandardOutput=null
StandardError=journal
StandardInput=socket
ExecStart=/usr/lib/cgi-bin/qgis_mapserv.fcgi
EnvironmentFile=/etc/qgis-server/env

[Install]
WantedBy=multi-user.target
```

Note: The QGIS Server *environment variables* are defined in a separate file, /etc/qgis-server/env. It could look like this:

```
QGIS_PROJECT_FILE=/etc/qgis/myproject.qgs
QGIS_SERVER_LOG_STDERR=1
QGIS_SERVER_LOG_LEVEL=3
```

4. Now start socket service:

```
for i in 1 2 3 4; do systemctl enable --now qgis-server@$i.service; done
```

5. Finally, for the NGINX HTTP server, let's introduce the configuration for this setup:

```
upstream qgis-server_backend {
    server unix:/var/run/qgis-server-1.sock;
    server unix:/var/run/qgis-server-2.sock;
    server unix:/var/run/qgis-server-3.sock;
    server unix:/var/run/qgis-server-4.sock;
}

server {
    unix:/var/run/qgis-server-4.sock;
    include fastcgi_params;
    fastcgi_pass qgis-server_backend;
    }
}
```

6. Now restart NGINX for the new configuration to be taken into account:

```
systemctl restart nginx
```

Thanks to Oslandia for sharing their tutorial.

2.1.3 Xvfb

QGIS Server needs a running X Server to be fully usable, in particular for printing. On servers it is usually recommended not to install it, so you may use xvfb to have a virtual X environment.

If you're running the Server in graphic/X11 environment then there is no need to install xvfb. More info at https://www.itopen.it/qgis-server-setup-notes/.

1. To install the package:

```
apt install xvfb
```

2. Create the service file, /etc/systemd/system/xvfb.service, with this content:

```
[Unit]
Description=X Virtual Frame Buffer Service
After=network.target

[Service]
ExecStart=/usr/bin/Xvfb :99 -screen 0 1024x768x24 -ac +extension GLX +render -
→noreset

[Install]
WantedBy=multi-user.target
```

3. Enable, start and check the status of the xvfb.service:

```
systemctl enable --now xvfb.service systemctl status xvfb.service
```

- 4. Then, according to your HTTP server, you should configure the DISPLAY parameter or directly use xvfb-run.
 - Using Apache:
 - 1. Add to your Fcgid configuration (see Apache HTTP Server):

```
FcgidInitialEnv DISPLAY ":99"
```

2. Restart Apache for the new configuration to be taken into account:

```
systemctl restart apache2
```

- Using NGINX
 - With spawn-fcgi using xvfb-run:

- With the **DISPLAY** environment variable in the HTTP server configuration.


```
fastcgi_param DISPLAY ":99";
```

2.2 Installation on Windows

QGIS Server can also be installed on Windows systems using the 64 bit version of the OSGeo4W network installer (https://qgis.org/en/site/forusers/download.html).

A simple procedure is the following:

- 1. Download and run the OSGeo4W installer
- 2. Follow the "Advanced Install" and install the QGIS Desktop, QGIS Server apache and mod_fcgid packages.



- 3. Apache is not directly installed as a service on Windows. You need to:
 - 1. Right-click the OSGeo4W.bat file at the root of the C: $\OSGeo4W64\$ folder (if the default installation paths have been used) and select *Run as administrator*
 - 2. In the console, run apache-install.bat, which will output

```
> apache-install.bat
Installing the 'Apache OSGeo4W Web Server' service
The 'Apache OSGeo4W Web Server' service is successfully installed.
Testing httpd.conf....
Errors reported here must be corrected before the service can be started.
...
```

The service is started as you can notice in the report. But the server may fail to run due to missing custom configuration.

4. Edit the C:\OSGeo4w64\apps\apache\conf\httpd.conf file with the following changes (various other combinations are possible):

Purpose	Existing config	Replacement
(Optional) Customize the address to listen to using an IP and/or port, You can and add as many entries as you wish.	Listen \${SRVPORT}	Listen localhost:8080
Indicate where to find the script files	ScriptAlias /cgi-bin/ "\$ →{SRVROOT}/cgi-bin/"	ScriptAlias /cgi-bin/ →"C:/OSGeo4W64/apps/ →qgis/bin/"
Provide permissions on the script folder	<pre><directory "\${srvroot}="" <="" th=""><th><pre><directory "c:="" <="" th=""></directory></pre></th></directory></pre>	<pre><directory "c:="" <="" th=""></directory></pre>
Enable file extensions to use for script files. Uncomment and complete	#AddHandler cgi-script . ⇔cgi	AddHandler cgi-script . →cgi .exe
Add more OSGeo4W custom configuration variables	<pre># parse OSGeo4W apache_</pre>	# parse OSGeo4W apache. → conf files IncludeOptional "C:/ → OSGeo4W64/httpd.d/ → httpd_*.conf" SetEnv GDAL_DATA "C:/ → OSGeo4W64/share/gdal" SetEnv QGIS_AUTH_DB_DIR_ → PATH "C:/OSGeo4W64/ → apps/qgis/resources"

5. Restart the Apache web server

```
> apache-restart.bat
```

6. Open browser window to testing a GetCapabilities request to QGIS Server. Replace localhost: 8080 with the IP and port you set to listen.

```
\label{local-bin-qgis_mapserv.fcgi.exe} $$ $$ http://localhost:8080/cgi-bin/qgis_mapserv.fcgi.exe?SERVICE=WMS&VERSION=1.3.0& \\ $\hookrightarrow $$ REQUEST=GetCapabilities $$
```

A XML file with the capabilities should be returned. Your server is ready to use.

2.3 Serve a project

Now that QGIS Server is installed and running, we just have to use it.

Obviously, we need a QGIS project to work on. Of course, you can fully customize your project by defining contact information, precise some restrictions on CRS or even exclude some layers. Everything you need to know about that is described later in *Configure your project*.

But for now, we are going to use a simple project already configured and previously downloaded in /home/qgis/projects/world.ggs, as described above.

By opening the project and taking a quick look on layers, we know that 4 layers are currently available:

- airports
- · places
- · countries
- countries_shapeburst

You don't have to understand the full request for now but you may retrieve a map with some of the previous layers thanks to QGIS Server by doing something like this in your web browser to retrieve the *countries* layer:

```
http://qgis.demo/qgisserver?

MAP=/home/qgis/projects/world.qgs&
LAYERS=countries&
SERVICE=WMS&
VERSION=1.3.0&
REQUEST=GetMap&
CRS=EPSG:4326&
WIDTH=400&
HEIGHT=200&
BBOX=-90,-180,90,180
```

If you obtain the next image, then QGIS Server is running correctly:




Fig. 2.1: Server response to a basic GetMap request

Note that you may define **QGIS_PROJECT_FILE** environment variable to use a project by default instead of giving a **MAP** parameter (see *Environment variables*).

For example with spawn-fcgi:

```
export QGIS_PROJECT_FILE=/home/qgis/projects/world.qgs
spawn-fcgi -f /usr/lib/bin/cgi-bin/qgis_mapserv.fcgi \
-s /var/run/qgisserver.socket \
-U www-data -G www-data -n
```

2.4 Configure your project

To provide a new QGIS Server WMS, WFS or WCS, you have to create a QGIS project file with some data or use one of your current project. Define the colors and styles of the layers in QGIS and the project CRS, if not already defined.




Fig. 2.2: Definitions for a QGIS Server WMS/WFS/WCS project

Then, go to the *QGIS Server* menu of the *Project* > *Properties...* dialog and provide some information about the OWS in the fields under *Service Capabilities*. This will appear in the GetCapabilities response of the WMS, WFS or WCS. If you don't check Service capabilities, QGIS Server will use the information given in the wms_metadata.xml

file located in the cgi-bin folder.

2.4.1 WMS capabilities

In the *WMS capabilities* section, you can define the extent advertised in the WMS GetCapabilities response by entering the minimum and maximum X and Y values in the fields under *Advertised extent*. Clicking *Use Current Canvas Extent* sets these values to the extent currently displayed in the QGIS map canvas. By checking *CRS restrictions*, you can restrict in which coordinate reference systems (CRS) QGIS Server will offer to render maps. It is recommended that you restrict the offered CRS as this reduces the size of the WMS GetCapabilities response. Use the button below to select those CRSs from the Coordinate Reference System Selector, or click *Used* to add the CRSs used in

the QGIS project to the list.

If you have print layouts defined in your project, they will be listed in the GetProjectSettings response, and they can be used by the GetPrint request to create prints, using one of the print layouts as a template. This is a QGIS-specific extension to the WMS 1.3.0 specification. If you want to exclude any print layout from being published by

the WMS, check Exclude layouts and click the button below. Then, select a print layout from the Select print layout dialog in order to add it to the excluded layouts list.

If you want to exclude any layer or layer group from being published by the WMS, check Exclude Layers and click the button below. This opens the Select restricted layers and groups dialog, which allows you to choose the layers and groups that you don't want to be published. Use the Shift or Ctrl key if you want to select multiple entries. It is recommended that you exclude from publishing the layers that you don't need as this reduces the size of the WMS GetCapabilities response which leads to faster loading times on the client side.

If you check *Use layer ids as name*, layer ids will be used to reference layers in the GetCapabilities response or GetMap LAYERS parameter. If not, layer name or short name if defined (see vectorservermenu) is used.

You can receive requested GetFeatureInfo as plain text, XML and GML. The default is XML.

If you wish, you can check Add geometry to feature response. This will include the bounding box for each feature in the GetFeatureInfo response. See also the WITH_GEOMETRY parameter.

As many web clients can't display circular arcs in geometries you have the option to segmentize the geometry before sending it to the client in a GetFeatureInfo response. This allows such clients to still display a feature's geometry (e.g. for highlighting the feature). You need to check the Segmentize feature info geometry to activate the option.

You can also use the *GetFeatureInfo geometry precision* option to set the precision of the GetFeatureInfo geometry. This enables you to save bandwidth when you don't need the full precision.

If you want QGIS Server to advertise specific request URLs in the WMS GetCapabilities response, enter the corresponding URL in the Advertised URL field.

Furthermore, you can restrict the maximum size of the maps returned by the GetMap request by entering the maximum width and height into the respective fields under *Maximums for GetMap request*.

You can change the *Quality for JPEG images* factor. The quality factor must be in the range 0 to 100. Specify 0 for maximum compression, 100 for no compression.

You can change the limit for atlas features to be printed in one request by setting the *Maximum features for Atlas print requests* field.

When QGIS Server is used in tiled mode (see *TILED parameter*), you can set the *Tile buffer in pixels*. The recommended value is the size of the largest symbol or line width in your QGIS project.

If one of your layers uses the Map Tip display (i.e. to show text using expressions) this will be listed inside the GetFeatureInfo output. If the layer uses a Value Map for one of its attributes, this information will also be shown in the GetFeatureInfo output.

2.4.2 WFS capabilities

In the WFS capabilities area you can select the layers you want to publish as WFS, and specify if they will allow update, insert and delete operations. If you enter a URL in the Advertised URL field of the WFS capabilities section, QGIS Server will advertise this specific URL in the WFS GetCapabilities response.

2.4.3 WCS capabilities

In the WCS capabilities area, you can select the layers that you want to publish as WCS. If you enter a URL in the Advertised URL field of the WCS capabilities section, QGIS Server will advertise this specific URL in the WCS GetCapabilities response.

2.4.4 Fine tuning your OWS

For vector layers, the *Fields* menu of the *Layer* \triangleright *Layer Properties* dialog allows you to define for each attribute if it will be published or not. By default, all the attributes are published by your WMS and WFS. If you don't want a specific attribute to be published, uncheck the corresponding checkbox in the *WMS* or *WFS* column.

You can overlay watermarks over the maps produced by your WMS by adding text annotations or SVG annotations to the project file. See the sec_annotations section for instructions on creating annotations. For annotations to be displayed as watermarks on the WMS output, the *Fixed map position* checkbox in the *Annotation text* dialog must be unchecked. This can be accessed by double clicking the annotation while one of the annotation tools is active. For SVG annotations, you will need either to set the project to save absolute paths (in the *General* menu of the *Project* ► *Properties...* dialog) or to manually modify the path to the SVG image so that it represents a valid relative path.

2.5 Integration with third parties

QGIS Server provides standard OGC web services like WMS, WFS, etc. thus it can be used by a wide variety of end user tools.

2.5.1 Integration with QGIS Desktop

QGIS Desktop is the map designer where QGIS Server is the map server. The maps or QGIS projects will be served by the QGIS Server to provide OGC standards. These QGIS projects can either be files or entries in a database (by using *Project* ► *Save to* ► *PostgreSQL* in QGIS Desktop).

Furthermore, dedicated update workflow must be established to refresh a project used by a QGIS Server (ie. copy project files into server location and restart QGIS Server). For now, automated processes (as server reloading over message queue service) are not implemented yet.

2.5.2 Integration with MapProxy

MapProxy is a tile cache server and as it can read and serve any WMS/WMTS map server, it can be directly connected to QGIS server web services and improve end user experience.

2.5.3 Integration with QWC2

QWC2 is a responsive web application dedicated to QGIS Server. It helps you to build a highly customized map viewer with layer selection, feature info, etc.. Also many plugins are available like authentication or print service, the full list is available in this repository.

CHAPTER

THREE

SERVICES

QGIS Server is able to serve data according to standard protocols as described by the **Open Geospatial Consortium** (**OGC**):

- WMS 1.1.1 and 1.3.0
- WFS 1.0.0 and 1.1.0
- OGC API Features (WFS3)
- WCS 1.0.0 and 1.1.1
- WMTS 1.0.0

Extra vendor parameters and requests are supported in addition to the original standard that greatly enhance the possibilities of customizing its behavior thanks to the QGIS rendering engine.

3.1 Basics

This section describes concepts and parameters mutually shared by services. Some of these are standard and defined in OGC specifications while others are very specific to QGIS Server.

Standard concepts:

Concept	Description		
SERVICE	Name of the service		
REQUEST	Name of the request		

Vendor concepts:

Concept	Description
MAP	QGIS project file
FILE_NAME	File name of the downloaded file
Short name	Short name definition

3.1.1 SERVICE

This standard parameter allows to specify the name of the service to use for a specific *request* and has to be formed like SERVICE=NAME.

URL example for the WMS service:

```
http://localhost/qgisserver?
SERVICE=WMS
&...
```

Note: Not available for REST based services like WFS3 (OGC API Features).

3.1.2 REQUEST

This standard parameter allows to specify the name of the request to execute for a specific *service* and has to be formed like REQUEST=RequestName.

URL example for the **GetCapabilities** request:

```
http://localhost/qgisserver?
REQUEST=GetCapabilities
&...
```

Note: Not available for REST based services like WFS3 (OGC API Features).

3.1.3 MAP

This vendor parameter allows to define the QGIS project file to use. It may be an absolute path or a path relative to the location of the server executable <code>qgis_mapserv.fcgi</code>. MAP is mandatory by default because a request needs a QGIS project to actually work. However, the **QGIS_PROJECT_FILE** environment variable may be used to define a default QGIS project. In this specific case, MAP is no longer a required parameter. For further information you may refer to the *Advanced configuration* chapter.

URL example:

```
http://localhost/qgisserver?
MAP=/tmp/QGIS-Training-Data/exercise_data/qgis-server-tutorial-data/world.qgs
&...
```

3.1.4 FILE NAME

If this vendor parameter is set, the server response will be sent to the client as a file attachment with the specified file name

URL example to save an XML **GetCapabilities** document:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetCapabilities
&FILE_FORMAT=wms_capabilities.xml
&...
```

Note: Not available for REST based services like WFS3 (OGC API Features).

3.1.5 Short name

A number of elements have both a **short name** and a **title**. The short name is a text string used for machine-to-machine communication while the title is for the benefit of humans. For example, a dataset might have the descriptive title "Maximum Atmospheric Temperature" and be requested using the abbreviated short name "ATMAX". You can set title, short name and abstract for:

- Layers: right-click on a layer and choose *Properties...* ► *QGIS Server* ► *Description*.
- Groups: right-click on a group and select Set Group WMS data
- **Project**: go to *Project* ➤ *Properties...* ➤ *QGIS Server* ➤ *Service Capabilities.*




Fig. 3.1: Set group WMS data dialog

Thus, the short name may be used to identify these items when interacting with QGIS Server. For example with the standard LAYERS parameter:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&LAYERS=shortname1,shortname2
&...
```

3.2 Web Map Service (WMS)

The **1.1.1** and **1.3.0** WMS standards implemented in QGIS Server provide a HTTP interface to request map or legend images generated from a QGIS project. A typical WMS request defines the QGIS project to use, the layers to render as well as the image format to generate. Basic support is also available for **Styled Layer Descriptor (SLD)**.

Specifications:

- WMS 1.1.1
- WMS 1.3.0
- SLD 1.1.0 WMS profile

Standard requests provided by QGIS Server:

Request	Description			
GetCapabilities	Returns XML metadata with information about the server			
GetMap	Returns a map			
GetFeatureInfo	Retrieves data (geometry and values) for a pixel location			
GetLegendGraph-	Returns legend symbols			
ics				
GetStyle(s)	Returns XML document with style description in SLD			
DescribeLayer	ver Returns information about WFS and WCS availability respectively for vector and raster			
	layers			

Vendor requests provided by QGIS Server:

Request	Description
GetPrint	Returns a QGIS layout
GetProjectSettings	Returns specific information about QGIS Server
GetSchemaExtension	Returns XML metadata about optional extended capabilities

3.2.1 GetCapabilities

Standard parameters for the **GetCapabilities** request according to the OGC WMS 1.1.1 and 1.3.0 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WMS)
REQUEST	Yes	Name of the request (GetCapabilities)
VERSION	No	Version of the service

The **GetCapabilities** request supports as well the following vendor parameters:

Parameter	Required	Description		
MAP	Yes	QGIS project file		

URL example:

http://localhost/qgis_server?
SERVICE=WMS
&VERSION=1.3.0
&REQUEST=GetCapabilities

3.2.2 GetMap

Standard parameters for the **GetMap** request according to the OGC WMS 1.1.1 and 1.3.0 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WMS)
REQUEST	Yes	Name of the request (GetMap)
VERSION	Yes	Version of the service
LAYERS	No	Layers to display
STYLES	No	Layers' style
SRS / CRS	Yes	Coordinate reference system
BBOX	Yes	Map extent
WIDTH	Yes	Width of the image in pixels
HEIGHT	Yes	Height of the image in pixels
FORMAT	No	Image format
TRANSPARENT	No	Transparent background
SLD	No	URL of an SLD to be used for styling
SLD_BODY	No	In-line SLD (XML) to be used for styling

In addition to the standard ones, QGIS Server supports *redlining*, *external WMS layers* as well as the following extra parameters:

Parameter	Re-	Description	
	quired		
MAP	Yes	QGIS project file	
BGCOLOR	No	Specify the background color	
DPI	No	Specify the output resolution	
IMAGE_QUALITY	No	JPEG compression	
OPACITIES	No	Opacity for layer or group	
FILTER	No	Subset of features	
SELECTION	No	Highlight features	
FILE_NAME	No	File name of the downloaded file	
		Only for FORMAT=application/dxf	
FORMAT_OPTIONS	No	Options of the specified file format	
		Only for FORMAT=application/dxf	
TILED	No	Working in tiled mode	

URL example:

```
http://localhost/qgis_server?
SERVICE=WMS
&VERSION=1.3.0
&REQUEST=GetMap
&MAP=/home/qgis/projects/world.qgs
&LAYERS=mylayer1,mylayer2,mylayer3
&STYLES=style1,default,style3
&OPACITIES=125,200,125
&CRS=EPSG:4326
&WIDTH=400
&HEIGHT=400
&HEIGHT=400
&FORMAT=image/png
&TRANSPARENT=TRUE
&DPI=300
&TILED=TRUE
```

VERSION

This parameter allows to specify the version of the service to use. Available values for the VERSION parameter are:

- 1.1.1
- 1.3.0

According to the version number, slight differences have to be expected as explained later for the next parameters:

- CRS / SRS
- BBOX

LAYERS

This parameter allows to specify the layers to display on the map. Names have to be separated by a comma.

In addition, QGIS Server introduced some options to select layers by:

- a short name
- the layer id

The project option allowing to select layers by their id is in *QGIS Server* ► *WMS Capabilities* menu of the *Project* ► *Properties...* dialog. Check the *Use layer ids as names* checkbox to activate this option.

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetMap

&LAYERS=mylayerid1, mylayerid2
&...
```

STYLES

This parameter can be used to specify a layer's style for the rendering step. Styles have to be separated by a comma. The name of the default style is default.

SRS / CRS

This parameter allows to indicate the map output Spatial Reference System in WMS 1.1.1 and has to be formed like EPSG: XXXX. Note that CRS is also supported if current version is 1.1.1.

For WMS 1.3.0, CRS parameter is preferable but SRS is also supported.

Note that if both CRS and SRS parameters are indicated in the request, then it's the current version indicated in VERSION parameter which is decisive.

In the next case, the SRS parameter is kept whatever the VERSION parameter because CRS is not indicated:

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetMap

&VERSION=1.3.0

&SRS=EPSG:2854

&...
```

In the next case, the SRS parameter is kept instead of CRS because of the VERSION parameter:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.1.1
&CRS=EPSG:4326
&SRS=EPSG:2854
&...
```

In the next case, the CRS parameter is kept instead of SRS because of the VERSION parameter:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&CRS=EPSG:4326
&SRS=EPSG:2854
&...
```

BBOX

This parameter allows to specify the map extent with units according to the current CRS. Coordinates have to be separated by a comma.

The BBOX parameter is formed like min_a, min_b, max_a, max_b but a and b axis definition is different according to the current VERSION parameter:

- in WMS 1.1.1, the axis ordering is always east/north
- in WMS 1.3.0, the axis ordering depends on the CRS authority

For example in case of EPSG: 4326 and WMS 1.1.1, a is the longitude (east) and b the latitude (north), leading to a request like:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.1.1
&SRS=epsg:4326
&BBOX=-180,-90,180,90
&...
```

But in case of WMS 1.3.0, the axis ordering defined in the EPSG database is north/east so a is the latitude and b the longitude:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&CRS=epsg:4326
&BBOX=-90,-180,90,180
&...
```

WIDTH

This parameter allows to specify the width in pixels of the output image.

HEIGHT

This parameter allows to specify the height in pixels of the output image.

FORMAT

This parameter may be used to specify the format of map image. Available values are:

- jpg
- jpeg
- image/jpeg
- image/png
- image/png; mode=1bit
- image/png; mode=8bit
- image/png; mode=16bit
- application/dxf: only layers that have read access in the WFS service are exported in the DXF format URL example:

```
http://localhost/qgisserver?
SERVICE=WMS&VERSION=1.3.0
&REQUEST=GetMap
&FORMAT=application/dxf
&LAYERS=Haltungen,Normschacht,Spezialbauwerke
&CRS=EPSG%3A21781
&BBOX=696136.28844801,245797.12108743,696318.91114315,245939.25832905
&WIDTH=1042
&HEIGHT=811
&FORMAT_OPTIONS=MODE:SYMBOLLAYERSYMBOLOGY;SCALE:250
&FILE_NAME=plan.dxf
```

TRANSPARENT

This boolean parameter can be used to specify the background transparency. Available values are (not case sensitive):

- TRUE
- FALSE

However, this parameter is ignored if the format of the image indicated with FORMAT is different from PNG.

BGCOLOR

This parameter allows to indicate a background color for the map image. However it cannot be combined with TRANSPARENT parameter in case of PNG images (transparency takes priority). The colour may be literal or in hexadecimal notation.

URL example with the literal notation:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&BGCOLOR=green
&...
```

URL example with the hexadecimal notation:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&BGCOLOR=0x00FF00
&...
```

DPI

This parameter can be used to specify the requested output resolution.

IMAGE QUALITY

This parameter is only used for JPEG images. By default, the JPEG compression is -1.

You can change the default per QGIS project in the *OWS Server* ► *WMS capabilities* menu of the *Project* ► *Properties...* dialog. If you want to override it in a GetMap request you can do it using the IMAGE_QUALITY parameter.

OPACITIES

Comma separated list of opacity values. Opacity can be set on layer or group level. Allowed values range from 0 (fully transparent) to 255 (fully opaque).

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
&WIDTH=400
&HEIGHT=200
&CRS=EPSG:4326
&LAYERS=countries,places
&BBOX=42,-6,52,15
&OPACITIES=255,0
```





Fig. 3.2: To the left OPACITIES=255, 0 and to the right OPACITIES=255, 255

FILTER

A subset of layers can be selected with the FILTER parameter. The syntax is basically the same as for the QGIS subset string. However, there are some restrictions to avoid SQL injections into databases via QGIS Server. If a dangerous string is found in the parameter, QGIS Server will return the next error:

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&VERSION=1.3.0
```

(continues on next page)

(continued from previous page)

```
&WIDTH=400

&HEIGHT=300

&CRS=EPSG:4326

&BBOX=41,-6,52,10

&LAYERS=countries_shapeburst,countries,places

&FILTER=countries_shapeburst,countries:"name" = 'France';places: "name" = 'Paris'
```



Fig. 3.3: Server response to a GetMap request with FILTER parameter

In this example, the same filter "name" = 'France' is applied to layers countries and countries_shapeburst, while the filter "name" = 'Paris' is only applied to places.

Note: It is possible to make attribute searches via GetFeatureInfo and omit the X/Y parameter if a FILTER is there. QGIS Server then returns info about the matching features and generates a combined bounding box in the XML output.

SELECTION

The SELECTION parameter can highlight features from one or more layers. Vector features can be selected by passing comma separated lists with feature ids.

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&LAYERS=mylayer1,mylayer2
&SELECTION=mylayer1:3,6,9;mylayer2:1,5,6
&...
```

The following image presents the response from a GetMap request using the SELECTION option e.g. http://myserver.com/...&SELECTION=countries:171,65.

As those features id's correspond in the source dataset to **France** and **Romania** they're highlighted in yellow.



Fig. 3.4: Server response to a GetMap request with SELECTION parameter

FORMAT-OPTIONS

This parameter can be used to specify options for the selected format. Only for FORMAT=application/dxf. A list of key:value pairs separated by semicolon:

- SCALE: to be used for symbology rules, filters and styles (not actual scaling of the data data remains in the original scale).
- MODE: corresponds to the export options offered in the QGIS Desktop DXF export dialog. Possible values are NOSYMBOLOGY, FEATURESYMBOLOGY and SYMBOLLAYERSYMBOLOGY.
- LAYERSATTRIBUTES: specify a field that contains values for DXF layer names if not specified, the original QGIS layer names are used.
- USE_TITLE_AS_LAYERNAME: if enabled, the title of the layer will be used as layer name.
- CODEC: specify a codec to be used for encoding. Default is ISO-8859-1 check the QGIS desktop DXF export dialog for valid values.
- NO_MTEXT: Use TEXT instead of MTEXT for labels.
- FORCE_2D: Force 2D output. This is required for polyline width.

TILED

For performance reasons, QGIS Server can be used in tiled mode. In this mode, the client requests several small fixed size tiles, and assembles them to form the whole map. Doing this, symbols at or near the boundary between two tiles may appeared cut, because they are only present in one of the tile.

Set the TILED parameter to TRUE to tell QGIS Server to work in *tiled* mode, and to apply the *Tile buffer* configured in the QGIS project (see *Configure your project*).

When TILED is TRUE and when a non-zero Tile buffer is configured in the QGIS project, features outside the tile extent are drawn to avoid cut symbols at tile boundaries.

TILED defaults to FALSE.

3.2.3 GetFeatureInfo

Standard parameters for the **GetFeatureInfo** request according to the OGC WMS 1.1.1 and 1.3.0 specifications:

Parame-	Re-	Description	
ter	quirec		
SERVICE	Yes	Name of the service (WMS)	
RE-	Yes	Name of the request (GetFeatureInfo)	
QUEST			
VER-	No	Version of the service	
SION			
QUERY_LA	AYYE&SS	Layers to query	
LAYERS	Yes	Layers to display (identical to QUERY_LAYERS)	
STYLES	No	Layers' style	
SRS /	Yes	Coordinate reference system	
CRS			
BBOX	No	Map extent	
WIDTH	Yes	Width of the image in pixels	
HEIGHT	Yes	Height of the image in pixels	
TRANS-	No	Transparent background	
<i>PARENT</i>			
INFO_FOR	MMT	Output format	
FEA-	No	Maximum number of features to return	
TURE_CO	UNT		
I	No	Pixel column of the point to query	
X	No	Same as <i>I</i> parameter, but in WMS 1.1.1	
J	No	Pixel row of the point to query	
Y	No	Same as <i>J</i> parameter, but in WMS 1.1.1	
WMS_PRECUSIONThe precision (number of digits) to be used when returning geometry (see how to add geom-			
		etry to feature response). The default value is -1 meaning that the precision defined in the	
		project is used.	

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file
FILTER	No	Subset of features
FI_POINT_TOLERANCE	No	Tolerance in pixels for point layers
FI_LINE_TOLERANCE	No	Tolerance in pixels for line layers
FI_POLYGON_TOLERANCE	No	Tolerance in pixels for polygon layers
FILTER_GEOM	No	Geometry filtering
WITH_MAPTIP	No	Add map tips to the output
WITH_GEOMETRY	No	Add geometry to the output

URL example:

```
http://localhost/qgisserver?

SERVICE=WMS

&VERSION=1.3.0

&REQUEST=GetMap

&MAP=/home/qgis/projects/world.qgs

&LAYERS=mylayer1,mylayer2,mylayer3

&CRS=EPSG:4326

&WIDTH=400

&HEIGHT=400

&HEIGHT=400

&INFO_FORMAT=text/xml

&TRANSPARENT=TRUE

&QUERY_LAYERS=mylayer1

&FEATURE_COUNT=3

&I=250

&J=250
```

INFO FORMAT

This parameter may be used to specify the format of the result. Available values are:

- text/xml
- text/html
- text/plain
- application/vnd.ogc.gml
- application/json

QUERY_LAYERS

This parameter specifies the layers to display on the map. Names are separated by a comma.

In addition, QGIS Server introduces options to select layers by:

- short name
- · layer id

See the LAYERS parameter defined in GetMap for more information.

FEATURE COUNT

This parameter specifies the maximum number of features per layer to return. For example if QUERY_LAYERS is set to layer1, layer2 and FEATURE_COUNT is set to 3 then a maximum of 3 features from layer1 will be returned. Likewise a maximum of 3 features from layer2 will be returned.

By default, only 1 feature per layer is returned.

This parameter, defined in WMS 1.3.0, allows you to specify the pixel column of the query point.

X

Same parameter as I, but defined in WMS 1.1.1.

J

This parameter, defined in WMS 1.3.0, allows you to specify the pixel row of the query point.

Υ

Same parameter as J, but defined in WMS 1.1.1.

FI_POINT_TOLERANCE

This parameter specifies the tolerance in pixels for point layers.

FI_LINE_TOLERANCE

This parameter specifies the tolerance in pixels for line layers.

FI_POLYGON_TOLERANCE

This parameter specifies the tolerance in pixels for polygon layers.

FILTER_GEOM

This parameter specifies a WKT geometry with which features have to intersect.

WITH MAPTIP

This parameter specifies whether to add map tips to the output.

Available values are (not case sensitive):

- TRUE
- FALSE

WITH_GEOMETRY

This parameter specifies whether to add geometries to the output. To use this feature you must first enable the *Add geometry to feature response* option in the QGIS project. See *Configure your project*.

Available values are (not case sensitive):

- TRUE
- FALSE

3.2.4 GetLegendGraphics

 $Standard\ parameters\ for\ the\ \textbf{GetLegendGraphics}\ request\ according\ to\ the\ OGC\ WMS\ 1.1.1\ and\ 1.3.0\ specifications:$

Parameter	Required	Description
SERVICE	Yes	Name of the service (WMS)
REQUEST	Yes	Name of the request (GetLegendGraphics)
VERSION	No	Version of the service
LAYERS	Yes	Layers to display
STYLES	No	Layers' style
SRS / CRS	No	Coordinate reference system
BBOX	No	Map extent
WIDTH	No	Width of the image in pixels
HEIGHT	No	Height of the image in pixels
FORMAT	No	Legend format
TRANSPARENT	No	Transparent background

In addition to the standard ones, QGIS Server supports extra parameters to change the size of the legend elements or the font properties for layer titles and item labels:

Parameter	Required	Description
MAP	Yes	QGIS project file
SRCWIDTH	No	Map width
SRCHEIGHT	No	Map height
SHOWFEATURECOUNT	No	Add feature count of features
RULE	No	Rule symbol to render
RULELABEL	No	Item labels rendering
BOXSPACE	No	Space between legend frame and content (mm)
LAYERSPACE	No	Vertical space between layers (mm)
LAYERTITLESPACE	No	Vertical space between layer title and items (mm)
SYMBOLSPACE	No	Vertical space between symbol and items (mm)
ICONLABELSPACE	No	Horizontal space between symbol and label (mm)
SYMBOLWIDTH	No	Width of the symbol preview (mm)
SYMBOLHEIGHT	No	Height of the symbol preview (mm)
LAYERTITLE	No	Layer title rendering
LAYERFONTFAMILY	No	Layer font family
LAYERFONTBOLD	No	Layer title bold rendering
LAYERFONTSIZE	No	Layer title font size (pt)
LAYERFONTITALIC	No	Layer title italic rendering
LAYERFONTCOLOR	No	Layer title color
ITEMFONTFAMILY	No	Item font family
ITEMFONTBOLD	No	Item label bold rendering
ITEMFONTSIZE	No	Item label font size (pt)
ITEMFONTITALIC	No	Item label italic rendering
ITEMFONTCOLOR	No	Item label color

BBOX

This parameter can be used to specify the geographical area for which the legend should be built (its format is described *here*) but cannot be combined with the RULE parameter. The SRS/CRS parameter becomes mandatory when using the BBOX parameter.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries,airports
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
```

Note: When the BBOX parameter is defined, the legend is referred to as a content based legend.

WIDTH

This parameter is not used by default but becomes mandatory when the RULE parameter is set. In this case it allows to specify the width in pixels of the output image.

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYER=testlayer%20%C3%A8%C3%A9
&RULE=rule1
&WIDTH=30
&HEIGHT=30
```

HEIGHT

This parameter is not used by default but becomes mandatory when the RULE parameter is set. In this case it allows to specify the height in pixels of the output image.

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics
&LAYER=testlayer%20%C3%A8%C3%A9
&RULE=rule1
&WIDTH=30
&HEIGHT=30
```

FORMAT

This parameter may be used to specify the format of legend image. Available values are:

- image/jpeg
- image/png
- application/json

For JSON, symbols are encoded with Base64 and most other options related to layout or fonts are not taken into account because the legend must be built on the client side. The RULE parameter cannot be combined with this format.

URL example with the corresponding JSON output:

```
http://localhost/qgisserver?

SERVICE=WMS&

REQUEST=GetLegendGraphics&

LAYERS=airports&

FORMAT=application/json
```

And the corresponding JSON output:

SRCWIDTH

This parameter may de defined when the RULE parameter is set. In this case, the SRCWIDTH value is forwarded to the underlying GetMap request as the WIDTH parameter while the WIDTH parameter of GetLegendGraphics is used for the image legend size.

SRCHEIGHT


This parameter may de defined when the RULE parameter is set. In this case, the SRCHEIGHT value is forwarded to the underlying GetMap request as the HEIGHT parameter while the HEIGHT parameter of GetLegendGraphics is used for the image legend size.

SHOWFEATURECOUNT

This parameter can be used to activate feature count in the legend. Available values are (not case sensitive):

- TRUE
- FALSE

For example:



RULE

This parameter is available on layers with *Rule-based* rendering and allows to build a legend with only the named rule symbol. It cannot be combined with BBOX parameter nor the JSON format.

URL example:

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics
&LAYERS=mylayer,
&RULE=myrulename
```

RULELABEL

This parameter allows to control the item label rendering. Available values are (not case sensitive):

- TRUE: display item label
- FALSE: hide item label
- AUTO: hide item label for layers with Single symbol rendering

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics
&LAYERS=countries,airports
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&RULELABEL=AUTO
```




Fig. 3.5: Legend rendering without label for single symbol layers

BOXSPACE

This parameter allows to specify the space between legend frame and content in millimeters. By default, the space value is 2 mm.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&BOXSPACE=0
```




Fig. 3.6: To the left BOXSPACE=0 and to the right BOXSPACE=15

LAYERSPACE

This parameter allows to specify the vertical space between layers in millimeters. By default, the space value is 3 mm.

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics

&LAYERS=airports,places

&BBOX=43.20,-2.93,49.35,8.32

&CRS=EPSG:4326

&TRANSPARENT=TRUE

&LAYERSPACE=0
```




Fig. 3.7: To the left LAYERSPACE=0 and to the right LAYERSPACE=10

LAYERTITLESPACE

This parameter allows to specify the vertical space between layer title and items following in millimeters. By default the space value is 3 mm.

URL example:

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics

&LAYERS=airports,places

&BBOX=43.20,-2.93,49.35,8.32

&CRS=EPSG:4326

&TRANSPARENT=TRUE

&LAYERTITLESPACE=0
```




Fig. 3.8: To the left LAYERTITLESPACE=0 and to the right LAYERTITLESPACE=10

SYMBOLSPACE

This parameter allows to specify the vertical space between symbol and item following in millimeters. By default the space value is 2 mm.

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&SYMBOLSPACE=0
```




Fig. 3.9: To the left ${\tt SYMBOLSPACE=0}$ and to the right ${\tt SYMBOLSPACE=5}$

ICONLABELSPACE

This parameter allows to specify the horizontal space between symbol and label text in millimeters. By default the space value is 2 mm.

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics
&LAYERS=countries,
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&ICONLABELSPACE=0
```



Fig. 3.10: To the left <code>ICONLABELSPACE=0</code> and to the right <code>ICONLABELSPACE=10</code>

SYMBOLWIDTH

This parameter allows to specify the width of the symbol preview in millimeters. By default the width value is 7 mm.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries,
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&SYMBOLWIDTH=2
```



Fig. 3.11: To the left SYMBOLWIDTH=2 and to the right SYMBOLWIDTH=20

SYMBOLHEIGHT

This parameter allows to specify the height of the symbol preview in millimeters. By default the height value is 4 mm.

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries,
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&SYMBOLHEIGHT=2
```




Fig. 3.12: To the left SYMBOLHEIGHT=2 and to the right SYMBOLHEIGHT=6

LAYERTITLE

This parameter specifies whether to render layer title.

Available values are (not case sensitive):

- TRUE (default value)
- FALSE

LAYERFONTFAMILY

This parameter specifies the font family to use for rendering layer title.

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=countries
&LAYERFONTFAMILY=monospace
```

LAYERFONTBOLD

This parameter specifies whether the layer title is rendered in bold. Available values are (not case sensitive):

- TRUE
- FALSE

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports,places
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&LAYERFONTBOLD=TRUE
```



Fig. 3.13: Legend with LAYERFONTBOLD=TRUE

LAYERFONTSIZE

This parameter specifies the font size for rendering layer title in point.

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports,places
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&LAYERFONTSIZE=20
```



Fig. 3.14: Legend with LAYERFONTSIZE=20

LAYERFONTITALIC

This parameter specifies whether the layer title is rendered in italic. Available values are (not case sensitive):

- TRUE
- FALSE

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics

&LAYERS=airports,places

&BBOX=43.20,-2.93,49.35,8.32

&CRS=EPSG:4326

&TRANSPARENT=TRUE

&LAYERFONTITALIC=TRUE
```



Fig. 3.15: Legend with LAYERFONTITALIC=TRUE

LAYERFONTCOLOR

This parameter specifies the layer title color. The color may be literal (red, green, ..) or in hexadecimal notation (0xFF0000, 0x00FF00, ...).

URL example:

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics

&LAYERS=airports,places

&BBOX=43.20,-2.93,49.35,8.32

&CRS=EPSG:4326

&TRANSPARENT=TRUE

&LAYERFONTCOLOR=0x5f9930
```



Fig. 3.16: Legend with LAYERFONTCOLOR=0x5f9930

ITEMFONTFAMILY

This parameter specifies the font family to use for rendering item label.

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics
&LAYERS=countries
&ITEMFONTFAMILY=monospace
```

ITEMFONTBOLD

This parameter specifies whether the item label is rendered in bold. Available values are (not case sensitive):

- TRUE
- FALSE

URL example:

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics

&LAYERS=airports,places

&BBOX=43.20,-2.93,49.35,8.32

&CRS=EPSG:4326

&TRANSPARENT=TRUE

&ITEMFONTBOLD=TRUE
```



Fig. 3.17: Legend with ITEMFONTBOLD=TRUE

ITEMFONTSIZE

This parameter specifies the font size for rendering layer title in point.

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports,places
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&ITEMFONTSIZE=20
```



Fig. 3.18: Legend with ITEMFONTSIZE=30

ITEMFONTITALIC

This parameter specifies whether the item label is rendered in italic. Available values are (not case sensitive):

- TRUE
- FALSE

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetLegendGraphics
&LAYERS=airports,places
&BBOX=43.20,-2.93,49.35,8.32
&CRS=EPSG:4326
&TRANSPARENT=TRUE
&ITEMFONTITALIC=TRUE
```



Fig. 3.19: Legend with ITEMFONTITALIC=TRUE

ITEMFONTCOLOR

This parameter specifies the item label color. The color may be literal (red, green, ..) or in hexadecimal notation (0xFF0000, 0x00FF00, ...).

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetLegendGraphics

&LAYERS=airports,places

&BBOX=43.20,-2.93,49.35,8.32

&CRS=EPSG:4326

&TRANSPARENT=TRUE

&ITEMFONTCOLOR=0x5f9930
```



Fig. 3.20: Legend with ITEMFONTCOLOR=0x5f9930

3.2.5 GetStyle(s)

Standard parameters for the GetStyle (or GetStyles) request according to the OGC WMS 1.1.1 specifications:

Parameter	Required	Description	
SERVICE	Yes	Name of the service (WMS)	
REQUEST	Yes	Name of the request (GetStyle or GetStyles)	
LAYERS	Yes	Layers to query	

The **GetStyle** request supports as well the following vendor parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file

URL example:

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetStyles

&LAYERS=mylayer1, mylayer2
```

3.2.6 DescribeLayer

Standard parameters for the **DescribeLayer** request according to the OGC WMS 1.1.1 and 1.3.0 specifications:

Parameter	Required	Description	
SERVICE	Yes Name of the service (WMS)		
REQUEST	Yes	Name of the request (DescribeLayer)	
LAYERS	Yes	Layers to describe	
SLD_VERSION	Yes	SLD version	

The **DescribeLayer** request supports as well the following vendor parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file

URL example:

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=DescribeLayer

&SLD_VERSION=1.1.0

&LAYERS=mylayer1
```

The XML document looks like:

SLD_VERSION

This parameter allows to specify the version of SLD. Only the value 1.1.0 is available.

3.2.7 GetPrint

QGIS Server has the capability to create print layout output in pdf or pixel format. Print layout windows in the published project are used as templates. In the **GetPrint** request, the client has the possibility to specify parameters of the contained layout maps and labels.

The **GetPrint** request supports *redlining*, *external WMS layers* as well as the following parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file
SERVICE	Yes	Name of the service (WMS)
REQUEST	Yes	Name of the request (GetPrint)
VERSION	No	Version of the service
LAYERS	No	Layers to display
TEMPLATE	Yes	Layout template to use
SRS / CRS	Yes	Coordinate reference system
FORMAT	No	Output format
ATLAS_PK	No	Atlas features
STYLES	No	Layers' style
TRANSPARENT	No	Transparent background
OPACITIES	No	Opacity for layer or group
SELECTION	No	Highlight features
mapX:EXTENT	No	Extent of the map 'X'
mapX:LAYERS	No	Layers of the map 'X'
mapX:STYLES	No	Layers' style of the map 'X'
mapX:SCALE	No	Layers' scale of the map 'X'
mapX:ROTATION	No	Rotation of the map 'X'
mapX:GRID_INTERVAL_X	No	Grid interval on x axis of the map 'X'
mapX:GRID_INTERVAL_Y	No	Grid interval on y axis of the map 'X'

URL example:

```
http://localhost/qgisserver?

SERVICE=WMS
&VERSION=1.3.0
&REQUEST=GetPrint
&MAP=/home/qgis/projects/world.qgs
```

```
&CRS=EPSG:4326
&FORMAT=png
&TEMPLATE=Layout%201
&map0:EXTENT=-180,-90,180,90
&map0:LAYERS=mylayer1,mylayer2,mylayer3
&map0:OPACITIES=125,200,125
&map0:ROTATION=45
```

Note that the layout template may contain more than one map. In this way, if you want to configure a specific map, you have to use mapX: parameters where X is a positive number that you can retrieve thanks to the **GetProjectSettings** request.

For example:

```
<WMS_Capabilities>
...
<ComposerTemplates xsi:type="wms:_ExtendedCapabilities">
<ComposerTemplate width="297" height="210" name="Druckzusammenstellung 1">
<ComposerMap width="171" height="133" name="map0"/>
<ComposerMap width="49" height="46" name="map1"/></ComposerTemplate>
</ComposerTemplates>
...
</WMS_Capabilities>
```

TEMPLATE

This parameter can be used to specify the name of a layout template to use for printing.

FORMAT

This parameter specifies the format of map image. Available values are:

- png (default value)
- image/png
- jpg
- jpeg
- image/jpeg
- svg
- image/svg
- image/svg+xml
- pdf
- application/pdf

If the FORMAT parameter is different from one of these values, then an exception is returned.

ATLAS PK

This parameter allows activation of Atlas rendering by indicating which features we want to print. In order to retrieve an atlas with all features, the * symbol may be used (according to the maximum number of features allowed in the project configuration).

When FORMAT is pdf, a single PDF document combining the feature pages is returned. For all other formats, a single page is returned.

mapX:EXTENT

This parameter specifies the extent for a layout map item as xmin,ymin,xmax,ymax.

mapX:ROTATION

This parameter specifies the map rotation in degrees.

mapX:GRID_INTERVAL_X

This parameter specifies the grid line density in the X direction.

mapX:GRID_INTERVAL_Y

This parameter specifies the grid line density in the Y direction.

mapX:SCALE

This parameter specifies the map scale for a layout map item. This is useful to ensure scale based visibility of layers and labels even if client and server may have different algorithms to calculate the scale denominator.

mapX:LAYERS

This parameter specifies the layers for a layout map item. See *GetMap Layers* for more information on this parameter.

mapX:STYLES

This parameter specifies the layers' styles defined in a specific layout map item. See *GetMap Styles* for more information on this parameter.

3.2.8 GetProjectSettings

This request type works similar to *GetCapabilities*, but it is more specific to QGIS Server and allows a client to read additional information which are not available in the *GetCapabilities* output:

- initial visibility of layers
- information about vector attributes and their edit types
- · information about layer order and drawing order
- · list of layers published in WFS
- show if a group in the layer tree is mutually exclusive

The **GetProjectSettings** request supports the following parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file
SERVICE	Yes	Name of the service (WMS)
REQUEST	Yes	Name of the request (GetProjectSettings)

3.2.9 GetSchemaExtension

The **GetSchemaExtension** request allows to retrieve optional extended capabilities and operations of the WMS service such as implemented by QGIS Server.

Parameter	Required	Description	
MAP	Yes	QGIS project file	
SERVICE	Yes	Name of the service (WMS)	
REQUEST	Yes	Name of the request (GetSchemaExtension)	

URL example:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetSchemaExtension
```

The XML document looks like:

3.2.10 External WMS layers

QGIS Server allows including layers from external WMS servers in WMS *GetMap* and WMS *GetPrint* requests. This is especially useful if a web client uses an external background layer in the web map. For performance reasons, such layers should be directly requested by the web client (not cascaded via QGIS server). For printing however, these layers should be cascaded via QGIS server in order to appear in the printed map.

External layers can be added to the LAYERS parameter as EXTERNAL_WMS:<layername>. The parameters for the external WMS layers (e.g. url, format, dpiMode, crs, layers, styles) can later be given as service parameters <layername>:<parameter>. In a *GetMap* request, this might look like this:

```
http://localhost/qgisserver?
SERVICE=WMS
&REQUEST=GetMap
&LAYERS=EXTERNAL_WMS:basemap,layer1,layer2
&OPACITIES=100,200,255
&STYLES=,,
&basemap:url=http://externalserver.com/wms.fcgi
&basemap:format=image/jpeg
&basemap:dpiMode=7
&basemap:crs=EPSG:2056
```

```
&basemap:layers=orthofoto
&basemap:styles=default
```

Similarly, external layers can be used in *GetPrint* requests:

```
http://localhost/qgisserver?

SERVICE=WMS

&REQUEST=GetPrint

&TEMPLATE=A4

&map0:layers=EXTERNAL_WMS:basemap,layer1,layer2

&map0:EXTENT=<minx,miny,maxx,maxy>

&OPACITIES=100,200,255

&basemap:url=http://externalserver.com/wms.fcgi
&basemap:format=image/jpeg
&basemap:dpiMode=7
&basemap:crs=EPSG:2056
&basemap:layers=orthofoto
&basemap:styles=default
```

3.2.11 Redlining

This feature is available and can be used with GetMap and GetPrint requests.

The redlining feature can be used to pass geometries and labels in the request which are overlapped by the server over the standard returned image (map). This permits the user to put emphasis or maybe add some comments (labels) to some areas, locations etc. that are not in the standard map.

The *GetMap* request is in the format:

```
http://localhost/ggisserver?
SERVICE=WMS
&VERSION=1.3.0
&REQUEST=GetMap
&HIGHLIGHT_GEOM=POLYGON((590000 5647000, 590000 6110620, 2500000 6110620, 2500000
\hookrightarrow 5647000, 590000 5647000))
&HIGHLIGHT_SYMBOL=<StyledLayerDescriptor><UserStyle><Name>Highlight</Name>
→<FeatureTypeStyle><Rule><Name>Symbol</Name><LineSymbolizer><Stroke><SvgParameter_
→name="stroke">%23ea1173</SvgParameter><SvgParameter name="stroke-opacity">1</
→SvgParameter><SvgParameter name="stroke-width">1.6</SvgParameter></Stroke></
→LineSymbolizer></Rule></FeatureTypeStyle></UserStyle></StyledLayerDescriptor>
&HIGHLIGHT_LABELSTRING=Write label here
&HIGHLIGHT_LABELSIZE=16
&HIGHLIGHT_LABELCOLOR=%23000000
&HIGHLIGHT_LABELBUFFERCOLOR=%23FFFFFF
&HIGHLIGHT_LABELBUFFERSIZE=1.5
```

The GetPrint equivalent is in the format (note that mapX: parameter is added to tell which map has redlining):

&map0:HIGHLIGHT_LABELSIZE=16
&map0:HIGHLIGHT_LABELCOLOR=%23000000
&map0:HIGHLIGHT_LABELBUFFERCOLOR=%23FFFFFF
&map0:HIGHLIGHT_LABELBUFFERSIZE=1.5

Here is the image outputed by the above request in which a polygon and a label are drawn on top of the normal map:



Fig. 3.21: Server response to a GetMap request with redlining parameters

You can see there are several parameters in this request:

- HIGHLIGHT_GEOM: You can add POINT, MULTILINESTRING, POLYGON etc. It supports multipart geometries. Here is an example: <code>HIGHLIGHT_GEOM=MULTILINESTRING((0 0, 0 1, 1 1))</code>. The coordinates should be in the CRS of the GetMap/GetPrint request.
- **HIGHLIGHT_SYMBOL**: This controls how the geometry is outlined and you can change the stroke width, color and opacity.
- HIGHLIGHT_LABELSTRING: You can pass your labeling text to this parameter.
- HIGHLIGHT_LABELSIZE: This parameter controls the size of the label.
- HIGHLIGHT LABELFONT: This parameter controls the font of the label (e.g. Arial)
- **HIGHLIGHT_LABELCOLOR**: This parameter controls the label color.
- HIGHLIGHT_LABELBUFFERCOLOR: This parameter controls the label buffer color.

• HIGHLIGHT_LABELBUFFERSIZE: This parameter controls the label buffer size.

3.3 Web Feature Service (WFS)

The **1.0.0** and **1.1.0** WFS standards implemented in QGIS Server provide a HTTP interface to query geographic features from a QGIS project. A typical WFS request defines the QGIS project to use and the layer to query.

Specifications document according to the version number of the service:

- WFS 1.0.0
- WFS 1.1.0

Standard requests provided by QGIS Server:

Request	Description
GetCapabilities	Returns XML metadata with information about the server
GetFeature	Returns a selection of features
DescribeFeatureType	Returns a description of feature types and properties
Transaction	Allows features to be inserted, updated or deleted

3.3.1 GetCapabilities

Standard parameters for the **GetCapabilities** request according to the OGC WFS 1.0.0 and 1.1.0 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WFS)
REQUEST	Yes	Name of the request (GetCapabilities)
VERSION	No	Version of the service

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file

VERSION

This parameter allows to specify the version of the service to use. Available values for the VERSION parameter are:

- 1.0.0
- 1.1.0

If no version is indicated in the request, then 1.1.0 is used by default.

```
http://localhost/qgisserver?

SERVICE=WFS
&VERSION=1.1.0
&...
```

3.3.2 GetFeature

Standard parameters for the **GetFeature** request according to the OGC WFS 1.0.0 and 1.1.0 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WFS)
REQUEST	Yes	Name of the request (GetFeature)
VERSION	No	Version of the service
TYPENAME	No	Name of layers
FEATUREID	No	Filter the features by ids
OUTPUTFORMAT	No	Output Format
RESULTTYPE	No	Type of the result
PROPERTYNAME	No	Name of properties to return
MAXFEATURES	No	Maximum number of features to return
SRSNAME	No	Coordinate reference system
FILTER	No	OGC Filter Encoding
BBOX	No	Map Extent
SORTBY	No	Sort the results

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file
STARTINDEX	No	Paging
GEOMETRYNAME	No	Type of geometry to return
EXP_FILTER	No	Expression filtering

TYPENAME

This parameter allows to specify layer names and is mandatory if FEATUREID is not set.

URL example:

```
http://localhost/qgisserver?

SERVICE=WFS

&VERSION=1.1.0

&REQUEST=GetFeature
&TYPENAME=countries
```

FEATUREID

This parameter allows to specify the ID of a specific feature and is formed like typename.fid, typename. fid,

URL example:

```
http://localhost/qgisserver?

SERVICE=WFS

&REQUEST=GetFeature

&FEATUREID=countries.0,places.1
```

XML response:

```
<wfs:FeatureCollection xmlns:wfs="http://www.opengis.net/wfs" xmlns:oqc="http://</pre>
→www.opengis.net/ogc" xmlns:qml="http://www.opengis.net/gml" xmlns:ows="http://
→www.opengis.net/ows" xmlns:xlink="http://www.w3.org/1999/xlink" xmlns:qgs="http:/
→/www.qgis.org/gml" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"_
→xsi:schemaLocation="http://www.opengis.net/wfs http://schemas.opengis.net/wfs/1.
→1.0/wfs.xsd http://www.qgis.org/gml http://192.168.1.15/qgisserver?SERVICE=WFS&
→VERSION=1.1.0&REQUEST=DescribeFeatureType&TYPENAME=countries,places&
→OUTPUTFORMAT=text/xml; subtype%3Dgml/3.1.1">
 <qml:boundedBy>
 </gml:boundedBy>
 <qml:featureMember>
   <qgs:countries gml:id="countries.1">
   </qgs:countries>
 </gml:featureMember>
 <qml:featureMember>
   <qgs:places gml:id="places.1">
   </qgs:places>
 </gml:featureMember>
</wfs:FeatureCollection>
```

OUTPUTFORMAT

This parameter may be used to specify the format of the response. If VERSION is greater or equal than 1.1.0, GML3 is the default format. Otherwise GML2 is used.

Available values are:

- gml2
- text/xml; subtype=gml/2.1.2
- qml3
- text/xml; subtype=gml/3.1.1
- geojson
- application/vnd.geo+json,
- application/vnd.geo json
- application/geo+json
- application/geo json
- application/json

URL example:

```
http://localhost/qgisserver?

SERVICE=WFS

&REQUEST=GetFeature

&FEATUREID=countries.0

&OUTPUTFORMAT=geojson
```

GeoJSON response:

```
"type":"FeatureCollection",
"bbox":[
    -180,
```

```
-90,
    180,
    83.6236
"features":[
    {
        "bbox":[
            -61.891113,
            16.989719,
             -61.666389,
            17.724998
        ],
        "geometry":{
             "coordinates":[
                 " . . . "
             "type": "MultiPolygon"
        },
        "id": "countries.1",
        "properties":{
             "id":1,
             "name": "Antigua and Barbuda"
        "type": "Feature"
    }
]
```

RESULTTYPE

This parameter may be used to specify the kind of result to return. Available values are:

- results: the default behavior
- hits: returns only a feature count

URL example:

```
http://localhost/qgisserver?

SERVICE=WFS
&VERSION=1.1.0
&REQUEST=GetFeature
&RESULTTYPE=hits
&...
```

PROPERTYNAME

This parameter may be used to specify a specific property to return. A property needs to be mapped with a TYPE-NAME or a FEATUREID:

Valid URL example:

```
http://localhost/qgisserver?
SERVICE=WFS
&REQUEST=GetFeature
&PROPERTYNAME=name
&TYPENAME=places
```

On the contrary, the next URL will return an exception:

```
http://localhost/qgisserver?

SERVICE=WFS

&REQUEST=GetFeature

&PROPERTYNAME=name
&TYPENAME=places, countries
```

MAXFEATURES

This parameter allows to limit the number of features returned by the request.

Note: This parameter may be useful to improve performances when underlying vector layers are heavy.

SRSNAME

This parameter allows to indicate the response output Spatial Reference System as well as the BBOX CRS and has to be formed like EPSG: XXXX.

```
http://localhost/qgisserver?

SERVICE=WFS

&REQUEST=GetFeature

&TYPENAME=places

&SRSNAME=EPSG:32620
```

FILTER

This parameter allows to filter the response with the **Filter Encoding** language defined by the OGC Filter Encoding standard.

URL example:

```
http://localhost/qgisserver?

SERVICE=WFS&

REQUEST=GetFeature&

TYPENAME=places&

FILTER=<Filter><PropertyIsEqualTo><PropertyName>name</PropertyName><Literal>Paris</
```

BBOX

This parameter allows to specify the map extent with units according to the current CRS. Coordinates have to be separated by a comma.

The SRSNAME parameter may specify the CRS of the extent. If not specified, the CRS of the layer is used.

URL example:

```
http://localhost/qgisserver?
SERVICE=WFS
&REQUEST=GetFeature
```

```
&TYPENAME=places
&BBOX=-11.84,42.53,8.46,50.98
```

The FEATUREID parameter cannot be used with the BBOX. Any attempt will result in an exception:

SORTBY

This parameter allows to sort resulting features according to property values and has to be formed like property-name SORTRULE.

Available values for SORTRULE in case of descending sorting:

- D
- +D
- DESC
- +DESC

Available values for SORTRULE in case of ascending sorting:

- A
- +A
- ASC
- +ASC

URL example:

```
http://localhost/qgisserver?

SERVICE=WFS

&REQUEST=GetFeature

&TYPENAME=places

&PROPERTYNAME=name

&MAXFEATURES=3

&SORTBY=name DESC
```

The corresponding result:

GEOMETRYNAME

This parameter can be used to specify the kind of geometry to return for features. Available values are:

- extent
- centroid
- none

URL example:

```
http://localhost/qgisserver?
SERVICE=WFS
&VERSION=1.1.0
&REQUEST=GetFeature
&GEOMETRYNAME=centroid
&...
```

STARTINDEX

This parameter is standard in WFS 2.0, but it's an extension for WFS 1.0.0.

Actually, it can be used to skip some features in the result set and in combination with MAXFEATURES, it provides the ability to page through results.

URL example:

```
http://localhost/qgisserver?

SERVICE=WFS
&VERSION=1.1.0
&REQUEST=GetFeature
&STARTINDEX=2
&...
```

EXP_FILTER

This parameter allows to filter the response with QGIS expressions.

```
http://localhost/qgisserver?

SERVICE=WFS&

REQUEST=GetFeature&

TYPENAME=places&

EXP_FILTER="name"='Paris'
```

3.3.3 DescribeFeatureType

Standard parameters for the **DescribeFeatureType** request according to the OGC WFS 1.0.0 and 1.1.0 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WFS)
REQUEST	Yes	Name of the request (DescribeFeatureType)
VERSION	No	Version of the service
OUTPUTFORMAT	No	Format of the response
TYPENAME	No	Name of layers

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file

URL example:

```
http://localhost/qgisserver?

SERVICE=WFS

&VERSION=1.1.0

&REQUEST=DescribeFeatureType
&TYPENAME=countries
```

Output response:

```
<schema xmlns:ogc="http://www.opengis.net/ogc" xmlns:xsd="http://www.w3.org/2001/</pre>
→XMLSchema" xmlns="http://www.w3.org/2001/XMLSchema" xmlns:qgs="http://www.qgis.
→org/gml" xmlns:gml="http://www.opengis.net/gml" targetNamespace="http://www.qgis.
→org/gml" version="1.0" elementFormDefault="qualified">
 <import schemaLocation="http://schemas.opengis.net/gml/3.1.1/base/gml.xsd"_</pre>
→namespace="http://www.opengis.net/gml"/>
 <element type="qgs:countriesType" substitutionGroup="gml:_Feature" name=</pre>
→"countries"/>
 <complexType name="countriesType">
    <complexContent>
      <extension base="gml:AbstractFeatureType">
        <sequence>
          <element minOccurs="0" type="gml:MultiPolygonPropertyType" maxOccurs="1"_</pre>
→name="geometry"/>
          <element type="long" name="id"/>
          <element nillable="true" type="string" name="name"/>
        </sequence>
      </extension>
    </complexContent>
 </complexType>
</schema>
```

3.3.4 Transaction

This request allows to update, delete or add one or several features thanks to a XML document. The *delete* action may be achieved with a POST request as well as with the *OPERATION* parameter while the *add* and the *update* operations may be achieved through POST request only.

Standard parameters for the **Transaction** request according to the OGC WFS 1.0.0 and 1.1.0 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WFS)
REQUEST	Yes	Name of the request (Transaction)
VERSION	No	Version of the service
FILTER	No	OGC Filter Encoding
BBOX	No	Map Extent
FEATUREID	No	Filter the features by ids
TYPENAME	No	Name of layers

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file
OPERATION	No	Specify the operation
EXP_FILTER	No	Expression filtering

OPERATION

This parameter allows to delete a feature without using a POST request with a dedicated XML document.

URL example:

```
http://localhost/qgisserver?
SERVICE=WFS
&VERSION=1.1.0
&REQUEST=Transaction
&OPERATION=DELETE
&FEATUREID=24
```

Note: FEATUREID, BBOX and FILTER parameters are mutually exclusive and prioritized in this order.

Add features

POST request example:

```
wget --post-file=add.xml "http://localhost/qgisserver?SERVICE=WFS&

→REQUEST=Transaction"
```

with the add.xml document:

Update features

POST request example:

with the *update.xml* document:

```
<?xml version="1.0" encoding="UTF-8"?>
<wfs:Transaction service="WFS" version="1.0.0" xmlns:wfs="http://www.opengis.net/</pre>
→wfs" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:ogc="http://www.
→opengis.net/ogc" xmlns="http://www.opengis.net/wfs" updateSequence="0"_
→xmlns:xlink="http://www.w3.org/1999/xlink" xsi:schemaLocation="http://www.
→opengis.net/wfs http://schemas.opengis.net/wfs/1.0.0/WFS-capabilities.xsd"_
→xmlns:gml="http://www.opengis.net/gml" xmlns:ows="http://www.opengis.net/ows">
   <wfs:Update typeName="places">
     <wfs:Property>
          <wfs:Name>name</wfs:Name>
          <wfs:Value>Lutece</wfs:Value>
     </wfs:Property>
     <ogc:Filter>
          <ogc:FeatureId fid="24"/>
     </ogc:Filter>
   </wfs:Update>
</wfs:Transaction>
```

Delete features

POST request example:

```
wget --post-file=delete.xml "http://localhost/qgisserver?SERVICE=WFS&

→REQUEST=Transaction"
```

with the delete.xml document:

3.4 Web Coverage Service (WCS)

The **1.0.0** and **1.1.1** WCS standards implemented in QGIS Server provide a HTTP interface to access raster data, referred to as *coverage*, coming from a QGIS project.

Specifications:

- WCS 1.0.0
- WCS 1.1.1

Standard requests provided by QGIS Server:

	Request	Description	
	GetCapabilities	Returns XML metadata with information about the server	
	DescribeCoverage	Retrieves XML document about additional information about coverages	
Ì	GetCoverage	Retrieves coverage	

3.4.1 GetCapabilities

Standard parameters for the GetCapabilities request according to the OGC WCS 1.1.1 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WCS)
REQUEST	Yes	Name of the request (GetCapabilities)
VERSION	No	Version of the service

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file

URL example:

```
http://localhost/qgis_server?
SERVICE=WCS
&VERSION=1.1.1
&REQUEST=GetCapabilities
```

XML document example when a single raster layer (named T20QPD_20171123T144719_TCI) is published in the QGIS project for the WCS service:

VERSION

This parameter allows to specify the version of the service to use. Currently, the version values is not internally used and always fallback to 1.1.1.

3.4.2 DescribeCoverage

This request allows to retrieve additional information about coverages like the format of the underlying datasource, the number of bands, ... Standard parameters for the **DescribeCoverage** request according to the OGC WCS 1.1.1 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WCS)
REQUEST	Yes	Name of the request (DescribeCoverage)
VERSION	No	Version of the service
COVERAGE	No	Specify coverage layers (WCS 1.0.0)
IDENTIFIER	No	Specify coverage layers (WCS 1.1.1)

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file

The XML document for a 3 bands GeoTIFF raster layer looks like:

```
<RangeSet>
        <name>Bands</name>
        <label>Bands</label>
        <axisDescription>
          <a href="#">AxisDescription></a>
            <name>bands</name>
            <label>bands</label>
            <values>
               <singleValue>1</singleValue>
               <singleValue>2</singleValue>
               <singleValue>3</singleValue>
            </values>
          </AxisDescription>
        </axisDescription>
      </RangeSet>
    </rangeSet>
    <supportedCRSs>
    </supportedCRSs>
    <supportedFormats nativeFormat="raw binary">
      <formats>GeoTIFF</formats>
    </supportedFormats>
  </CoverageOffering>
</CoverageDescription>
```

COVERAGE

This parameter, defined in WCS 1.0.0, allows to specify the layers to query for additional information. Names have to be separated by a comma.

In addition, QGIS Server introduced an option to select layers by its short name. The short name of a layer may be configured through *Properties* \blacktriangleright *Metadata* in layer menu. If the short name is defined, then it's used by default instead of the layer's name:

```
http://localhost/qgisserver?
SERVICE=WCS
&REQUEST=DescribeCoverage
&COVERAGE=mylayer1name, mylayer2shortname
```

Note: COVERAGE is mandatory if IDENTIFIER is not set.

IDENTIFIER

This parameter replaces the *COVERAGE* parameter in WCS 1.1.1. But QGIS Server does not filter according to the VERSION parameter so IDENTIFIER and COVERAGE have the same effect.

Note: IDENTIFIER is mandatory if COVERAGE is not set. If both IDENTIFIER and COVERAGE parameters are defined, COVERAGE is always used in priority.

3.4.3 GetCoverage

This request allows to retrieve the coverage according to specific constraints like the extent or the CRS. Standard parameters for the **DescribeCoverage** request according to the OGC WCS 1.1.1 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WCS)
REQUEST	Yes	Name of the request (GetCoverage)
VERSION	No	Version of the service
COVERAGE	No	Specify coverage layers (WCS 1.0.0)
IDENTIFIER	No	Specify coverage layers (WCS 1.1.1)
WIDTH	Yes	Width of the response in pixels
HEIGHT	Yes	Height of the response in pixels
BBOX	Yes	Map extent in CRS units
CRS	Yes	Coordinate reference system of the extent
RESPONSE_CRS	No	Coordinate reference system of the response

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file

BBOX

This parameter allows to specify the map extent in the units of the current CRS. Coordinates have to be separated by a comma. The BBOX parameter is formed like minx, miny, maxx, maxy.

URL example:

```
http://localhost/qgisserver?

SERVICE=WCS

&REQUEST=GetCoverage

&IDENTIFIER=T20QPD_20171123T144719_TCI

&BBOX=647533,1805950,660987,1813940

&CRS=EPSG:32620
```

CRS

This parameter allows to indicate the Spatial Reference System of the BBOX parameter and has to be formed like EPSG: XXXX.

RESPONSE_CRS

This parameter allows to indicate the output response Spatial Reference System and has to be formed like EPSG: XXXX. The CRS of the corresponding coverage layer is used by default.

WIDTH

This parameter allows to specify the width in pixels of the output image. The resolution of the response image depends on this value.

HEIGHT

This parameter allows to specify the height in pixels of the output image. The resolution of the response image depends on this value.







Fig. 3.22: From left WIDTH=100&HEIGHT=100

o right:

WIDTH=20&HEIGHT=20,

WIDTH=50&HEIGHT=50,

3.5 Web Map Tile Service (WMTS)

The **1.0.0** WMTS standard implemented in QGIS Server provides a HTTP interface to request tiled map images generated from a QGIS project. A typical WMTS request defined the QGIS project to use, some WMS parameters like layers to render, as well as tile parameters.

Specifications document of the service:

• WMTS 1.0.0

Standard requests provided by QGIS Server:

Request	Description
GetCapabilities	Returns XML metadata with information about the server
GetTile	Returns a tile
GetFeatureInfo	Retrieves data (geometry and values) for a pixel location

3.5.1 GetCapabilities

Standard parameters for the **GetCapabilities** request according to the OGC WMTS 1.0.0 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WMTS)
REQUEST	Yes	Name of the request (GetCapabilities)

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file

URL example:

```
http://localhost/?
SERVICE=WMTS
&REQUEST=GetCapabilities
&MAP=/home/qgis/projects/world.qgs
```

3.5.2 GetTile

Standard parameters for the GetTile request according to the OGC WMTS 1.0.0 specifications:

Parameter	Required	Description
SERVICE	Yes	Name of the service (WMTS)
REQUEST	Yes	Name of the request (GetTile)
LAYER	Yes	Layer identifier
FORMAT	Yes	Output format of the tile
TILEMATRIXSET	Yes	Name of the pyramid
TILEMATRIX	Yes	Meshing
TILEROW	Yes	Row coordinate in the mesh
TILECOL	Yes	Column coordinate in the mesh

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description
MAP	Yes	QGIS project file

URL example:

```
http://localhost/?

SERVICE=WMTS

&REQUEST=GetTile

&MAP=/home/qgis/projects/world.qgs

&LAYER=mylayer

&FORMAT=image/png

&TILEMATRIXSET=EPSG:4326

&TILEROW=0

&TILECOL=0
```

FORMAT

This parameter may be used to specify the format of tile image. Available values are:

- jpg
- jpeg
- image/jpeg
- image/png

If the ${\tt FORMAT}$ parameter is different from one of these values, then the default format PNG is used instead.

TILEMATRIXSET

This parameter defines the CRS to use when computing the underlying pyramid. Format: EPSG:XXXX.

TILEMATRIX

This parameter allows to define the matrix to use for the output tile.

TILEROW

This parameter allows to select the row of the tile to get within the matrix.

TILECOL

This parameter allows to select the column of the tile to get within the matrix.

3.5.3 GetFeatureInfo

Standard parameters for the GetFeatureInfo request according to the OGC WMTS 1.0.0 specification:

Parameter	Required	Description	
SERVICE	Yes	Name of the service (WMTS)	
REQUEST	Yes	Name of the request (GetFeatureInfo)	
LAYER	Yes	Layer identifier	
INFOFORMAT	No	Output format	
I	No	X coordinate of a pixel	
J	No	Y coordinate of a pixel	
TILEMATRIXSET	Yes	Name of the pyramid	
TILEMATRIX	Meshing		
TILEROW	Yes	Row coordinate in the mesh	
TILECOL	Yes	Column coordinate in the mesh	

In addition to the standard ones, QGIS Server supports the following extra parameters:

Parameter	Required	Description		
MAP	Yes	QGIS project file		

URL example:

```
http://localhost/?
SERVICE=WMTS
&REQUEST=GetFeatureInfo
&MAP=/home/qgis/projects/world.qgs
&LAYER=mylayer
&INFOFORMAT=image/html
&I=10
&J=5
```

INFOFORMAT

This parameter allows to define the output format of the result. Available values are:

- text/xml
- text/html
- text/plain
- application/vnd.ogc.gml

The default value is text/plain.

ı

This parameter allows to define the X coordinate of the pixel for which we want to retrieve underlying information.

J

This parameter allows to define the Y coordinate of the pixel for which we want to retrieve underlying information.

3.6 OGC API Features

OGC API Features (OAPIF) is the first implementation of the new generation of OGC protocols. It is described by the OGC API - Features - Part 1: Core document.

Here is a quick informal summary of the most important differences between the well known WFS protocol and OAPIF:

- · OAPIF is based on a REST API
- OAPIF must follow the OPENAPI specifications
- OAPIF supports multiple output formats but it does not dictate any (only GeoJSON and HTML are currently
 available in QGIS OAPIF) and it uses content negotiation to determine which format is to be served to the
 client
- JSON and HTML are first class citizens in OAPIF
- OAPIF is self-documenting (through the /api endpoint)
- OAPIF is fully navigable (through links) and browsable

Important: While the OGC API Features implementation in QGIS can make use of the MAP parameter to specify the project file, no extra query parameters are allowed by the OPENAPI specification. For this reason it is strongly recommended that MAP is not exposed in the URL and the project file is specified in the environment by other means (i.e. setting QGIS_PROJECT_FILE in the environment through a web server rewrite rule).

Note: The **API** endpoint provides comprehensive documentation of all supported parameters and output formats of your service. The following paragraphs will only describe the most important ones.

3.6.1 Resource representation

The implementation of OGC API Features in QGIS Server currently supports the following resource representation (output) formats:

- HTML
- JSON

The format that is actually served will depend on content negotiation, but a specific format can be explicitly requested by appending a format specifier to the endpoints.

Supported format specifier extensions are:

- .json
- .html

Additional format specifier aliases may be defined by specific endpoints:

- .openapi: alias for .json supported by the API endpoint
- .geojson: alias for .json supported by the Features and Feature endpoints

3.6.2 Endpoints

The API provides a list of endpoints that the clients can retrieve. The system is designed in such a way that every response provides a set of links to navigate through all the provided resources.

Endpoints points provided by the QGIS implementation are:

Name	Path	Description
Land-	/	General information about the service and provides links
ing		to all available endpoints
Page		
Confor-	/conformance	Information about the conformance of the service to the
mance		standards
API	/api	Full description of the endpoints provided by the service
		and the returned documents structure
Collec-	/collections	List of all collections (i.e. 'vector layers') provided by the
tions		service
Collec-	/collections/	Information about a collection (name, metadata, extent
tion	{collectionId}	etc.)
Fea-	/collections/	List of the features provided by the collection
tures	{collectionId}/items	
Feature	/collections/	Information about a single feature
	{collectionId}/items/	
	{featureId}	

Landing Page

The main endpoint is the **Landing Page**. From that page it is possible to navigate to all the available service endpoints. The **Landing Page** must provide links to

- the API definition (path /api link relations service-desc and service-doc),
- the Conformance declaration (path /conformance, link relation conformance), and
- the Collections (path /collections, link relation data).

QGIS Server
Available services

• Feature collections
• WFS 3.0 conformance classes
• API definition

powered by QGIS Server

Fig. 3.23: Server OAPIF landing page

API Definition

The **API Definition** is an OPENAPI-compliant description of the API provided by the service. In its HTML representation it is a browsable page where all the endpoints and their response formats are accurately listed and documented. The path of this endpoint is /api.

The API definition provides a comprehensive and authoritative documentation of the service, including all supported parameters and returned formats.

Note: This endpoint is analogue to WFS's GetCapabilities

Collections list

The collections endpoint provides a list of all the collections available in the service. Since the service "serves" a single QGIS project the collections are the vector layers from the current project (if they were published as WFS in the project properties). The path of this endpoint is /collections/.




Fig. 3.24: Server OAPIF collections list page

Collection detail

While the collections endpoint does not provide detailed information about each available collection, that information is available in the /collections/{collectionId} endpoints. Typical information includes the extent, a description, CRSs and other metadata.

The HTML representation also provides a browsable map with the available features.




Fig. 3.25: Server OAPIF collection detail page

Features list

This endpoint provides a list of all features in a collection knowing the collection ID. The path of this endpoint is /collections/{collectionId}/items.

The HTML representation also provides a browsable map with the available features.

Note: This endpoint is analogue to GetFeature in WFS 1 and WFS 2.




Fig. 3.26: Server OAPIF features list page

Feature detail

This endpoint provides all the available information about a single feature, including the feature attributes and its geometry. The path of this endpoint is $/collections/{collectionId}/items/{itemId}$.

The HTML representation also provides a browsable map with the feature geometry.



Fig. 3.27: Server OAPIF feature detail page

3.6.3 Pagination

Pagination of a long list of features is implemented in the OGC API through next and prev links, QGIS server constructs these links by appending limit and offset as query string parameters.

URL example:

http://localhost/qgisserver/oapif/collection_one/items.json?offset=10&limit=10

Note: The maximum acceptable value for limit can be configured with the QGIS_SERVER_API_WFS3_MAX_LIMIT server configuration setting (see: *Environment variables*).

3.6.4 Feature filtering

The features available in a collection can be filtered/searched by specifying one or more filters.

Date and time filter

Collections with date and/or datetime attributes can be filtered by specifying a datetime argument in the query string. By default the first date/datetime field is used for filtering. This behavior can be configured by setting a "Date" or "Time" dimension in the *QGIS Server* > *Dimension* section of the layer properties dialog.

The date and time filtering syntax is fully described in the *API Definition* and also supports ranges (begin and end values are included) in addition to single values.

URL examples:

Returns only the features with date dimension matching 2019-01-01

http://localhost/qgisserver/oapif/collection_one/items.json?datetime=2019-01-01

Returns only the features with datetime dimension matching 2019-01-01T01:01:01

http://localhost/qgisserver/oapif/collection_one/items.json?datetime=2019-01-01T01:01:01

Returns only the features with datetime dimension in the range 2019-01-01T01:01:01 - 2019-01-01T12:00:00

 $\label{localhost/qgisserver/oapif/collection_one/items.json?datetime=2019-01-01T01:01:01/2019-01-01T12:00:00$

Bounding box filter

A bounding box spatial filter can be specified with the bbox parameter:

The order of the comma separated elements is:

- Lower left corner, WGS 84 longitude
- Lower left corner, WGS 84 latitude
- Upper right corner, WGS 84 longitude
- Upper right corner, WGS 84 latitude

Note: The OGC specifications also allow a 6 item bbox specifier where the third and sixth items are the Z components, this is not yet supported by QGIS server.

URL example:

```
http://localhost/qgisserver/oapif/collection_one/items.json?bbox=-180,-90,180,90
```

If the CRS of the bounding box is not WGS 84, a different CRS can be specified by using the optional parameter bbox-crs. The CRS format identifier must be in the OGC URI format:

URL example:

```
http://localhost/qgisserver/oapif/collection_one/items.json?bbox=913191,5606014, 

$\to 913234,5606029 \text{\cond}$bbox-crs=http://www.opengis.net/def/crs/EPSG/9.6.2/3857
```

Attribute filters

Attribute filters can be combined with the bounding box filter and they are in the general form: <attribute name>=<attribute value>. Multiple filters can be combined using the AND operator.

URL example:

filters all features where attribute name equals "my value"

```
\label{local-const-q} $$ $$ $$ http://localhost/qgisserver/oapif/collection_one/items.json?attribute_one=my $$ $$ $$ $$ alue $$
```

Partial matches are also supported by using a * ("star") operator:

URL example:

filters all features where attribute name ends with "value"

http://localhost/qgisserver/oapif/collection_one/items.json?attribute_one=*value

3.6.5 Feature sorting

It is possible to order the result set by field value using the sortby query parameter.

The results are sorted in ascending order by default. To sort the results in descending order, a boolean flag (sortdesc) can be set:

3.6.6 Attribute selection

The feature attributes returned by a *Features list* call can be limited by adding a comma separated list of attribute names in the optional properties query string argument.

URL example:

returns only the name attribute

http://localhost/qgisserver/oapif/collection_one/items.json?properties=name

3.6.7 Customize the HTML pages

The HTML representation uses a set of HTML templates to generate the response. The template is parsed by a template engine called inja. The templates can be customized by overriding them (see: *Template overrides*). The template has access to the same data that are available to the JSON representation and a few additional functions are available to the template:

Custom template functions

- path_append(path): appends a directory path to the current url
- path chomp (n): removes the specified number "n" of directory components from the current url path
- json_dump(): prints the JSON data passed to the template
- static (path): returns the full URL to the specified static path. For example: "static ("/style/black.css")" with a root path "http://localhost/qgisserver/oapif" will return "http://localhost/qgisserver/oapif/static/style/black.css".
- links_filter(links, key, value): Returns filtered links from a link list
- \bullet content_type_name (content_type): Returns a short name from a content type, for example "text/html" will return "HTML"
- nl2br (text): Returns the input text with all newlines replaced by "
br>" tags

Template overrides

Templates and static assets are stored in subdirectories of the QGIS server default API resource directory (/usr/share/qgis/resources/server/api/on a Linux system), the base directory can be customized by changing the environment variable QGIS_SERVER_API_RESOURCES_DIRECTORY.

A typical Linux installation will have the following directory tree:

```
/usr/share/qgis/resources/server/api/
└─ ogc
    ├─ schema.json
       static
        jsonFormatter.min.css
          - jsonFormatter.min.js
         — style.css
       templates
        └─wfs3
            ├─ describeCollection.html
             — describeCollections.html
             — footer.html

    getApiDescription.html

             — getFeature.html

    getFeatures.html

              - getLandingPage.html
              - getRequirementClasses.html
              - header.html
               leaflet_map.html
             — links.html
```

To override the templates you can copy the whole tree to another location and point QGIS_SERVER_API_RESOURCES_DIRECTORY to the new location.

3.6. OGC API Features

FOUR

CATALOG

The QGIS Server Catalog is a simple catalog that shows the list of QGIS projects served by the QGIS Server. It provides a user-friendly fully browsable website with basic mapping capabilities to quickly browse the datasets exposed through those QGIS projects.

The QGIS Server catalog uses the variables QGIS_SERVER_LANDING_PAGE_PROJECTS_DIRECTORIES and QGIS_SERVER_LANDING_PAGE_PROJECTS_PG_CONNECTIONS (see *Environment variables*)




Fig. 4.1: Server Catalog project list page

You can consult the metadata associated to a project and the services that it provides. Links to those services are also given.




Fig. 4.2: Server Catalog, metadata associated to a project and services (links to) that it provides.

By browsing a project, it is listed the dataset that it serves.



Fig. 4.3: Browsing a dataset served by a project in the Server Catalog

Use Right click on a layer to display the attribute table associated to it.




Fig. 4.4: Attribute table associated to a layer

It is possible to consult information of the elements in the map as shown in the image below:

80 Chapter 4. Catalog



Fig. 4.5: Consulting information of a map element

CHAPTER

FIVE

PLUGINS

5.1 List of plugins

Plugins can also be installed on QGIS Server.

Some plugins designed for server can be found on the official QGIS repository.

Install only plugins you need for your own purpose. On QGIS server, plugins are like hooks into QGIS server, they can alter inputs or outputs of QGIS server. They can produce unexpected result if you don't know how the plugin works. Please refer to their respective documentation or the application that needs QGIS server plugins to know which plugin can be useful for you.

5.2 Location of plugins

By default, on Debian based systems, QGIS Server will look for plugins located in /usr/lib/qgis/plugins. The default value is displayed when QGIS Server is starting, in the logs. It's possible to set a custom path by defining the environment variable QGIS_PLUGINPATH in the web server configuration.

5.3 Installation

5.3.1 Manually with a ZIP

As an example, to install the **HelloWorld** plugin for testing the server, using a specific folder, you first have to create a directory to hold server plugins. This will be specified in the virtual host configuration and passed on to the server through an environment variable:

```
mkdir -p /var/www/qgis-server/plugins
cd /var/www/qgis-server/plugins
wget https://github.com/elpaso/qgis-helloserver/archive/master.zip
unzip master.zip
mv qgis-helloserver-master HelloServer
```

Warning: According to its description, HelloServer plugin is designed for development and demonstration purposes. Do not keep this plugin for production if you don't need it.

5.3.2 With a command line tool

If you need to install and regularly upgrade plugins which are stored in the QGIS plugin repository, you may use the QGIS-Plugin-Manager. It's a tool to help you manage plugins from the command line.

The installation is using pip. Installing in a virtual environment is a good practice but not required:

```
pip3 install qgis-plugin-manager
```

To upgrade the tool:

```
pip3 install --upgrade qgis-plugin-manager
```

Then, you can use the qgis-plugin-manager executable from the command line:

```
cd /var/www/qgis-server/plugins
qgis-plugin-manager list
QGIS server version 3.19.0
List all plugins in /var/www/qgis-server/plugins
| Version | Experimental | QGIS_
    _____
|wfsOutputExtension |wfsOutputExtension|1.6.2 |
                                                      13.0 _
→ | | 3Liz
                             1
|qgis_server_render_geojson|GeoJson Renderer |v0.4 |
                                                      |3.4 <u></u>
\hookrightarrow | Matthias Kuhn (OPENGIS.ch)|
                  |Data Plotly |3.7.1
                                                      |3.4 <u></u>
|DataPlotly
→ |3.98 |Matteo Ghetta (Faunalia) |Upgrade to 3.8.1 |
```

We suggest you to read the full documentation in the readme file to know how to install or upgrade plugins with this tool.

5.4 HTTP Server configuration

5.4.1 Apache

To be able to use server plugins, FastCGI needs to know where to look. So, we have to modify the Apache configuration file to indicate the QGIS_PLUGINPATH environment variable to FastCGI:

```
FcgidInitialEnv QGIS_PLUGINPATH "/var/www/qgis-server/plugins"
```

Moreover, a basic HTTP authorization is necessary to play with the HelloWorld plugin previously introduced. So we have to update the Apache configuration file a last time:

```
# Needed for QGIS HelloServer plugin HTTP BASIC auth
<IfModule mod_fcgid.c>
    RewriteEngine on
    RewriteCond %{HTTP:Authorization} .
    RewriteRule .* - [E=HTTP_AUTHORIZATION:%{HTTP:Authorization}]
</IfModule>
```

Then, restart Apache:

systemctl restart apache2

5.5 How to use a plugin

Test the server with the HelloWorld plugin:

```
wget -q -0 - "http://localhost/cgi-bin/qgis_mapserv.fcgi?SERVICE=HELLO"
HelloServer!
```

You can have a look at the default GetCapabilities of the QGIS server at:

 $\label{local-bin-qgis_mapserv.fcgi?SERVICE=WMS&VERSION=1.3.0& $$\hookrightarrow$ REQUEST=GetCapabilities$

ADVANCED CONFIGURATION

6.1 Logging

To log requests sent to the server, you have to set the following environment variable:

• QGIS_SERVER_LOG_STDERR

With the following variables the logging can be further customized:

- QGIS_SERVER_LOG_LEVEL
- QGIS_SERVER_LOG_PROFILE

6.2 Environment variables

You can configure some aspects of QGIS Server by setting environment variables.

According to the HTTP server and how you run QGIS Server, there are several ways to define these variables. This is fully described in *Apache HTTP Server*.

Name		Description	Default	Services	
QGIS_OPTIONS	_PATH	Specifies the path to the directory with	·	All	
		settings. It works the same way as			
		QGIS applicationoptionspath			
		option. It is looking for settings file in			
		<qgis_options_path>/QGIS/</qgis_options_path>			
OCIC DI LICIND	ATH	QGIS3.ini.		A 11	
QGIS_PLUGINPA	AIH	Useful if you are using Python plugins for the server, this sets the folder that is		All	
		searched for Python plugins.			
QGIS_PROJECT	FILE	The .qgs or .qgz project file, normally	·	All	
ZOD_I KOJECI	11.1.	passed as a parameter in the query string			
		(with <i>MAP</i>), you can also set it as an en-			
		vironment variable (for example by using			
		mod_rewrite Apache module).			
		Note that you may also indicate a			
		project stored in PostgreSQL, e.g.			
		postgresql://localhost:5432?			
OOIG GERVER	ADI DECOME	sslmode=disable&dbname=mydb&s			myproject.
QGIS_SERVER_	API_RESOUR	CHESE DIRECTORY all OGC API (such	depends on	WFS	
		as OAPIF/WFS3) static resources (HTML	packaging		
OGIS SEDVED	ADI WEGO N	templates, CSS, JS,) ANALYMENT value for limit in a features	10000	WFS	
QGIS_SERVER_	API_WF35_IV	request.	10000	WLS	
OGIS SERVER	CACHE DIRI	ESPORM's the network cache directory on the	cache in	All	
ZOID_DERVIEK_	.c.rcrit_Diki	filesystem.	profile direc-		
			tory		
QGIS_SERVER	CACHE_ SIZE	Sets the network cache size in MB.	50 MB	All	
		TPININGTan option at the project level to im-	false	WMS	
_	_	prove project read time by disabling loading			
		of layouts.			
		Activating this option disables the QGIS			
		WMS GetPrint request. Set this QGIS			
OCIO CERTITI	IONORE	project flag to not load layouts.	C.1	A 11	
QGIS_SERVER_	IGNORE_BAI	D"BANTERSers are layers that cannot be	false	All	
		loaded. The default behavior of QGIS Server is to consider the project as not avail-			
		able if it contains a bad layer.			
		The default behavior can be overridden by			
		setting this variable to 1 or true. In this			
		case, "bad" layers will just be ignored, and			
		the project will be considered valid and			
		available.			
QGIS_SERVER_	LANDING_PA	OFE RREHIX path component of the landing	4477	All	
		page base URL			
QGIS_SERVER_	LANDING PA	Directories used by the landing page service	"	All	
ZOID_DERVER_		to mid .qgs and .qgz projects	····	A 11	
QGIS_SERVER_	LANDING_PA	randing page service to find projects		All	
OCIC CEDVED		Specify path and filename. Make sure that	·	All	
QGIS_SERVER_	LOO_FILE	server has proper permissions for writing to			
		file. File should be created automatically,			
		just send some requests to server. If it's not			
		there, check permissions.			
	Warning				
	Warning:	ER_LOG_FILE			
	is is				
	dep-				
88	re-	Chapte	r 6. Advanced	configuration	
	cated				
	since				
	QGIS				

6.3 Settings summary

When QGIS Server is starting, you have a summary of all configurable parameters thanks to environment variables. Moreover, the value currently used and the origin is also displayed.

For example with spawn-fcgi:

```
export QGIS_OPTIONS_PATH=/home/user/.local/share/QGIS/QGIS3/profiles/default/
export OGIS SERVER LOG STDERR=1
export QGIS_SERVER_LOG_LEVEL=2
spawn-fcqi -f /usr/lib/cqi-bin/qqis_mapserv.fcqi -s /tmp/qqisserver.sock -U www-

    →data -G www-data -n

QGIS Server Settings:
  - QGIS_OPTIONS_PATH / '' (Override the default path for user configuration): '/
→home/user/.local/share/QGIS/QGIS3/profiles/default/' (read from ENVIRONMENT_
→VARIABLE)
  - QGIS_SERVER_PARALLEL_RENDERING / '/qgis/parallel_rendering' (Activate/
→Deactivate parallel rendering for WMS getMap request): 'true' (read from INI_
\hookrightarrowFILE)
   - QGIS_SERVER_MAX_THREADS / '/qqis/max_threads' (Number of threads to use when_
→parallel rendering is activated): '4' (read from INI_FILE)
   - QGIS_SERVER_LOG_LEVEL / '' (Log level): '2' (read from ENVIRONMENT_VARIABLE)
   - QGIS_SERVER_LOG_STDERR / '' (Activate/Deactivate logging to stderr): '1'_
- QGIS_PROJECT_FILE / '' (QGIS project file): '' (read from DEFAULT_VALUE)
   - MAX_CACHE_LAYERS / '' (Specify the maximum number of cached layers): '100'_
- QGIS_SERVER_CACHE_DIRECTORY / '/cache/directory' (Specify the cache_
→directory): '/root/.local/share/QGIS/QGIS3/profiles/default/cache' (read from_
→DEFAULT_VALUE)
   - QGIS_SERVER_CACHE_SIZE / '/cache/size' (Specify the cache size): '52428800'_
→ (read from INI FILE)
Ini file used to initialize settings: /home/user/.local/share/QGIS/QGIS3/profiles/
→default/QGIS/QGIS3.ini
```

In this particular case, we know that QGIS_SERVER_MAX_THREADS and QGIS_SERVER_PARALLEL_RENDERING values are read from the ini file found in QGIS_OPTIONS_PATH directory (which is defined through an environment variable). The corresponding entries in the ini file are /qgis/max_threads and /qgis/parallel_rendering and their values are true and 4 threads.

6.4 Connection to service file

In order to make apache aware of the PostgreSQL service file (see the pg-service-file section) you need to make your *.conf file look like:

```
SetEnv PGSERVICEFILE /home/web/.pg_service.conf

<Directory "/home/web/apps2/bin/">
   AllowOverride None
.....
```

6.5 Add fonts to your linux server

Keep in mind that you may use QGIS projects that point to fonts that may not exist by default on other machines. This means that if you share the project, it may look different on other machines (if the fonts don't exist on the target machine).

In order to ensure this does not happen you just need to install the missing fonts on the target machine. Doing this on desktop systems is usually trivial (double clicking the fonts).

For linux, if you don't have a desktop environment installed (or you prefer the command line) you need to:

• On Debian based systems:

```
sudo su
mkdir -p /usr/local/share/fonts/truetype/myfonts && cd /usr/local/share/fonts/
→truetype/myfonts

# copy the fonts from their location
cp /fonts_location/* .

chown root *
cd .. && fc-cache -f -v
```

• On Fedora based systems:

```
sudo su
mkdir /usr/share/fonts/myfonts && cd /usr/share/fonts/myfonts

# copy the fonts from their location
cp /fonts_location/* .

chown root *
cd .. && fc-cache -f -v
```

DEVELOPMENT SERVER

A production installation and deployment of QGIS Server usually involves setting up a web server component (e.g. Apache or Nginx) that can forward the HTTP requests coming from the clients to the QGIS Server FastCGI binary application.

If you want to quickly test QGIS Server on your local machine without configuring and installing a full web server stack you can use the QGIS Development Standalone server.

This is an independent application that provides a very simple web server ready to serve your project files.

Warning: The Standalone Development Server has not been developed with the purpose of being used in production, it was not checked for security vulnerabilities or for other stress conditions that normally will occur on a publicly exposed server.

To launch the server:

```
$ qgis_mapserver
```

The default port the Development Server listens to is 8000. Example output:

The server has a few options that can be passed as command line arguments. You can see them all by invoking the server with -h.

(continues on next page)

(continued from previous page)

and the QGIS_PROJECT_FILE environment variable

Arguments:
addressAndPort Listen to address and port (default: "localhost:8000")
address and port can also be specified with the environment variables QGIS_SERVER_ADDRESS and QGIS_SERVER_PORT

CONTAINERIZED DEPLOYMENT

There are many ways to use containerized application, from the most simple (simple Docker images) to sophisticated (Kubernetes and so on).

Note: This kind of deployment needs the docker application to be installed and running. Check this tutorial.

Hint: Docker run pre packaged application (aka images) which can be retrieved as sources (Dockerfile and resources) to build or already built from registries (private or public).

Note: QGIS Debian-Ubuntu package downloads need a valid gpg authentication key. Please refer to the installation pages to update the following Dockerfile.

8.1 Simple docker images

As the docker image does not exist in a public registry. you will need to build it. To do so create a directory qgis-server and within its directory:

• create a file Dockerfile with this content:

```
FROM debian:bullseye-slim
ENV LANG=en_EN.UTF-8
RUN apt-get update \
    && apt-get install --no-install-recommends --no-install-suggests --allow-
→unauthenticated -y \
        gnupg \
        ca-certificates \
        wget \
        locales \
    && localedef -i en_US -f UTF-8 en_US.UTF-8 \
    # Add the current key for package downloading
    # Please refer to QGIS install documentation (https://www.qgis.org/fr/site/
→forusers/alldownloads.html#debian-ubuntu)
    && mkdir -m755 -p /etc/apt/keyrings \
    && wget -0 /etc/apt/keyrings/qgis-archive-keyring.gpg https://download.qgis.
→org/downloads/qgis-archive-keyring.gpg \
    # Add repository for latest version of qgis-server
    # Please refer to QGIS repositories documentation if you want other version_
→ (https://ggis.org/en/site/forusers/alldownloads.html#repositories)
    && echo "deb [signed-by=/etc/apt/keyrings/qgis-archive-keyring.gpg] https://
 →qgis.org/debian bullseye main" | tee /etc/apt/sources.list.d/qgis.li(&&ntihues on next page)
```

(continued from previous page)

```
&& apt-get update \
   && apt-get install --no-install-recommends --no-install-suggests --allow-
→unauthenticated -y \
       qgis-server \
       spawn-fcgi \
       xauth \
       xvfb \
   && apt-get remove --purge -y \
       gnupg \
       wget \
    && rm -rf /var/lib/apt/lists/*
RUN useradd -m qgis
ENV TINI_VERSION v0.19.0
ADD https://github.com/krallin/tini/releases/download/${TINI_VERSION}/tini /tini
RUN chmod +x /tini
ENV QGIS_PREFIX_PATH /usr
ENV QGIS_SERVER_LOG_STDERR 1
ENV QGIS_SERVER_LOG_LEVEL 2
COPY cmd.sh /home/qgis/cmd.sh
RUN chmod -R 777 /home/qgis/cmd.sh
RUN chown qgis:qgis /home/qgis/cmd.sh
USER qgis
WORKDIR /home/qgis
ENTRYPOINT ["/tini", "--"]
CMD ["/home/qgis/cmd.sh"]
```

• create a file cmd. sh with this content:

```
#!/bin/bash
[[ $DEBUG == "1" ]] && env
exec /usr/bin/xvfb-run --auto-servernum --server-num=1 /usr/bin/spawn-fcgi -p 5555_
--n -d /home/qgis -- /usr/lib/cgi-bin/qgis_mapserv.fcgi
```

• build the image with:

```
docker build -f Dockerfile -t qgis-server ./
```

8.1.1 First run

To run the server you will need a QGIS project file. You can use one of yours or pick this sample.

To do so, create a directory data within the directory qgis-server and copy your file in it. To comply with the following explanations, rename it to osm.qgs.

Note: You may need to add advertised URLs under the *QGIS Server* tab of the *Project* ► *Properties* if the Get-Capabilites are broken. For example if your server is exposed on port 8080, you will put this for advertised URL http://localhost:8080/qgis-server/. More information available in section *Configure your project* and subsequent.

Now, you can run the server with:

Options used:

- -d: run in the background
- -rm: remove the container when it is stopped
- -name: name of the container to be created
- -net: (previously created) sub network
- -hostname: container hostname, for later referencing
- -v: local data directory to be mounted in the container
- -p: host/container port mapping
- -e: environment variable to be used in the container

To check, type docker ps | grep qgis-server and you should see a line with qgis-server:

```
CONTAINER ID IMAGE COMMAND CREATED STATUS

→ PORTS NAMES

4de8192da76e qgis-server "/tini -- /home/qgis..." 3 seconds ago Up 2 seconds...

→ 0.0.0.0:5555->5555/tcp qgis-server
```

8.1.2 Usable sample

As the server is only accepting fastcgi connections, you need an HTTP server that handles this protocol. To do so we have to create a simple Nginx configuration file and start a Nginx image.

Create a file nginx.conf in the current directory with this content:

```
server {
  listen 80;
  server_name _;
  location / {
    root /usr/share/nginx/html;
    index index.html index.htm;
  }
  location /qgis-server {
    proxy_buffers 16 16k;
    proxy_buffer_size 16k;
    gzip off;
    include fastcgi_params;
    fastcgi_pass qgis-server:5555;
  }
}
```

And type this command:

To check capabilities availability, type in a browser http://localhost:8080/qgis-server/?SERVICE=WMS& VERSION=1.3.0&REQUEST=GetCapabilities

8.1.3 Cleanup

To cleanup the running images, type:

```
docker stop qgis-server nginx
```

8.2 Docker stacks

The previous method is scriptable, but not easily packageable nor standardized or easily manageable.

To work with a docker image set you could use a docker stack managed by an orchestrator. In a stack, the images are working in the same private network, and you can start / stop the whole stack or deploy the stack to other workers. There are many orchestrators, for example Swarm, Kubernetes and Mesos.

In the following, we will present simple configurations for testing purposes. They are not suitable for production.

8.2.1 Swarm/docker-compose

Docker now has its own orchestrator: Swarm (compatible with docker-compose files). You have to enable it (the Mac version will also work with Linux).

Stack description

Now that you have Swarm working, create the service file (see Deploy to Swarm) qgis-stack.yaml:

```
version: '3.7'
services:
 qgis-server:
    # Should use version with utf-8 locale support:
    image: qgis-server:latest
   volumes:
    - REPLACE_WITH_FULL_PATH/data:/data:ro
   environment:
    - LANG=en_EN.UTF-8
    - QGIS_PROJECT_FILE=/data/osm.qgs
    - QGIS_SERVER_LOG_LEVEL=0 # INFO (log all requests)
    - DEBUG=1
                               # display env before spawning QGIS Server
 nginx:
   image: nginx:1.13
   ports:
    - 8080:80
    volumes:
    - REPLACE_WITH_FULL_PATH/nginx.conf:/etc/nginx/conf.d/default.conf:ro
    depends_on:
    - qgis-server
```

To deploy (or update) the stack, type:

```
docker stack deploy -c qgis-stack.yaml qgis-stack
```

Check the stack deployment status until you obtain 1/1 in the **replicas** column:

```
docker stack services qgis-stack
```

Something like:

ID	NAME	MODE	REPLICAS	_
→ IMAGE	PORTS			
gmx7ewlvwsqt →nginx:1.13	<pre>qgis_nginx *:8080->80/tcp</pre>	replicated	1/1	ш
10v2e7c143u3 →qgis-server:la	qgis_qgis-server test	replicated	1/1	u

To check WMS capabilities, type in a web browser http://localhost:8080/qgis-server/?SERVICE=WMS& VERSION=1.3.0&REQUEST=GetCapabilities

Cleanup

To cleanup, type:

```
docker stack rm qgis-stack
```

8.2.2 Kubernetes

Installation

If you have a **Docker Desktop** installation, using Kubernetes (aka k8s) is pretty straight forward: enable k8s.

If not, follow the minikube tutorial or microk8s for Ubuntu.

As Kubernetes installation can be really complex, we will only focus on aspects used by this demo. For further / deeper information, check the official documentation.

microk8s

microk8s needs extra steps: you have to enable the registry and tag the qgis-server image in order to have Kubernetes to find the created images.

First, enable the registry:

```
microk8s enable dashboard dns registry
```

Then, tag and push the image to your newly created registry:

```
docker tag qgis-server 127.0.0.1:32000/qgis-server && docker push 127.0.0.1:32000/ \hookrightarrowqgis-server
```

Finally, add or complete the /etc/docker/daemon.json to have your registry 127.0.0.1:32000 listed in the insecure-registries field:

```
{
    "insecure-registries": ["127.0.0.1:32000"]
}
```

8.2. Docker stacks 97

Creating manifests

Kubernetes describes the objects to deploy in yaml manifests. There are many different kinds, but we will only use deployments (handle pods, i.e. docker images) and services to expose the deployments to internal or external purposes.

Deployment manifests

Create a file deployments.yaml with this content:

```
apiVersion: apps/v1
kind: Deployment
metadata:
 name: qgis-server
 namespace: default
spec:
  replicas: 1
  selector:
    matchLabels:
     myLabel: qgis-server
  template:
   metadata:
      labels:
       myLabel: qgis-server
    spec:
      containers:
        - name: qgis-server
          image: localhost:32000/qgis-server:latest
          imagePullPolicy: IfNotPresent
          env:
            - name: LANG
              value: en_EN.UTF-8
            - name: QGIS_PROJECT_FILE
              value: /data/osm.qgs
            - name: QGIS_SERVER_LOG_LEVEL
              value: "0"
            - name: DEBUG
              value: "1"
          ports:
            - containerPort: 5555
          volumeMounts:
            - name: qgis-data
              mountPath: /data/
      volumes:
        - name: qgis-data
          hostPath:
            path: REPLACE_WITH_FULL_PATH/data
apiVersion: apps/v1
kind: Deployment
metadata:
  name: qgis-nginx
 namespace: default
  replicas: 1
  selector:
    matchLabels:
     myLabel: qgis-nginx
  template:
    metadata:
```

(continues on next page)

(continued from previous page)

```
labels:
    myLabel: qgis-nginx

spec:
    containers:
    - name: qgis-nginx
        image: nginx:1.13
        ports:
        - containerPort: 80
        volumeMounts:
        - name: nginx-conf
            mountPath: /etc/nginx/conf.d/default.conf

volumes:
        - name: nginx-conf
        hostPath:
        path: REPLACE_WITH_FULL_PATH/nginx.conf
```

Service manifests

Create a file services. yaml with this content:

```
apiVersion: v1
kind: Service
metadata:
  name: qgis-server
  namespace: default
spec:
  type: ClusterIP
  selector:
   myLabel: qgis-server
  ports:
    - port: 5555
      targetPort: 5555
apiVersion: v1
kind: Service
metadata:
  name: qgis-nginx
  namespace: default
  type: NodePort
  selector:
   myLabel: qgis-nginx
  ports:
    - port: 80
      targetPort: 80
      nodePort: 30080
```

Deploying manifests

To deploy the images and services in Kubernetes, one can use the dashboard (click on the + on the upper right) or the command line.

Note: When using the command line with microk8s you will have to prefix each command with microk8s.

To deploy or update your manifests:

8.2. Docker stacks 99

```
kubectl apply -k ./
```

To check what is currently deployed:

```
kubectl get pods, services, deployment
```

You should obtain something like:

NAME pod/qgis-nginx-54845ff6f6-8 pod/qgis-server-75df8ddd89-	-	READ 1/1 1/1	Ι	STATUS Running Running	RE: 0 0	STARTS	AGE 27m 27m		
NAME	TYPE		CLUST	TER-IP		EXTERNA	L-IP	PORT(S)	
→ AGE									
service/Kubernetes	Cluster	ΙP	10.15	52.183.1		<none></none>		443/TCP	
→ 5h51m									
service/qgis-exec-server	Cluster	ΙP	10.15	52.183.2	18	<none></none>		5555/TCP	
→ 35m									
service/qgis-nginx	NodePor	t	10.15	52.183.2	34	<none></none>		80:30080/T	CP_
→ 27m									
service/qgis-server	Cluster	ΙP	10.15	52.183.1	32	<none></none>		5555/TCP	_
NAME	READ'			-DATE	AVAI	LABLE	AGE		
deployment.apps/qgis-nginx	1/1	1	L		1		27m		
deployment.apps/qgis-server	1/1	1	L		1		27m		

To read nginx/qgis logs, type:

```
kubectl logs -f POD_NAME
```

To check WMS capabilities, type in a web browser http://localhost:30080/qgis-server/?SERVICE=WMS& VERSION=1.3.0&REQUEST=GetCapabilities

Cleanup

To clean up, type:

kubectl delete -n default service/qgis-server service/qgis-nginx deployment/qgis- \rightarrow nginx deployment/qgis-server

8.3 Cloud deployment

Managing your own cluster of servers to handle the deployment of containerized applications, is a complex job. You have to handle multiple issues, such as hardware, bandwidth and security at different levels.

Cloud deployment solutions can be a good alternative when you do not want to focus on infrastructure management.

A cloud deployment may use proprietary mechanisms, but they are also compatible with the stages explained previously (*docker images* and *stack management*).

8.3.1 AWS usecase

With Amazon AWS, through ECS (Elastic Container Service) functionalities, you can use docker-compose or Kubernetes compatible wrappers to manage your stack. You will have to create an image registry for your custom images to be accessible.

To use docker-compose alike functionalities, you need to install the **ecs-cli** client and have proper permissions / roles. Then, with the help of the *ecs-cli compose* commands (see the ecs-cli compose manual and ecs-cli tutorial), you can reuse the *stack description*.

To use Kubernetes, you can use the AWS web console or the command line tool eksctl and have the proper permissions / roles. Then with a well configured kubectl environment, you can reuse the *Kubernetes manifests*.

FREQUENTLY ASKED QUESTION

• What are the differences between QGIS Desktop and QGIS Server?

QGIS Desktop has a graphical user interface and allows you to create and modify maps. QGIS Server is a server application serving your QGIS project files to end user applications via OGC web services like WMS, WFS, etc..

• What is OGC?

The OGC (Open Geospatial Consortium) is an international not for profit organization committed to making quality open standards for the global geospatial community.

• Name some other web mapping servers?

ArcGIS server, Geoserver, Mapserver, Mapnik etc.

• How to compare QGIS server to other web mapping servers? (2021/01/01)

Features	QGIS Server	GeoServer	ArcGIS Server
Since	2006	2001	1999
Licence	GPL	GPL	commercial
Commercial support	Multiple companies	Multiple compa-	ESRI and its vendors
		nies	network
Technology	C++/python	Java	C++
Tile cache	yes	yes (via GeoWe-	yes
		bCache)	
3D	No	No	Yes
Querying	FES (2.0) and OGC (1.0) fil-	CQL and OGC	OGC filters
	ters	filters	
Report generation	yes	yes	yes
Server administration	yes via third parties (LizMap,	web + API	web + API REST
	QWC2, etc.)	REST	
GIS project	complete via dedicated GUI	simple via web	complete via dedi-
Layer/symbology edi-		interface	cated GUI
tion			

• What are the OGC specification versions implemented in QGIS server compared to other web mapping servers? (2021/01/01)

OGC standards	QGIS Server	GeoServer	ArcGIS Server
WMS (Web Map Service)	1.3.0 - 1.1.1	1.3.0 - 1.1.1	1.3.0 - 1.1.1
WFS (Web Feature Service)	1.1.0 - 1.0.0	2.0.0 - 1.0.0	2.0.0 - 1.0.0
OAPIF (aka WFS3)	1.0.0	no	no
WMTS (Web Map Tile Service)	1.0.0	1.0.0	1.0.0
WCS (Web Coverage Service)	1.0.0	2.0.1 - 1.0.0	2.0.1 - 1.0.0
WPS (Web Processing Service)	no	1.0.0	1.0.0
CSW (Catalogue Service for the Web)	no	2.0.2	no
SLD (Styled Layer Descriptor)	yes	yes	yes

• What is a tile cache?

Maps are often static. As most mapping clients render WMS (Web Map Service) data every time they are queried, this can result in unnecessary processing and increased wait times.

The tile cache optimizes this experience by saving (caching) map images, or tiles, as they are requested, in effect acting as a proxy between client (such as OpenLayers or Google Maps) and server (any WMS-compliant server). As new maps and tiles are requested, QGIS server intercepts these calls and returns pre-rendered tiles if stored, or calls the QGIs engine to render new tiles as necessary. Thus, once tiles are stored, the speed of map rendering increases by many times, creating a much improved user experience.

• What is PostgreSQL?

PostgreSQL is a powerful, open source object-relational database companion for QGIS.

• What is PostGIS?

PostGIS is a spatial database extender for PostgreSQL object-relational database. It adds support for geographic objects allowing location queries to be run in SQL.

• To be continued...