DashboardLive - Überblick

Gruppen

Einbau unter
<vehicle>
<dashboards>
<groups>
<group .../>
</groups>
</dashboards>
</dashboards>
</vehicle>

		To be implemented w	rithin											
		<vehicle></vehicle>								factor:				
		<dashboard></dashboard>				trailer:				(optional)				
Elemente		<dashboardlive:< td=""><td></td><td></td><td></td><td>Number of</td><td></td><td></td><td></td><td>Number the</td><td></td><td></td><td></td><td></td></dashboardlive:<>				Number of				Number the				
		<dashboard< td=""><td></td><td></td><td></td><td>choosen trailer</td><td>partition:</td><td></td><td></td><td>dashboard's</td><td></td><td></td><td></td><td></td></dashboard<>				choosen trailer	partition:			dashboard's				
		<td>!></td> <td></td> <td></td> <td>or "S" for</td> <td>Number of</td> <td>max:</td> <td>min:</td> <td>value will be</td> <td></td> <td></td> <td></td> <td></td>	!>			or "S" for	Number of	max:	min:	value will be				
						currently	choosen	(optional)	(optional)	multiplied				
					T = .	selected vehicle			Lower limit					In
valueType=	cmd=	option=	joints=	state=	stateText=	trailer=	partition=	max=	min=	factor=	selection=	selectionGroup=	suggested displayTypes	Description
	disconnected connected	all any all any	12n S				1	optional	optional optional	optional optional			VISIBLE, EMITTER VISIBLE, EMITTER	Active if nothing is connected to the given joints Active if something is connected to the given joints
	lifted	all any	12n S					optional optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lifted
	lifting	all any	12n S				1	optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lifting
	lowering	all any	12n S				1	optional	optional	optional			VISIBLE, EMITTER	Active if given joint is linting Active if given joint is lowering
	lowered	all any	12n S				1	optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowered
	lowerable	all any	12n S					optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowerable
	pto	all any	12n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	
	ptoRpm	all any	12n S					optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of PTO's turn rate in relation to the vehicles RPM. Set min, max
														and factor for fine tuning
	foldable folded	all any all anv	12n S					optional optional	optional optional	optional optional			VISIBLE, EMITTER, ANIMATION, SLIDER VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is foldable Active if implement at given joint is folded
	unfolded	all any	12n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	
	folding	all any	12n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	
	unfolding	all I any	12n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is loiding Active if implement at given joint is unfolding
	foldingState	all any	12n S				1	optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current folding process (0 1). Use factor for scaling.
	unfoldingState	all anv	12n S				1	optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current unfolding process (0 1). Use factor for scaling.
	tipping	all I any	12n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is tipping to the ground/trigger
	swath	all any	12n S	1 2 3				optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	
	mpConditioner	all any	12n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if Conditioner is on (requires Maize+)
	seedType	all any	12n S					optional	optional	optional			TEXT	Returns the current set seed type
base														Value of current fillLevel of choosen trailer and partition at given joint.
	fillLevel	abs percent max abskg percentkg	1 2 n S			1n S	1n	optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	abs: absolute value, percent: fillLevel in percent, max: capacity absKg: absolute fill weight, percentkg: percent from max weight,
		maxkg												maxkg: maximum weight
	hasSpec	all any <specname></specname>	12n S					optional	optional	optional			VISIBLE, EMITTER	Active if implement at given joint has the given specialization
	hasTypedesc	all any <typedescname></typedescname>	1 2 n S					optional	optional	optional			VISIBLE, EMITTER	Active if implement at given joint has the given type description
1	tippingState	all any	12n S					optional	optional	optional				Value of current tipping process (01). User factor for scaling.
	ridgeMarker	all any	12n S	1 2 3				optional	optional	optional			VISIBLE, EMITTER	Active if ridgeMarker has given state
	liftState	all any	12n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Value of current lifting state (01). This only makes sense with 3P- Attachers. Use factor for scaling.
	tipSide	all any	1 2 n S	Front Back Left Right BackGrainDoor				optional	optional	optional			VISIBLE, EMITTER	Active if set tipSide equals given tipSide.
	tipSideText	all any	12n S					optional	optional	optional			TEXT	Returns current set tipSide as plain text.
	realClock	all any	12n S					optional	optional	optional			TEXT	Returns real world clock time as plain text.
	heading	all any	12n S					optional	optional	optional			NUMBER, TEXT	Returns current heading in degree
	headingText1	all any	12n S					optional	optional	optional			TEXT	Returns current heading as N, E, S, W.
	headingText2	all any	12n S					optional	optional	optional			TEXT	Returns current heading as N, NE, E, SE, S, SW, W, NW.
	fieldNumber	all any	12n S					optional	optional	optional			NUMBER, TEXT	Returns current field number
	chopper				enabled active			optional	optional	optional			VISIBLE, EMITTER	Active if chopper of combine is active (no swath): enabled: chopper is activated, active: chopper is currently working
	swath				enabled active			optional	optional	optional			VISIBLE, EMITTER	Active if combine is producing straw swathes: enabled: swath is activated, active: swath is currently being produced
combine	filling							optional	optional	optional			VISIBLE, EMITTER	Active if combine's tank is currently filling
COMDINE	hectars							optional	optional	optional			NUMBER, TEXT	Value of worked area
	cutHeight							optional	optional	optional			NUMBER, TEXT	Value of set cutting height
	pipeState			1 2 3				optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if current pipe state equals given state
	pipeFolding							optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if pipe is currently folding or unfolding
	pipeFoldingState			410101				optional	optional	optional				Value of current folding state (01). Use factor for scaling.
	overloading			1 2 3				optional	optional	optional optional			VISIBLE, EMITTER	Active if pipe is currently overloading
	park diff front							optional	optional	optional			VISIBLE, EMITTER	Active if park break is set
	diff_front							optional optional	optional	optional			VISIBLE, EMITTER	Active if front differential is activated Active if back differential is activated
	diff							optional	optional	optional			VISIBLE, EMITTER	Active if back differential is activated Active if front or back differential is activated
	diff awd							optional	optional	optional			VISIBLE, EMITTER	Active if noncor back differential is activated Active if all-wheel-drive is activated
vca	aa							-puona	-puona					, louro il all'illicol allivo lo activatoù

vua	-1:ttIT					ti					VIOIDLE EMITTED	A still if a discuss and of fount and in a still stand
	diff_awdF					optional	optional	optional			VISIBLE, EMITTER	Active if advance speed of front axle is activated
	KS					optional	optional	optional			VISIBLE, EMITTER	Active if "Keep Speed" is activated
	slip					optional	optional	optional			NUMBER, TEXT	Value of current slip (requires VCA or REA GUI)
	speed2					optional	optional	optional			NUMBER, TEXT	Value of second speed control
	speed3					optional	optional	optional			NUMBER, TEXT	Value of third speed control
hlm						optional	optional	optional			VISIBLE, EMITTER	Active if Headland Managament is turned on
	field					optional	optional	optional			VISIBLE, EMITTER	Active if Headland Management is currently in field mode
	headland					optional	optional	optional			VISIBLE, EMITTER	Active if Headland Management is currently in headland mode
	contour					optional	optional	optional			VISIBLE, EMITTER	Active if Headland Management is currently in field mode and contour quidance is activated
		on				optional	optional	optional			VISIBLE EMITTER ANIMATION SLIDER	Active if GPS is turned on (Guidance Steering/GS or VCA)
gps		active				optional	optional	optional			VISIBLE, EMITTER	Active if GPS is currently active (GS or VCA)
		lane+				optional	optional	optional			VISIBLE, EMITTER	Active if current GPS-Lane is bigger than 0 (GS only)
		lane-				optional	optional	optional			VISIBLE, EMITTER	Active if current GPS-Lane is smaller than 0 (GS only)
		iario				optional	optional	optional			NUMBER, TEXT	Value of current GPS-Lane (GS only)
						Ориона	ориона	ориона			- /	Value of necessary course correction (-0.5+0.5, GS only). Use factor
		delta				optional	optional	optional			ALL	for scaling.
gpsLane		dir				optional	optional	optional			ANIMATION	Direction of course correction (-1: left, +1: right, GS only.
		dirLeft				optional	optional	optional			ALL	Active if direction of necessary course correction is left
		dirRight				optional	optional	optional			ALL	Active if direction of necessary course correction is right
		headingDelta				optional	optional	optional			ALL	Value of heading delta to gps course (GS or VCA)
gpsWidth						optional	optional	optional			NUMBER, TEXT	Value of currently set gps width
		mode				optional	optional	optional			TEXT	Value of ProSeed's mode in plain text
		mode		auto semi manual		optional	optional	optional			VISIBLE, EMITTER	Active if proSeed's mode equals given state
		distance		manuai		optional	optional	optional			NUMBER, TEXT	Value of tramLine distance
		laneDrive				optional	optional	optional			NUMBER, TEXT	Value of currently set lane
		laneFull				optional	optional	optional			NUMBER, TEXT	Number of lanes set
		tram				optional	optional	optional			VISIBLE, EMITTER	Active if tramLines are created
proSeed		fert				optional	optional	optional			VISIBLE, EMITTER	Active if fertilizer is enabled
prooced		areaWork				optional	optional	optional			NUMBER. TEXT	
		areaField				optional	optional	optional			NUMBER, TEXT	Value of worked area Value of field size
		timeUse				optional	optional	optional			NUMBER, TEXT	
		seedUse									NUMBER, TEXT	Value of hectars per hour
				410101		optional	optional	optional				Value of seed use
		segment		1 2 3		optional	optional	optional			VISIBLE, EMITTER	Active if segment choosen in state is enabled
		tramType				optional	optional	optional			VISIBLE, EMITTER	Active if premarked tramlines are created
		audio				optional	optional	optional			VISIBLE, EMITTER	Active if proSeed's audio signals are enabled
selection						optional	optional	optional	-2 -1 0 1 2		VISIBLE, EMITTER	Active if currently selected vehicle/implement equals given selection
						optional	optional	optional		-2 -1 0 1 2	VISIBLE, EMITTER	Active if currently selected group equals given selectionGroup
		all any selected current	1 2 n S			optional	optional	optional			VISIBLE, EMITTER	Active if bale is a round bale selected: baler setting, current: current bale
	baleSize	all any selected current	1 2 n S			optional	optional	optional			NUMBER, TEXT	Value of current bale size selected: baler setting, current: current bale
baler	baleCountAnz	all any	1 2 n S			optional	optional	optional			NUMBER, TEXT	Current value of processed bales (requires Ifko's baleCounter Mod or Göweill DLC or Vermeer DLC)
	baleCountTotal	all any	1 2 n S			optional	optional	optional			NUMBER, TEXT	Total value of processed bales (requires Ifko's baleCounter Mod or Göweill DLC or Vermeer DLC)
	wrappedBaleCountAnz	all I any	12n S			optional	optional	optional			NUMBER, TEXT	Current value of wrapped bales (requires Ifko's baleCounter Mod)
	wrappedBaleCountTotal		12n S			optional	optional	optional			NUMBER, TEXT	Total value of wrapped bales (requires lfko's baleCounter Mod)
lockSteeringAxle	mapped balcoount Total	un i uliy				optional	ориони	Spiionai			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if steering axle lock is activated (requires lifkos lockSteeringAxle mod)
	tonPerHour										NUMBER, TEXT	Value of currently processed tons per hour
											NUMBER, TEXT	
combineXP	engineLoad										NUMBER, TEXT	Value of engine load
	yield											Value of current yield
	highMoisture										VISIBLE, EMITTER, ANIMATION, SLIDER	
frontLoader		all any	12n S			optional	optional	optional			NUMBER, TEXT	Value of tool's rotation
	toolRotation	all any	12n S		origin	optional	optional	optional			NUMBER, TEXT	Value of tool's rotation normalized
		all any	12n S			optional	optional	optional				Active if tool's rotation is between min and max
		all any	12 n S		origin	optional	optional	optional				Active if tool's normalized rotation is between min and max
print	<text></text>										TEXT	Prints value of <cmd></cmd>