

1 Configuration of Uploads

Summary

Configuration of Uploads to SAP CO

SAP CO has been designed as dynamically as possible to be able to meet the different requirements and situations. The table SAP_RCK_DATA_CONF is used for configurations. Parameters, program parameters and field parameters are defined in this table.

Parameters:

Statistical values required for the generation of the IDoc can be defined using these parameters (e.g. the company code).

Program parameters

Program parameters control program processing. These parameters can be used, for example, to define that only orders of a specific HYDRA order type are uploaded/confirmed.

Field parameters:

Field parameters define from which HYDRA data model fields values relevant for the upload are taken. Moreover, for certain field parameters it is possible to define in which length and as of which position these values are to be taken.

All parameters are saved as variant. This means that the upload program is called up with the corresponding message type and the variant and the settings defined in this variant are used for the upload.

Please note: Important: When calling the program MYERPRCK to generate upload records, the variant is to be sent as well so that this variant will be forwarded as parameter to the user exit.

e.g. sh.exe ./myerprck.scr /MESTYP=ACC_ACT_ALLOC /KAT=GK /UE_PARAMS="VARIANTE=SAP"

Parameters

Key type	Parameter	Description	Values
P	CO_AREA	The content of this field of the segment E1BPDOCHDRP000 of the upload IDoc is transferred to the field CO_AREA. It includes the SAP controlling area.	e.g. 1000

Key type	Parameter	Description	Values
P	VERSION	The content of this field of the segment E1BPDOCHDRP000 of the upload IDoc is transferred to the field VERSION.	e.g. 000
P	VARIANT	The content of this field of the segment E1BPDOCHDRP000 of the upload IDoc is transferred to the field VARIANT. It includes the specific upload variant in SAP.	e.g. SAP02
P	ACTIVITYUN	Determines the upload unit	SEK second MIN minute M minute STD hour (Default) H hour

Program parameter overview

Key type	Parameter	Description	Values
PP	NOSAP	If this parameter is set only orders will be uploaded that are not known in SAP	-
PP	ONLYSAP	If this parameter is set only orders will be uploaded that are not known in SAP. →default setting	-
PP	LOGSYS	The logical system specified here determines the communication user from the configuration tables of the HYDRA mySAP communication. This user is also entered as the user of data records in SAP.	Logical system of the mySAP communication
PP	MAX_SEG	Maximum number of segments summarized for the upload.	Default 100
PP	USERNAME	User name who is specified as generating user in the data record structure. If no user is specified the communication user indicated in LOGSYS of the logical system is determined and used as the user.	

Field parameters

Key type	Parameter	Description	Values
F	SEND_CCTR	Sending cost center	MNR.KST: cost center of the workplace ADEPRO.ANR: HYDRA order indicating the position from / to PNR.KST: The employee's cost center

Key type	Parameter	Description	Values
F	ACTTYPE	Activity type	ADEPRO.ANR: HYDRA order number indicating the position from / to PNR.INFOTEXT:1 The employee's activity type from the HR master
F	ACTVTY_QTY	Quantity of the activity type	ADEPRO.EGR:PDAUER: Duration of the B record posting
F	REC_CCTR	Receiving cost center	ADEPRO.ANR: HYDRA order number specifying the position from / to
F	REC_ORDER	Receiving order	AGNR.SAPAUNR: SAP order number of the CO internal order
F	PERSON_NO	Personnel number	ADEPRO.PNR: HYDRA personnel number

Structure of the table SAP_RCK_DATA_CONF

The below table includes the configurations for the upload/confirmation to SAP CO. At the moment, the table can only be edited directly in the database.

Field name	T	L	Meaning	Meaning in HYDRA
KEY_TYPE	Char	2	Key type	Parameter type: „P“ Parameter „PP“ Program parameter „F“ Field parameter
KEY	Char	30	Key	Parameter name, e.g. SEND_CCTR, ONLYSAP
SUBKEY	Char	40	Variant	Variant name by which a configuration is saved and the upload program is started (free text).
MESTYP	Char	30	Message type	Name of the SAP message type
POS_VON	Num		Position from	Field position from which the value is to be taken. If nothing is entered the entire field will be taken over.
POS_BIS	Num		Position to	Field position up to which the value is to be taken. If nothing is entered the entire field will be taken over.
LFD_NR	Num		Consecutive number	Not relevant

Field name	T	L	Meaning	Meaning in HYDRA
VERWEIS	Num		Reference	Unique reference (assigned by the database).
BEARB	Char	10	Editor	Not used
BEARB_DATE	Date		Editing date	Not used
BEARB_TIME	Time		Editing time	Not used
ANLAGE_DATE	Date		Creation date	Not used
ANLAGE_ZEIT	Time		Creation time	Not used
PARAM_STR1	Char	20	Parameter 1	Not used
PARAM_STR2	Char	20	Parameter 2	Not used
PARAM_STR3	Char	40	Parameter 3	Not used
PARAM01	Num		Parameter integer	Not used
PARAM02	Num		Parameter integer	Not used
PARAM01_d	Dec	18,6	Parameter decimal	Not used