

1 Passing on Batch Attributes

Usage

You use the "pass batch attributes on" function if attributes of input batches are to be transferred to the generated output batch when changing the output batch.

Prerequisites /restrictions

- Mixing up the two methods of passing on (in the background on the server) and manual collection at the terminal is **excluded**. Therefore, server processing checks if the option "Capture attribute while generating batch" is set for the batch attributes to be passed on:
 - Yes – "Capture attribute while generating batch" is set
 - Manual collection takes priority - the attribute will not be passed on.
 - No - "Capture attribute while generating batch":
 - The attribute will be passed on.
- The transfer is performed based on the currently registered input batches upon completion of the output batch. Provided that attributes were recorded manually beforehand, they will be overwritten. It is not possible to pass on several input batches changed while the output batch was running and/or only data of the last input batch is passed on.
- It is not possible to pass on attributes from the level of subordinate batches to the level of merged batches.
- If for a material for which inheritance rules apply several items exist in the component list of an OP, the value of the batch with the lower BOM item will be used (i.e. "0010" prior to "0040").

Procedure

The different initial scenarios have to be taken into account for passing on batch attributes. There are the following options:


- Inheritance/transfer for simple batches
- Pass on simple batches/merged batches and their subordinate batches to merged batches and their subordinate batches when collecting serial numbers
- Pass on merged batches to merged batches when merging serial numbers

Data/results/inspections

- If the advanced object configuration includes an inheritance rule for the material of the input batch:
 - the inheritance rule BATCH_TO_BATCH transfers the value of the specified attribute from the input batch to the output batch.


- the inheritance rule CHILD_BATCH_TO_CHILD_BATCH transfers the value of the specified attribute from the subordinate batch of the input batch to the generated subordinate batch of the output batch.
- the inheritance rule BATCH_TO_CHILD_BATCH transfers the value of the specified attribute from the registered batch, for merged batches from the superordinate batch level, to the subordinate batch of the generated output batch.

Inheritance/transfer for "simple" batches



Attributes are passed on from all input batches to the output batch. The value from the first input batch will be used if an attribute is configured several times.

Inheritance/transfer for simple batches/merged batches to merged batches




The inheritance is performed as follows:

- Attributes are passed on from the simple input batch to the output merged batch.
- Attributes are passed on from the simple input batch to the subordinate batches of the output merged batch.
- Attributes are passed on from the input merged batch to the output merged batch.
- Attributes are passed on from the input merged batch to the subordinate batches of the output merged batch.
- Attributes are passed on from the subordinate batches of the input merged batch to the subordinate batches of the output merged batch.

The value from the first input batch is used if an attribute is configured several times.

Inheritance/transfer for merged batches to merged batches when merging serial numbers



The inheritance is performed as follows:

- Attributes are passed on from the input merged batch to the output merged batch.
- Attributes are passed on from the input merged batch to the subordinate batches of the output merged batch.
- Attributes are passed on from the subordinate batches of input merged batches to the subordinate batches of output merged batches.

The value from the first input batch is used if an attribute is configured several times.