

1 Settings Relevant to the Application in HYDRA

Maintenance of the distribution model - HYDRA inbound processing

Use the [HYDRA distribution model](#) to maintain entries for HYDRA inbound processing:

Parameter name	Value
To process material staging/material supply	
Message type	ZMBEW
Priority	None
Command	mle72imp.scr
Command parameter	/VARIANTE=< MLE variant to be used
Description	Material staging ERP → HYDRA
Log. target system	Created logical system
Storage duration	10



Please restart HYDRA after editing entries.

Maintenance of the distribution model - HYDRA outbound processing

Use the [HYDRA distribution model](#) to maintain entries for HYDRA outbound processing:

Parameter name	Value
To upload material withdrawals (consumptions):	
Message type	ZWAU
Description	Upload material withdrawals

Parameter name	Value
IDoc type	ZWAU
Storage duration	10
Log. target system	Created logical system
Segment name 1	Z2WAU000X000
To upload incoming materials:	
Message type	ZWEI
Description	Upload incoming materials
IDoc type	ZWEI02
Storage duration	10
Log. target system	Created logical system
Segment name 1	Z2WEI000X000
To upload the usage decision	
Message type	ZCNRVEW
Description	Upload of the usage decision
IDoc type	ZCNRVEW02
Storage duration	10
Log. target system	Created logical system
Segment name 1	Z2CNRVEW000X000

Scheduler maintenance

The following entries must be made for confirmations/uploads of goods movements in the [Scheduler](#):

Parameter name	Value
----------------	-------

Parameter name	Value
To upload incoming materials:	
Product key	MPL-BP
License key	MPL-BP
Command (Windows):	sh.exe ./myerprck.scr /MESTYP=ZWEI
Command (Unix):	./myerprck.scr /MESTYP=ZWEI
Comment:	Goods receipt HYDRA → ERP
Interval	5
To upload material consumptions:	
Product key	MPL-BP
License key	MPL-BP
Command (Windows):	sh.exe ./myerprck.scr /MESTYP=ZWAU
Command (Unix):	./myerprck.scr /MESTYP=ZWAU
Comment:	Goods issue HYDRA → ERP
Interval	5
To upload the usage decision:	
Product key	MPL-BP
License key	MPL-BP
Command (Windows):	sh.exe ./myerprck.scr /MESTYP=ZCNRVIEW
Command (Unix):	./myerprck.scr /MESTYP=ZCNRVIEW
Comment:	Usage decision HYDRA → ERP
Interval	5
To upload incoming material:	

Parameter name	Value
Product key	MPL-BP
License key	MPL-BP
Command (Windows):	sh.exe ./hysapupl.scr /UPLSEGNAM=Z2WEI000X000 /SINGLE_IDOC /SUBLEVEL=2
Command (Unix):	./hysapupl.scr /UPLSEGNAM=Z2WEI000X000 /SINGLE_IDOC /SUBLEVEL=2
Comment:	Upload of incoming goods HYDRA → ERP
Interval	5
To upload outgoing material:	
Product key	MPL-BP
License key	MPL-BP
Command (Windows):	sh.exe ./hysapupl.scr /UPLSEGNAM=Z2WAU000X000
Command (Unix):	./hysapupl.scr /UPLSEGNAM=Z2WAU000X000
Comment:	Upload goods issues HYDRA → ERP
Interval	5
To upload the usage decision	
Product key	MPL-BP
License key	MPL-BP
Command (Windows):	sh.exe ./hysapupl.scr /UPLSEGNAM=Z2CNRVIEW000X000
Command (Unix):	./hysapupl.scr /UPLSEGNAM=Z2CNRVIEW000X000

Parameter name	Value
Comment:	Upload goods issues HYDRA → ERP
Interval	5

Activation in material type

Set the indicator *Goods movements > Transfer to interface* for the [material types](#), for which a transfer of the material movements is necessary.

In case the HYDRA material type is not available as application, the indicator can also be set directly via the database:



```
update hz_typen set we_ext_kz = ,J' where hz_typ = '<Material type for which the indicator is to be set>';
```

INI-Configuration for segment Z2CNR_USRFLD000X000

Provided with version 1.8 of the script *mle_rckmestyp_zwei_out.hsc* there is the option to transfer/upload the user fields of a batch as well. The transfer/upload has to be activated explicitly in the [HYDRA INI configuration](#).

Parameter name	Value
INI name	MCL
Section	ZWEI
Key	USERFIELDS
Value	J / Y Transfer of the user field segment
Active	Ja (yes)
Comment	Transfer of the segment Z2CNR_USRFLD000X000

INI configuration for the segment Z2CNRATT_N001X000

Provided with version 1.72946 of the script *mle_rckmestyp_zwei_out.hsc* there is the option to use Z2CNRATT_N001X000 to upload numeric batch attributes. Depending on the product version in use, the segment has to be activated manually in [HYDRA INI configuration](#):

MPL/TRT 8.1	MPL/TRT 8.2
Uploads via segment Z2CNRATT_N001X000 must be enabled manually.	For new installations after SP7/2015 the segment is used by default. For installations prior to that date the segment has to be enabled manually.

The transfer/upload has to be activated explicitly in the [HYDRA INI configuration](#).

Parameter name	Value
INI name	MCL
Section	ZWEI
Key	CNRATTR_DEC_13_3
Value	J / Y Transfer of the segment Z2CNRATT_N001X000
Active	Ja (yes)
Comment	Transfer of the segment Z2CNRATT_N001X000