

1 Configuration of Separating/Rebuilding Serial Numbers

Dialog configuration

Define the AIP function key in the file *ctaipbut.ini*:

```
[ANR-LN-Page2]

...

1=A_SNR_D,L,SNR trennen, SNR_trennen.png
```

The below-mentioned sections are required in the layout configuration of *ctaisplay.ini*:

```
[A_SNR_D_GRID.LST ]
GRID_FONT=Arial
GRID_FONTSIZE=9
GRID_COLOR=clBlack
GRID_BACKGROUND=clWhite
GRID_ORDER=

DLL=C20,110,L,SNR
ALIAS LEER2=(DUMMY1)=C1,10,L
CNR=C20,0,L,CNR
ALIAS LEER3=(DUMMY2)=C1,40,L
SAPCNR=C20,110,L,Charge
ALIAS LEER4=(DUMMY3)=C1,10,L
ATK=C20,110,L,Material

[WF@DOC_DATA_D]
FILTER=
SECTION=DOC_DATA_D.LST
DATAFIELDS=
FILE=doc_data_d.lst
AUTOFILTERCOL=
MODE=DATALOCKUNTILSHOW=TRUE|

[DOC_DATA_D.LST]
GRID_FONT=Arial
GRID_FONTSIZE=9
GRID_COLOR=clBlack
GRID_BACKGROUND=clWhite
GRID_ORDER=

LINK=C20,400,L,link/document

[WF@ATTR_DATA_D]
SECTION=ATTR_DATA_D.LST
DATAFIELDS=
FILE=attr_data_d.lst
AUTOFILTERCOL=
MODE=DATALOCKUNTILSHOW=TRUE|
```

```
[ATTR_DATA_D.LST]
GRID_FONT=Arial
GRID_FONTSIZE=9
GRID_COLOR=clBlack
GRID_BACKGROUND=clWhite
GRID_ORDER=
```

```
ATTR=C20,100,L,Attribute
VALUE=C20,80,L,Value
EINH=C20,60,L,Unit
TEXT=C20,200,L,Text
```

System configuration

Collection of batch attributes

If you want to enter batch attributes manually when collecting serial numbers, create the [batch attributes](#) to be recorded in the system in relation to the [material type](#) of the ready-mounted serial number. To do so, maintain at least these configurations:

Parameter name	Value
Options → Capture attribute while generating batch	Enable the option.
Options → Position	Specify the position - the system sorts the configured attributes in an ascending numeric order (bottom up).
Data type	Maintain the data type and length of the attribute to be recorded

Control the generation of goods movements

Define for incorporated merged batches, serials numbers and produced serial numbers if you require goods movements subject to uploads to be provided. To do so, configure the following in [advanced object configuration](#):



The goods movement option has to be enabled for the relevant material type to be able to use this configuration.

Parameter name	Value
----------------	-------

Configuration for goods issues (consumptions)	
Object type	MPL
Object ID 1	SNR - serial number SAM - merged batch
Object ID 2	MATTYP
Object ID 3	Material type the entry applies for
Object ID 4	CMM_A
Parameter	CREATE_MOVEMENT
Parameter value	Y
Configuration for goods receipts (generated material)	
Object type	MPL
Object ID 1	SNR - serial number SAM - merged batch
Object ID 2	MATTYP
Object ID 3	Material type the entry applies for
Object ID 4	CMM_E
Parameter	CREATE_MOVEMENT
Parameter value	Y