

DataSync Pro - Technical Setup Guide

Anthrasync Internal Knowledge Base — Confidential

1. Installation (Self-Hosted)

Pull the official Docker image and start the stack using the provided docker-compose file. Run `docker compose up -d` from the installation directory. The application will be available on port 8080 by default. Configuration is read from the `.env` file in the same directory.

2. Initial Configuration

On first launch, navigate to the application URL and complete the setup wizard. You will create an administrator account, configure the metadata database connection, and set the encryption key. The encryption key must be at least 32 characters and cannot be changed after setup.

3. API Authentication

The REST API uses bearer-token authentication. Generate an API token from Settings > API Tokens. Include the token in the Authorization header as `Authorization: Bearer <token>`. Tokens can be scoped to read-only or read-write access and expire after 90 days unless renewed.

4. Rate Limits

The API allows 100 requests per minute per token on the Growth edition and 1,000 requests per minute on the Enterprise edition. Requests that exceed the limit receive an HTTP 429 response with a Retry-After header.

5. Troubleshooting

Pipeline stuck in 'queued' state: Verify that at least one worker container is running and that the worker can reach the metadata database. Restart the worker with `docker compose restart worker`.

Connection timeouts to a source: Confirm that the source host allows inbound connections from the DataSync Pro server IP and that credentials have not expired. Increase the connection timeout under the source's advanced settings if the source is slow to respond.

Recovering from a failed upgrade: Restore the metadata database from the automatic pre-upgrade backup located in the backups volume, then redeploy the previous image tag.