

Service now - ITOM

Connection parameters

Connection parameters

glide.mid.fast.responses

Instructs the MID Server to try sending messages to the instance as soon as they are ready. Normally the MID Servers send messages to the ServiceNow instance serially (that is, one message at a time). Since many probes can be run in parallel, there can be multiple messages transmitted simultaneously to the instance. Setting this parameter to true may decrease the time between a probe's completion and its response arriving at the instance. However, the multiple simultaneous messages consume resources, decreasing the overall instance responsiveness. If there are communications problems, this parameter's value can also cause a logjam on the MID Server, as threads normally used for running probes may become consumed for sending messages. Generally, leave this parameter out of your configuration. Setting it to true is meaningful only under very special circumstances.

Type: true | false

Default value: false

<

≡

MID Server ConfigurationParameter

Created 2023-03-25 10:41:00

🔗

🔍

⋮

Update

Delete

↑

↓

Parameter name

glide.mid.fast.responses (MID Server immediate response enable. Default: false)

▼

Domain

global

🔍

ⓘ

* MID server

MIDServer3

🔍

ⓘ

Value

true

Update

Delete

ⓘ

glide.mid.max.sender.queue.size: Places an upper limit on how large the queue is allowed to get. The MID Server starts deleting queued messages if this limit is exceeded. When the MID Server generates messages to the ServiceNow instance faster than it can send them, it queues them temporarily on the file system of the MID Server's host. This queue is normally quite small, and is completely emptied as soon as the MID Server processing slows for a short period. However, this queue can grow in size when there are communication problems between the MID Server and the instance, and especially if there is an integration running on the MID Server.

The parameter is of the form {number} {multiplier}, where {number} is any positive decimal number including non-integers, and the optional multiplier is any spelling of bytes, kilobytes, megabytes, gigabytes, or terabytes (only the first character is tested, and the test is case-insensitive). The default multiplier is bytes. White space is liberally tolerated. The following strings all represent valid parameters: "1000000000", "0.5m", "5 GB", "7.67gigas", "145.69392 meg", and "1.1 terra".

Type: string

Default value: 0.5 GB

Default value: yyyy-MM-dd HH:mm:ss

3

mid.disable_amb

Disables the Asynchronous Message Bus (AMB) Client. When AMB is enabled, the MID Server uses a default polling interval of 40 seconds. When the AMB client is disabled, the default polling interval switches to 5 seconds. If you set a polling interval with the mid.poll.time parameter, the MID Server uses that value whether or not the AMB client is enabled.

Type: true | false

Default value: false

<

≡

MID Server Configuration Parameter

Created 2023-03-28 18:59:28

🔗

⚙️

⋮

Update

Delete

↑

↓

Parameter name

mid.disable_amb (Disable the AMB Client on the MID Server. Default: false.)

▼

Domain

global

🔍

ℹ️

* MID server

MIDServer3

🔍

ℹ️

Value

true

Update

Delete

ℹ️

mid.https.truststore.password

Sets the trustStore password that is required for HTTPS connections with the Asynchronous Message Bus (AMB) Client.

Type: string

Default value: none

<

≡

MID Server Configuration Parameter

Created 2023-03-28 19:03:15

🔗

⚙️

⋮

Update

Delete

↑

↓

Parameter name

mid.https.truststore.password (Truststore password. Required for https connections)

▼

Domain

global

🔍

ℹ️

* MID server

MIDServer3

🔍

ℹ️

Value

123

Update

Delete

ℹ️

mid.https.truststore.path

Path to the trustStore to be used by the MID Server for TLS transactions (Asynchronous Message Bus (AMB) Client). Add this parameter only if you want to change the default path.

Type: string

Default: Path to the JRE trustStore bundled with the MID Server

<

≡

MID Server Configuration Parameter

Created 2023-03-29 06:42:46

🔗

⚙️

⋮

Update

Delete

Parameter name

mid.https.truststore.path (Path to the truststore to be used by the MID server for TLS transactions. Default: the JRE truststore bundled w

Domain

global

🔍

📘

* MID server

MIDServer3

🔍

📘

Value

Update

Delete

📘

mid.instance.skip_basic_auth

Allows the MID Server to connect to an instance using cookies instead of basic authentication credentials. When set to true, it uses cookies first. However, if the connection fails, the MID Server will try to connect again using basic authentication credentials.

Type: true | false

Default value: true

<

≡

MID Server Configuration Parameter

Created 2023-03-29 06:48:07

🔗

⚙️

⋮

Update

Delete

Parameter name

mid.instance.skip_basic_auth (MID will try to connect to instance using cookies instead of basic auth credential. Default: true)

Domain

global

🔍

📘

* MID server

MIDServer3

🔍

📘

Value

true

Update

Delete

📘

mid.jmx.enabled

Enables a JMX server on the MID Server, which exposes some management information to JMX consoles. Implementing JMX requires additional configuration of the Java runtime environment. Setting this parameter to true is only recommended for those with detailed knowledge of the Java security architecture and a specific need for JMX.

Type: true | false

Default value: false

The screenshot shows the configuration interface for the parameter `mid.jmx.enabled`. At the top, it says "MID Server Configuration Parameter" and "Created 2023-03-29 09:20:33". There are icons for edit, refresh, and a menu, along with "Update" and "Delete" buttons. The "Parameter name" dropdown is set to `mid.jmx.enabled (MID Server JMX enable. Default: false)`. The "Domain" is set to `global` and the "MID server" is set to `MIDServer3`. The "Value" is set to `true`. At the bottom, there are "Update" and "Delete" buttons and a help icon.

mid.poll.time

Sets the default MID Server polling interval (in seconds). The polling interval is the amount of time the MID Server waits before checking the ECC queue for work when the ECC queue is not busy. The MID Server polls the ECC queue using this interval if the AMB client connection is dropped.

Note: The default polling interval resets to 5 seconds when the AMB client is disabled. If you configure the `mid.poll.time` parameter, the MID Server uses this polling interval whether or not the AMB client is connected.

Type: integer (seconds)

Default value: 40

The screenshot shows the configuration interface for the parameter `mid.poll.time`. At the top, it says "MID Server Configuration Parameter" and "Created 2023-03-29 09:21:41". There are icons for edit, refresh, and a menu, along with "Update" and "Delete" buttons. The "Parameter name" dropdown is set to `mid.poll.time (MID Server poll time in seconds when MID server is not busy. Default: 40)`. The "Domain" is set to `global` and the "MID server" is set to `MIDServer3`. The "Value" is set to `50`. At the bottom, there are "Update" and "Delete" buttons and a help icon.

mid.probe.wait.resources

Indicates whether probe execution is delayed until resources are available. Used to enable MID Server Resource Reservation.

Note: Requires MID Server restart.

Type: true | false

Default value: true

<

≡

MID Server Configuration Parameter

Created 2023-03-29 09:24:59

✎

⚙

⋮

Update

Delete

Parameter name

mid.probe.wait.resources (Whether probe execution will be delayed until resources are available. Requires restart. Default: true) ▼

Domain

global

🔍

📘

* MID server

MIDServer3

🔍

📘

Value

true

Update

Delete

📘

mid.property.long_runner

Identifies the name of a script include that manages long running commands.

Note: **This property is applicable till the Rome version only.** If your instance is of a later version, you must configure the system property, glide.eccprobe.longrunner.class.

Type: string

Default value: LongRunner

threads.interactive.max

Sets the maximum number of interactive worker threads that can run simultaneously in the interactive thread pool. See Set MID Server Thread Use.

Type: integer

Default value: 10

<

≡

MID Server Configuration Parameter

Created 2023-03-29 09:32:33

✎

⚙

⋮

Update

Delete

Parameter name

threads.interactive.max (MID Server maximum number of interactive worker threads. Default: 10)

Domain

global

✱ MID server

MIDServer3

Value

20

Update

Delete

threads.expedited.max

Sets the maximum number of expedited worker threads that can run simultaneously in the expedited thread pool. See Set MID Server Thread Use.

Type: integer

Default value: 20

<

≡

MID Server Configuration Parameter

Created 2023-03-29 09:32:33

✎

⚙

⋮

Update

Delete

Parameter name

threads.expedited.max (MID Server maximum number of expedited worker threads. Default: 20)

Domain

global

✱ MID server

MIDServer3

Value

30

Update

Delete

threads.max

Sets the maximum number of standard worker threads that can run simultaneously in the standard thread pool. This parameter provides direct control over what CPU resources the MID Server consumes on the computer that hosts it. See Set MID Server Thread Use.

Type: integer

Default value: 25

Important: You can set threads.max as high as 200, however, this setting may need to be changed depending on the OS. For example, Windows-based MID Servers running Discovery uses Powershell which is resource intensive. In this case, you may exhaust the CPU power of the host machine with just 50 threads count.

The screenshot shows the 'MID Server Configuration Parameter' window. At the top, it says 'Created 2023-03-29 09:34:40'. There are 'Update' and 'Delete' buttons in the top right. The main form has three sections: 'Parameter name' with a dropdown menu showing 'threads.max (MID Server maximum number of standard worker threads. Default: 25)', 'Domain' with a text box containing 'global' and a search icon, and 'Value' with a text box containing '30'. There is also a section for 'MID server' with a dropdown menu showing 'MIDServer3' and a search icon. At the bottom, there are 'Update' and 'Delete' buttons.

Parameter name	Domain	MID server	Value
threads.max (MID Server maximum number of standard worker threads. Default: 25)	global	MIDServer3	30