

Go

ssl — TLS/SSL wrapper for socket objects

Source code: Lib/ssl.py

This module provides access to Transport Layer Security (often known as "Secure Sockets Layer") encryption and peer authentication facilities for network sockets, both client-side and server-side. This module uses the OpenSSL library. It is available on all modern Unix systems, Windows, macOS, and probably additional platforms, as long as OpenSSL is installed on that platform.

Note: Some behavior may be platform dependent, since calls are made to the operating system socket APIs. The installed version of OpenSSL may also cause variations in behavior. For example, TLSv1.3 with OpenSSL version 1.1.1.

Warning: Don't use this module without reading the Security considerations. Doing so may lead to a false sense of security, as the default settings of the ssl module are not necessarily appropriate for your application.

This section documents the objects and functions in the ssl module; for more general information about TLS, SSL, and certificates, the reader is referred to the documents in the "See Also" section at the bottom.

This module provides a class, ssl.SSLSocket, which is derived from the socket.socket type, and provides a socket-like wrapper that also encrypts and decrypts the data going over the socket with SSL. It supports additional methods such as getpeercert(), which retrieves the certificate of the other side of the connection, and cipher(), which retrieves the cipher being used for the secure connection.

For more sophisticated applications, the ssl.SSLContext class helps manage settings and certificates, which can then be inherited by SSL sockets created through the SSLContext.wrap socket() method.

Changed in version 3.5.3: Updated to support linking with OpenSSL 1.1.0

Changed in version 3.6: OpenSSL 0.9.8, 1.0.0 and 1.0.1 are deprecated and no longer supported. In the future the ssl module will require at least OpenSSL 1.0.2 or 1.1.0.

Changed in version 3.10: PEP 644 has been implemented. The ssl module requires OpenSSL 1.1.1 or newer.

Use of deprecated constants and functions result in deprecation warnings.

Functions, Constants, and Exceptions

Socket creation

Since Python 3.2 and 2.7.9, it is recommended to use the SSLContext.wrap_socket() of an SSLContext instance to wrap sockets as SSLSocket objects. The helper functions create_default_context() returns a new context with secure default settings. The old wrap_socket() function is deprecated since it is both inefficient and has no support for server name indication (SNI) and hostname matching.

Client socket example with default context and IPv4/IPv6 dual stack:

1 of 39 1/23/22, 00:31





Go

```
hostname = 'www.python.org'
context = ssl.create_default_context()

with socket.create_connection((hostname, 443)) as sock:
    with context.wrap_socket(sock, server_hostname=hostname) as ssock:
    print(ssock.version())
```

Client socket example with custom context and IPv4:

```
hostname = 'www.python.org'
# PROTOCOL_TLS_CLIENT requires valid cert chain and hostname
context = ssl.SSLContext(ssl.PROTOCOL_TLS_CLIENT)
context.load_verify_locations('path/to/cabundle.pem')
with socket.socket(socket.AF_INET, socket.SOCK_STREAM, 0) as sock:
    with context.wrap_socket(sock, server_hostname=hostname) as ssock:
    print(ssock.version())
```

Server socket example listening on localhost IPv4:

```
context = ssl.SSLContext(ssl.PR0T0COL_TLS_SERVER)
context.load_cert_chain('/path/to/certchain.pem', '/path/to/private.key')
with socket.socket(socket.AF_INET, socket.SOCK_STREAM, 0) as sock:
    sock.bind(('127.0.0.1', 8443))
    sock.listen(5)
    with context.wrap_socket(sock, server_side=True) as ssock:
        conn, addr = ssock.accept()
        ...
```

Context creation

A convenience function helps create SSLContext objects for common purposes.

ssl.create_default_context(purpose=Purpose.SERVER_AUTH, cafile=None,
capath=None, cadata=None)

Return a new SSLContext object with default settings for the given *purpose*. The settings are chosen by the ssl module, and usually represent a higher security level than when calling the SSLContext constructor directly.

cafile, capath, cadata represent optional CA certificates to trust for certificate verification, as in SSLContext.load_verify_locations(). If all three are None, this function can choose to trust the system's default CA certificates instead.

The settings are: PROTOCOL_TLS_CLIENT or PROTOCOL_TLS_SERVER, OP_NO_SSLv2, and OP_NO_SSLv3 with high encryption cipher suites without RC4 and without unauthenticated cipher suites. Passing SERVER_AUTH as purpose sets verify_mode to CERT_REQUIRED and either loads CA certificates (when at least one of cafile, capath or cadata is given) or uses SSLContext.load_default_certs() to load default CA certificates.

When keylog_filename is supported and the environment variable SSLKEYLOGFILE is set, create default context() enables key logging.

2 of 39 1/23/22, 00:31