# SUSE Manager 3 Hands-on



#### Hands-on :: Channels 03

Channel Management: Create a workflow, clone channels and create activation keys

Install the spacewalk-utils package on your SUMA:

# zypper -n install spacewalk-utils

Configure a cumstom workflow a la "adsy-sles12-sp1":


```
# cat .spacewalk-manage-channel-lifecycle/settings.conf
[general]
phases = dev, test, prod
exclude channels =

[adsy-sles12-sp1]
phases = devl, prod
exclude channels =

# export pass="verysecure"
```

List the current channels and your workflow:

```
# spacewalk-manage-channel-lifecycle -u admin -p "$pass" -f
# spacewalk-manage-channel-lifecycle -u admin -p "$pass" -l
```




# Channels 03 - Development Channel

Create a development channel from the vendor channel:

#### **Channels 03 - Production Channels**

Create a producation channel from the development channel:



Create an archive from the production channel:

Rollback the archive channel to the production channel:

# Channels 03 - spacecmd Configuration

Create a configuration file for the spacecmd command:

~/.spacecmd/config

[spacecmd]
server=localhost
username=admin
password=verysecure
nossl=0

Create an activation key for salt development systems:

```
# spacecmd activationkey_create
INFO: Connected to https://localhost/rpc/api as admin
Name (blank to autogenerate): ak-sles12sp1-devl-salt
Description [None]: activation key for sles12 sp1 salt developmen
Base Channels
archive-20161110-prod-sles12-sp1-pool-x86 64
devl-sles12-sp1-pool-x86_64
prod-sles12-sp1-pool-x86_64
sles12-sp1-pool-x86_64
Base Channel (blank for default): devl-sles12-sp1-pool-x86_64
virtualization_host Entitlement [y/N]:
```

List the details of the salt development activation key:

```
# spacecmd activationkey_details 1-ak-sles12sp1-devl-salt
INFO: Connected to https://localhost/rpc/api as admin
                       1-ak-sles12sp1-devl-salt
Key:
Description:
                       activation key for sles12 sp1 development
Universal Default:
                      False
Usage Limit:
Deploy Config Channels: False
Contact Method:
                        default
Software Channels
devl-sles12-sp1-pool-x86 64
Configuration Channels
```

Add the child channels to the salt development activation key:

Create an activation key for the salt producation systems:

```
# spacecmd activationkey_create
INFO: Connected to https://localhost/rpc/api as admin
Name (blank to autogenerate): ak-sles12sp1-prod-salt
Description [None]: activation key for sles12 sp1 salt production
Base Channels
archive-20161110-prod-sles12-sp1-pool-x86 64
devl-sles12-sp1-pool-x86_64
prod-sles12-sp1-pool-x86_64
sles12-sp1-pool-x86_64
Base Channel (blank for default): prod-sles12-sp1-pool-x86_64
virtualization_host Entitlement [y/N]:
```

Add the child channels to the salt production activation key:

Create an activation key for the traditional producation systems:

```
# spacecmd activationkey create
INFO: Connected to https://localhost/rpc/api as admin
Name (blank to autogenerate): ak-sles12sp1-prod-trad
Description [None]: activation key for traditional sles12 sp1 pro
Base Channels
archive-20161110-prod-sles12-sp1-pool-x86 64
devl-sles12-sp1-pool-x86 64
prod-sles12-sp1-pool-x86_64
sles12-sp1-pool-x86 64
Base Channel (blank for default): prod-sles12-sp1-pool-x86 64
virtualization host Entitlement [y/N]:
```

Add the child channels to the traditional production activation key:

Add the required packages to the acvivation key: