

Industrial Tileset - Free: Documentation

Version 1.0.0 · Atomic Realm

1. Requirements and contents
2. Quick start
3. Painting a level
4. Layers and parallax
5. World Builder reference
6. Troubleshooting
7. Support and changelog

1. Requirements and contents

- Unity 6.0 or later, Universal Render Pipeline with the 2D Renderer.
- Package: 2D Tilemap Extras (comes with Unity's 2D feature set and the Universal 2D project template). The demo's Pixel Perfect Camera is the one built into URP, not the separate 2D Pixel Perfect package.
- Tested with Unity 6000.0.59f2, URP 17.0.4 and 2D Tilemap Extras 4.1.0.

Everything is in `Assets/Atomic Realm/`:

Folder	What's in it
`Industrial Tileset/Palettes/32p`	Tile Palettes, one per theme and layer (`AR A Factory 32p`, `AR A Factory Background 32p`, ...)
`Industrial Tileset/Tiles`	the tiles and the AUTO brushes (`Tiles/32p/<theme>/Brushes`)

`Industrial Tileset/Sprites`	the sprite sheets
`Industrial Tileset/*.unity`	the demo scene `Industrial Tileset Demo FREE 32p`
`World Builder`	the scripts and tools the tiles and the demo use, and the demo robot (see 5)

Themes: A Factory, B Dieselpunk and C Steampunk, at 32x32 pixels. Steampunk is a sample of 9 tiles (the outer edges, corners and fill), so its brush paints plain rectangles: no inner corners, platforms or pillars.

2. Quick start

1. Create a project from the **Universal 2D** template (Unity 6.0 or later).
2. Open *Window* > *Package Manager*, select **My Assets**, find **Industrial Tileset - Free**, click **Download**, then **Import**, and import everything in the dialog (including `World Builder`).
3. Open `Assets/Atomic Realm/Industrial Tileset/Industrial Tileset Demo FREE 32p`.
4. Set the Game view to **1920x1080** and press Play.
5. Walk with **A/D** or the arrow keys, run with **Shift**, jump with **Space** (hold to jump higher, press again in the air for a double jump). A gamepad works too.

The demo uses a Pixel Perfect Camera at 32 pixels per unit and a reference resolution of 960x540 (1920x1080 shows the art at 2x).

3. Painting a level

1. Open *Window* > *2D* > *Tile Palette*, pick a palette, e.g. `AR A Factory 32p`, and turn on **Gizmos** in the Tile Palette window's toolbar (not the Scene view's): it shows the palette's labels.
2. Paint with the **SOLID** brush (framed in yellow and labelled AUTO): it paints ground, and edges and corners pick themselves.
3. Use the single tiles of the palette for variety. AUTO cells around a hand-placed tile join it correctly.

With Gizmos on, the palette also captions each block of tiles (e.g. TILESET 1), highlights every copy of the tile in the brush, and draws a **red line** on a side where a piece's art continues but the palette's example stops there: in a level, that side needs a matching neighbour.

The palettes:

Palette	Use
`AR <theme> 32p`, e.g. `AR A Factory 32p`	the level itself (Main)
`AR <theme> Background 32p`, e.g. `AR A Factory Background 32p`	the darker background layer behind the level
`AR C Steampunk Background Violet 32p`	Steampunk's background

Template View (*Tools* > *Atomic Realm* > *Template View*, Ctrl+Alt+T) colours each tile by how it connects, in the Scene view and the Tile Palette: pink is ground (SOLID). Useful to find a piece that doesn't join its neighbours.

Shift Tilemap (*Tools* > *Atomic Realm* > *Shift Tilemap...*) moves all tiles of the selected tilemaps by whole cells, e.g. to make room at the left of a level.

4. Layers and parallax

The demo uses one tilemap per layer, both on the Default sorting layer, ordered by Order in Layer:

Grid (cell size)	Tilemap	Order in Layer	Parallax factor (x, y)	Example palette
Grid (1)	Background	-20	0.5, 0.5	`AR A Factory Background 32p`
Grid (1)	Main (the ground, with the collider)	0	1, 1	`AR A Factory 32p`
none	Player (not a tilemap)	10	1, 1	

The parallax factor is how much a layer moves when the camera moves: 1 = with the level (no parallax), below 1 = slower, so further away (0 = fixed to the camera), above 1 = faster, so in front of the level. It's the **Factor** of the **ParallaxLayer** component on the tilemap (see 5); layers without one move with the level.

Copy this setup from the demo scene, or use your own sorting layers with the same order.

5. World Builder reference

World Builder ships with every Atomic Realm pack (`Assets/Atomic Realm/World Builder`); keep it in that folder. Importing another pack keeps the newest copy.

PlatformerController (on the robot `World Builder/Characters/Robot/Robot.prefab`):

Field	Default	Meaning
Speed	8	top walking speed, in tiles per second
Sprint Multiplier	2	speed factor while Shift is held
Jump Height	5	highest jump with the button held, in tiles
Time To Apex	0.4	seconds to the top of a full jump (sets the gravity)
Air Jumps	1	extra jumps in the air (1 = double jump)
Arrow Keys	on	walk with the arrow keys as well as A/D; off leaves them to something else

Confine To, Confine Margin	none, 1	a tilemap whose painted area the robot stays in, and how far inside its edge

The other fields (accelerations, gravity factors, coyote time, jump buffer) fine-tune the feel; their tooltips explain them. **FlyController** flies in any direction without gravity, with the same Speed and Confine fields; while a PlatformerController on the same object is enabled, the flyer stays off.

CameraFollow2D (on the camera):

Field	Meaning
Target, Offset	what to follow, and the offset from it
Smooth Time	seconds to catch up; 0 = locked to the target
Pixels Per Unit	snap to whole pixels: set it to the tile size (32)
Confine To	a tilemap whose painted area the view stays in (it allows for that tilemap's parallax)

ParallaxLayer (on a tilemap):

Field	Meaning
Factor	how much the layer moves with the level, per axis: 1 = like the level, 0 = fixed to the camera
Repeat Horizontally, Repeat Width	repeat the layer endlessly sideways (width 0 = its painted width)
Pixels Per Unit	snap to whole pixels: the tile size

6. Troubleshooting

Problem	Fix
Everything is pink	the project isn't on URP: use the Universal 2D template, or assign a URP asset with the 2D Renderer
Tile or Rule Tile errors on import	install 2D Tilemap Extras (Package Manager)
Thin lines or gaps between tiles	use the Pixel Perfect Camera settings of section 2, and a Game view size that's a whole multiple of the reference resolution
Things drawn in the wrong order	check the Order in Layer of your tilemaps against section 4

7. Support and changelog

Questions and feedback: our Discord, https://discord.gg/7E48f96wBA · https://atomicrealm.com · https://atomicrealm.itch.io

The full **Industrial Tileset** adds five more themes and the full Steampunk, 16x16 versions of everything, FRAME brushes (poles, beams, girders), props, water, animated tiles, far backgrounds and foregrounds, hazards, crates, a boss with its effects, and the Photoshop sources.

1.0.0 First Asset Store release.



Atomic Realm