

BOKARO STEEL PLANT — ILLUSTRATIVE SAMPLE

Standard Operating Procedure

SOP No: BSP-OHS-003

Title: Prevention and First Aid for Heat Stress and Burns

Department: Occupational Health Services

Revision: 02

Date: 02-Apr-2024

1. PURPOSE

To prevent heat-related illness among personnel working near furnaces, converters and casting floors, and to give first aid for heat illness and burns.

2. PREVENTION

- Drink 250 ml of water every 20 minutes during hot work, even if not thirsty
- ORS (oral rehydration salts) is available at all shop-floor rest rooms
- Work-rest cycle in extreme heat zones: 45 minutes work followed by 15 minutes rest in a cool room
- New workers must be acclimatised over 5 to 7 days

3. SIGNS OF HEAT EXHAUSTION

Heavy sweating, weakness, dizziness, headache, nausea, cold and clammy skin.

First aid: move to a cool place, loosen clothing, give ORS or water in small sips, rest for at least 30 minutes.

4. SIGNS OF HEAT STROKE (MEDICAL EMERGENCY)

Hot, dry skin, confusion, fainting, body temperature above 40°C.

First aid:

Step 1 — Call Medical Centre: Ext. 2400 immediately.

Step 2 — Move the person to shade and cool the body with water and fanning; place ice packs at the neck, armpits and groin.

Step 3 — Do NOT give anything to drink if the person is confused or unconscious.

5. FIRST AID FOR THERMAL BURNS

- Cool the burn under clean running water for at least 20 minutes
- Remove rings and watches before swelling starts
- Do NOT apply ice, toothpaste, oil or any cream
- Do NOT burst blisters
- Cover loosely with a clean non-fluffy dressing and send to the Medical Centre