

CREATION VM UNIFY


1) Se connecter à proxmox


2) Appuyer create vm (en haut à droite sur proxmox)


3) Remplir les champs comme ci-dessous pour configurer la vm :





Create: Virtual Machine
General
OS
System
Disks
CPU
Memory
Network
Confirm
Use CD/DVD disc image file (iso)
Guest OS:
Storage: local
Type: Linux
ISO image: ubuntu-24.04.4-live-serv
Version: 7.x - 2.6 Kernel
Use physical CD/DVD Driv
Do not use any media
Name
For...
Size
kali-linux-2026.1-installer-amd64.iso iso 4.73 GB
proxmox-ve_9.1-1.iso iso 1.83 GB
SERVER_EVAL_2022_x64FRE_fr-fr.iso iso 5.06 GB
SERVER_EVAL_x64FRE_fr-fr.iso iso 5.06 GB
ubuntu-24.04.4-desktop-amd64.iso iso 6.66 GB
ubuntu-24.04.4-live-server-amd64.iso iso 3.41 GB
UbuntuSIO1.iso iso 6.66 GB
Win11_25H2_French_x64.iso iso 7.75 GB
WIN11SIO1.iso iso 7.75 GB
Windows.iso iso 4.92 GB
WindowsServer2022SIO1.iso iso 5.06 GB
Advanced
Back
Next


Create: Virtual Machine
General
OS
System
Disks
CPU
Memory
Network
Confirm
sata0
Disk
Bandwidth
Bus/Device: SATA 0
Cache: Default (No cache)
Storage: local-lvm
Discard:
Disk size (GiB): 20
IO thread:
Format: Raw disk image (raw)
SSD emulation:
Backup:
Read-only:
Skip replication:
Async IO: Default (io_uring)
Add
Import
Help
Advanced
Back
Next


Create: Virtual Machine
General
OS
System
Disks
CPU
Memory
Network
Confirm
Sockets:
1
Type:
Default (x86-64-v2-AES)
Cores:
2
Total cores:
2
VCPUs:
2
CPU units:
100
CPU limit:
unlimited
Enable NUMA:
CPU Affinity:
All Cores
Extra CPU Flags:
Value
Flag
Description
Supported On
Off
Default
On
nested-virt
Controls nested virtualization, namely 'svm' for AMD CPUs and 'vmx' for Intel CPUs. Live migration still only works if it's the same flag on both sides. Use a CPU model similar to the host, with the same vendor, not x86-64-vX!
SRVDEPLOY-S4P1
Off
Default
On
aes
Activate AES instruction set for HW acceleration.
SRVDEPLOY-S4P1
Off
Default
On
amd-ssbd
Improves Spectre mitigation performance with AMD
SRVDEPLOY-
Only show flags supported by at least one node
Showing flags for KVM
Help
Advanced
Back
Next


Create: Virtual Machine
General
OS
System
Disks
CPU
Memory
Network
Confirm
Memory (MiB):
2048
Minimum memory (MiB):
2048
Shares:
Default (1000)
Ballooning Device:
Allow KSM:
Help
Advanced
Back
Next




4) Appuyer sur « finish »


5) Faire double clic gauche sur la vm configurée puis la démarrer

6) Lancer l'installation d'Ubuntu Server et choisir la langue et le clavier français


7) Configurer l'interface ens18 en manuel : sous-réseau 192.168.26.0/24, adresse 192.168.26.9, passerelle 192.168.26.254, serveurs DNS 192.168.26.1 et 8.8.8.8 puis « Save »



8) Profil : nom sio2, nom du serveur srv-unify, utilisateur sio2 et mot de passe




9) Cocher « Install OpenSSH server »




10) Terminer l'installation, redémarrer la vm puis se connecter avec le compte sio2

11) Installer les paquets nécessaires au script d'installation



12) Passer en root avec sudo -i puis télécharger et lancer le script d'installation du contrôleur UniFi



13) Suivre les questions du script jusqu'à la fin de l'installation

14) Depuis le PC admin, ouvrir https://192.168.26.9:8443 et suivre l'assistant de première configuration du contrôleur (nom du contrôleur et compte administrateur)