torch.nn.functional.avg_pool3d#

https://pytorch.org/docs/stable/generated/torch.nn.functional.avg_pool3d.htm

Description:

Applies 3D average-pooling operation in kT×kH×kWkT \times kH \times kWkT×kH×kW regions by step size sT×sH×sWsT \times sH \times sWsT×sH×sW steps. The number of output features is equal to ⌊input planessT⌋\lfloor\frac{\text{input planes}}{sT}\rfloor⌊sTinput planes⌋. See AvgPool3d for details and output shape. input – input tensor (minibatch,in_channels,iT×iH,iW)(\text{minibatch} , \text{in_channels} , iT \times iH , iW)(minibatch,in_channels,iT×iH,iW) kernel_size – size of the pooling region. Can be a single number or a tuple (kT, kH, kW) stride – stride of the pooling operation. Can be a single number or a tuple (sT, sH, sW). Default: kernel_size

Function Signature

```
torch.nn.functional.avg_pool3d(input, kernel_size,
stride=None, padding=0, ceil_mode=False,
count_include_pad=True, divisor_override=None) → Tensor#
```

Parameters

Detailed Documentation

Documentation

Applies 3D average-pooling operation in kT×kH×kWkT \times kH \times kWkT×kH×kW regions by step size sT×sH×sWsT \times sH \times sWsT×sH×sW steps. The number of output features is equal to ⌊input planessT⌋\lfloor\frac{\text{input planes}}{sT}\rfloor⌊sTinput planes⌋.

See AvgPool3d for details and output shape.

input – input tensor (minibatch,in_channels,iT×iH,iW)(\text{minibatch} , \text{in_channels} , iT \times iH , iW)(minibatch,in_channels,iT×iH,iW)

kernel_size – size of the pooling region. Can be a single number or a tuple (kT, kH, kW)

stride – stride of the pooling operation. Can be a single number or a tuple (sT, sH, sW). Default: kernel_size

padding – implicit zero paddings on both sides of the input. Can be a single number or a tuple (padT, padH, padW). Should be at most half of effective kernel size, that is ((kernelSize−1)∗dilation+1)/2((kernelSize - 1) * dilation + 1) / 2((kernelSize−1)∗dilation+1)/2. Default: 0

ceil_mode – when True, will use ceil instead of floor in the formula to compute the output shape

count_include_pad – when True, will include the zero-padding in the averaging calculation

divisor_override – if specified, it will be used as divisor, otherwise size of the pooling region will be used. Default: None