Conv1d#

https://pytorch.org/docs/stable/generated/torch.ao.nn.quantized.Conv1d.html

Description:

Applies a 1D convolution over a quantized input signal composed of several quantized input planes. For details on input arguments, parameters, and implementation see Conv1d. Only zeros is supported for the padding_mode argument.

Function Signature

```
class torch.ao.nn.quantized.Conv1d(in_channels,
out_channels, kernel_size, stride=1, padding=0, dilation=1,
groups=1, bias=True, padding_mode='zeros', device=None,
dtype=None)[source]#

Variables

classmethod from_float(mod,
use_precomputed_fake_quant=False)[source]#

Parameters
```

Code Examples

```
>>> m = nn.quantized.Conv1d(16, 33, 3, stride=2)
>>> input = torch.randn(20, 16, 100)
>>> # quantize input to quint8
>>> q_input = torch.quantize_per_tensor(input, scale=1.0,
zero_point=0,
...                                     dtype=torch.quint8)
>>> output = m(q_input)
```

Notes & Warnings

NOTE Note Only zeros is supported for the padding_mode argument.

NOTE Note Only torch.quint8 is supported for the input data type.

Detailed Documentation

Documentation

Applies a 1D convolution over a quantized input signal composed of several quantized input planes.

For details on input arguments, parameters, and implementation see Conv1d.

Only zeros is supported for the padding_mode argument.

Only torch.quint8 is supported for the input data type.

weight (Tensor) – packed tensor derived from the learnable weight parameter.

scale (Tensor) – scalar for the output scale

zero_point (Tensor) – scalar for the output zero point

See Conv1d for other attributes.

Creates a quantized module from a float module or qparams_dict.

mod (Module) – a float module, either produced by torch.ao.quantization utilities or provided by the user