

conv2d#

<https://pytorch.org/docs/stable/generated/torch.nn.quantized.functional.conv2d.html>

Description:

Applies a 2D convolution over a quantized 2D input composed of several input planes. See Conv2d for details and output shape. input – quantized input tensor of shape $(\text{minibatch}, \text{in_channels}, \text{iH}, \text{iW})$ weight – quantized filters of shape $(\text{out_channels}, \frac{\text{in_channels}}{\text{groups}}, \text{kH}, \text{kW})$ (out_channels, groups, in_channels, kH, kW) bias – non-quantized bias tensor of shape (out_channels). The tensor type must be torch.float.

Function Signature

```
class torch.nn.quantized.functional.conv2d(input, weight,
bias, stride=1, padding=0, dilation=1, groups=1,
padding_mode='zeros', scale=1.0, zero_point=0,
dtype=torch.qint8)[source]#
```

Parameters

Code Examples

```
>>> from torch.nn.quantized import functional as qF
>>> filters = torch.randn(8, 4, 3, 3, dtype=torch.float)
>>> inputs = torch.randn(1, 4, 5, 5, dtype=torch.float)
>>> bias = torch.randn(8, dtype=torch.float)
>>>
>>> scale, zero_point = 1.0, 0
>>> dtype_inputs = torch.qint8
>>> dtype_filters = torch.qint8
>>>
>>> q_filters = torch.quantize_per_tensor(filters, scale,
>>> zero_point, dtype_filters)
>>> q_inputs = torch.quantize_per_tensor(inputs, scale,
>>> zero_point, dtype_inputs)
>>> qF.conv2d(q_inputs, q_filters, bias, padding=1, scale=scale,
>>> zero_point=zero_point)
```

Detailed Documentation

Documentation

Applies a 2D convolution over a quantized 2D input composed of several input planes.

See Conv2d for details and output shape.

input – quantized input tensor of shape $(\text{minibatch}, \text{in_channels}, \text{iH}, \text{iW})$,
 $(\text{in_channels}, \text{iH}, \text{iW})$

weight – quantized filters of shape $(\text{out_channels}, \text{in_channelsgroups}, \text{kH}, \text{kW})$

$(\text{out_channels}, \frac{\text{in_channels}}{\text{groups}}, \text{KH}, \text{KW})$
(out_channels, groups, in_channels, kH, kW)

bias – non-quantized bias tensor of shape (out_channels)(\text{out_channels}) (out_channels). The tensor type must be torch.float.

stride – the stride of the convolving kernel. Can be a single number or a tuple (sH, sW).
Default: 1

padding – implicit paddings on both sides of the input. Can be a single number or a tuple (padH, padW). Default: 0

dilation – the spacing between kernel elements. Can be a single number or a tuple (dH, dW). Default: 1

groups – split input into groups, in_channels\text{in_channels}in_channels should be divisible by the number of groups. Default: 1

padding_mode – the padding mode to use. Only “zeros” is supported for quantized convolution at the moment. Default: “zeros”

scale – quantization scale for the output. Default: 1.0

zero_point – quantization zero_point for the output. Default: 0

dtype – quantization data type to use. Default: torch.quint8