Change project-level permissions

Article • 05/30/2024

Azure DevOps Services | Azure DevOps Server 2022 - Azure DevOps Server 2019

Many permissions get set at the project level. You can grant these permissions by adding a user or group to the **Project Administrators** group. Or, you can grant select project-level permissions to a custom security group or to a user.

Consider adding users to the **Project Administrators** group when they're tasked with adding or managing teams, area and iteration paths, repositories, service hooks, and service end points.

Project-level permissions

The following table lists the permissions assigned at the project-level. All of these permissions are granted to members of the **Project Administrators** group, except for the **Delete shared Analytics views** and **Edit shared Analytics views** permissions which are not set. For a description of each permission, see Permissions and groups reference, Groups.

General

- Delete team project
- Edit project-level information
- Manage project properties
- Rename team project
- Suppress notifications for work item updates
- Update project visibility
- View project-level information

Boards

- Bypass rules on work item updates
- Change process of team project
- Create tag definition
- Delete and restore work items
- Move work items out of this project
- Permanently delete work items

Analytics

- Delete shared Analytics views
- Edit shared Analytics views

View analytics

Test Plans

- Create test runs
- Delete test runs
- Manage test configurations
- Manage test environments
- View test runs

① Note

The permission to add or remove project-level security groups and add and manage project-level group membership is assigned to all members of the **Project Administrators** group. It isn't controlled by a permissions surfaced within the user interface.

Create tag definition permission

By default, members of the **Contributors** group are assigned the **Create tag definition** permission. Although the **Create tag definition** permission appears in the security settings at the project-level, tagging permissions are actually collection-level permissions that are scoped at the project level when they appear in the user interface. To scope tagging permissions to a single project when using a command-line tool, you must provide the GUID for the project as part of the command syntax. Otherwise, your change applies to the entire collection. For more information, see Security groups, service accounts, and permissions, Work item tags.

Prerequisites

- To manage permissions or groups at the project level, you must be a member of the Project Administrators security group. If you created the project, you're automatically added as a member of this group. To get added to this group, you need to request permissions from a member of the Project Administrators group.
 See Look up a project administrator.
- To add security groups defined in Microsoft Entra ID or Active Directory, make sure the security groups are first defined. For more information, see Add Active Directory / Microsoft Entra users or groups to a built-in security group.

! Note

Users granted **Stakeholder** access, can't access select features even if granted permissions to those features. For more information, see <u>Stakeholder access quick reference</u>.

Add members to the Project Administrators group

You can add users who are associated with a project, organization, or collection to the Project Administrators group. This group has specific permissions at the organizations or collection level. To add a custom security group, first create the group as described in Add or remove users or groups, manage security groups.


Here we show how to add a user to the built-in **Project Administrators** group. The method is similar to adding a Microsoft Entra ID or Active Directory group.

① Note


To enable the **Project Permissions Settings Page** preview page, see **Enable preview features**.

Preview page


- 1. Sign in to your organization (https://dev.azure.com/{yourorganization}).
- 2. Select **Project settings** > **Permissions**.



3. Select **Project Administrators** group > **Members** > **Add**.



4. Enter the name of the user account or custom security group into the text box. You can enter several identities recognized by the system into the **Add users and/or groups** box. The system automatically searches for matches. Choose one or more matches.



Change permissions for a group

You can modify project-level permissions for any group associated with a project, except for the **Project Administrators** group. Also, each team that is added to a project is automatically included as a project-level group. To add security groups to a project, see Add or remove users or groups, manage security groups. To understand permission assignments and inheritance, see About permissions, Permission states.

① Note

To enable the **Project Permissions Settings Page** preview page, see <u>Enable preview</u> <u>features</u>.

Preview page


1. Open the **Permissions** page as described in the previous section, Add a user or group to the Project Administrators group.

① Note

You can't change the permission settings for the Project Administrators group. This is by design.

2. From the **Permissions** page, choose the group whose permissions you want to change.

For example, we choose the **Contributors** group and change their permissions for **Delete and restore work items** to **Allow**.



Your changes are automatically saved.



If you add a user to the **Contributors** group, they can add and modify work items. You can restrict permissions of users or user groups to add and modify work items based on the **Area Path**. For more information, see **Modify work items under an area path**.

Change permissions for a user


You can change the project-level permissions for a specific user. To understand permission assignments and inheritance, see About permissions, Permission states.

① Note

To enable the **Project Permissions Settings Page** preview page, see <u>Enable preview</u> features.


Preview page

- 1. Open the **Permissions** page as described in the previous section, Add a user or group to the Project Administrators group.
- 2. From the **Permissions** page, select **Users**, and then choose the user whose permissions you want to change.



3. From the **Permissions** page, change the assignment for one or more permissions.

For example, we change the **Edit project-level information** for Christie Church.



Dismiss the dialog when you're done. Your changes are automatically saved.

Next steps

Manage projects

Related articles

Set object-level permissions

- Get started with permissions, access, and security groups
- Look up permissions
- Learn about permissions and groups
- Manage teams and configure team tools

Feedback

Provide product feedback