

# EMV<sup>®</sup> 3-D Secure

# **SDK—Device Information**

Version 2.1.0 October 2017

### **Legal Notice**

The EMV® Specifications are provided "AS IS" without warranties of any kind, and EMVCo neither assumes nor accepts any liability for any errors or omissions contained in these Specifications. EMVCO DISCLAIMS ALL REPRESENTATIONS AND WARRANTIES, EXPRESS OR IMPLIED, INCLUDING WITHOUT LIMITATION IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, TITLE AND NON-INFRINGEMENT, AS TO THESE SPECIFICATIONS.

EMVCo makes no representations or warranties with respect to intellectual property rights of any third parties in or in relation to the Specifications. EMVCo undertakes no responsibility to determine whether any implementation of the EMV® Specifications may violate, infringe, or otherwise exercise the patent, copyright, trademark, trade secret, know-how, or other intellectual property rights of third parties, and thus any person who implements any part of the EMV® Specifications should consult an intellectual property attorney before any such implementation.

Without limiting the foregoing, the Specifications may provide for the use of public key encryption and other technology, which may be the subject matter of patents in several countries. Any party seeking to implement these Specifications is solely responsible for determining whether its activities require a license to any such technology, including for patents on public key encryption technology. EMVCo shall not be liable under any theory for any party's infringement of any intellectual property rights in connection with the EMV® Specifications.

# **Revision Log—Version 2.1.0**

The following changes have been made to the document since the publication of Version 2.0.0.

- Updated Chapter 1 as follows:
  - o Updated the EMV 3DS Protocol Specification version number to 2.1.0.
  - o Removed the Definitions table and added a reference to the Definitions table present in *EMV 3DS Protocol Specification*.
  - o Added the Data Version Number section.
  - o Added the Supporting Documentation section.
- Updated Chapter 2 as follows:
  - Data version for the current set of device parameters changed to 1.1
  - o Renamed Windows Phone to Windows 10 Mobile.
  - Removed the following Android device parameters:
    - BluetoothAdapter
    - Timezone
  - Identifier of Android parameters re-ordered due to the removal of above parameters
  - Updated the description of Android parameters A127, A128, and A130.
  - o Moved the Android isSafeMode parameter to the Package Manager group.

### **Contents**

1	Intro	oduction 8	
	1.1	Purpose8	
	1.2	Audience	
	1.3	Definitions8	
	1.4	Abbreviations8	
	1.5	Data Version Number9	
	1.6	Supporting Documentation9	
	1.7	Terminology and Conventions	
2	Device Identification Parameters		
	2.1	Data Version11	
	2.2	Minimum Supported Platform Versions	
	2.3	Platform Permissions for Parameters	
	2.4	Common Device Identification Parameters Available in All Platforms 12	
	2.5	Android-Specific Device Parameters	
	2.6	iOS-Specific Device Parameters	
	2.7	Windows 10 Mobile-Specific Device Parameters	
	2.8	Reasons for Device Parameters Unavailability	
	2.9	Device Information JSON Data	

# **Tables**

Table 1.1:	Abbreviations	8
Table 1.2:	Data Version Numbers	9
Table 2.1:	Minimum Supported Platform Version	11
Table 2.2:	Common Parameters Available in Android, iOS and Windows 10 Mobile Platforms	
Table 2.3:	Android-Specific Device Parameters	15
Table 2.4:	iOS-Specific Device Parameters	34
Table 2.5:	Windows 10 Mobile-Specific Device Parameters	36
Table 2.6:	Device Parameter Unavailability Reasons	38
Table 2.7:	Device Parameters JSON Structure	39

# 1 Introduction

The 3-D Secure protocol is aimed at securing authentication in browser-based and mobile app-based transactions. The *EMV 3-D Secure Protocol and Core Functions Specification version 2.1.0* describes the 3-D Secure protocol and core functions.

The 3DS Mobile SDK is the mobile-device-side component of 3-D Secure. The *EMV 3-D Secure SDK Specification version 2.1.0* describes the specification for the 3DS SDK.

Device identification is used to uniquely identify mobile devices in the 3-D Secure ecosystem. The ThreeDS2Service interface is one of the code elements that are described in the *EMV 3-D Secure SDK Specification version 2.1.0*. The initialize method of this interface collects the information required for device identification. This information is then sent to the 3DS Requestor App in JSON format. The 3DS Requestor App passes this information to the 3DS Server. The 3DS Server uses this information to create an AReq.

### 1.1 Purpose

This document describes the device identification parameters that shall be collected by the 3DS SDK.

For purposes of this document, when the phrase 3-D Secure, and/or 3DS is utilised, the intent is EMV 3-D Secure.

### 1.2 Audience

This document is intended for use by implementers of the 3DS SDK.

### 1.3 Definitions

For the definition of the terms used in this document, refer to Table 1.3: Definitions in the *EMV* 3-D Secure Protocol and Core Functions Specification.

### 1.4 Abbreviations

The abbreviations listed in Table 1.1 are used in this specification.

**Table 1.1: Abbreviations** 

Abbreviation	Description
3DS	Three Domain Secure
3DS SDK	Three Domain Secure Software Development Kit

Abbreviation	Description
ACS	Access Control Server
AReq	Authentication Request
ARes	Authentication Response
DD	Device Data
DPNA	Device Parameter Not Available
DV	Data version
SDK	Software Development Kit
SW	Security Warning

### 1.5 Data Version Number

The following table provides the Data Version Number status for the 3-D Secure protocol version.

**Table 1.2: Data Version Numbers** 

Data Version Number	Protocol Version	Status
1.0	2.0.0	Deprecated
1.1	2.1.0	Active

# 1.6 Supporting Documentation

The following documents are specific to the EMV 3-D Secure protocol and should be used in conjunction with this specification. These documents as well as EMV 3-D Secure FAQs are located on the EMVCo website under the 3-D Secure heading.

- EMV 3-D Secure— Protocol and Core Functions Specification
- EMV 3-D Secure SDK Technical Guide
- EMV 3-D Secure—SDK Specification
- EMV 3-D Secure JSON Message Samples

# 1.7 Terminology and Conventions

The following words are used often in this specification and have a specific meaning:

#### Shall

Defines a product or system capability which is mandatory.

### May

Defines a product or system capability which is optional or a statement which is informative only and is out of scope for this specification.

#### **Should**

Defines a product or system capability which is recommended.

# 2 Device Identification Parameters

This chapter describes the device identification parameters that shall be collected by the 3DS SDK from all mobile platforms. These parameters are categorized as device-platform-specific parameters and parameters that are common to all device platforms.

Note: The 3DS SDK shall collect and pass the common parameters. This is the minimum requirement. In addition, the implementer shall ensure that the 3DS SDK collects as many device-platform-specific parameters as possible. The availability of a higher number of device parameters improves the effectiveness of risk-based decision making by the ACS. This, in turn, increases the probability of applying a frictionless flow.

### 2.1 Data Version

The data version specifies the set of device identification parameters that the 3DS SDK shall collect. The data version is a means for participating 3DS 2.0 components to know which set of device identification parameters is being transferred. The data version may change when, for example, there are parameter changes in future mobile OS versions, an existing parameter is deprecated, and so on.

The Data Version shall be included in the device identification information that is sent by the 3DS SDK.

The device identification parameters that are described in this document constitute Data Version 1.1.

### 2.2 Minimum Supported Platform Versions

Table 2.1 lists the minimum platform versions that shall be supported by the SDK.

Platform	Minimum Version
Android	KitKat 4.4 (API version 19)
iOS	8
Windows 10 Mobile	10

Table 2.1: Minimum Supported Platform Version

### 2.3 Platform Permissions for Parameters

The following types of permissions are required for collecting device identification parameters:

 No permissions required: Indicates that the device parameters can be directly collected by the 3DS SDK, without any user approval or system permissions.

- **Installation-time permissions**: Indicates that the device parameters require system permissions to be granted to the app during installation time.
- Run-time permissions: Indicates that the device parameters can be collected by the 3DS SDK only if the required permissions have already been granted to the app through user approval at run time.

The 3DS SDK shall check whether installation-time or run-time permission for a particular parameter is available or has already been granted to the app. If the permission for a particular parameter is not available, then the 3DS SDK shall send one of the reason codes stated in Table 2.6 as the value for the parameter within the Device Parameter Not Available (DPNA) tag.

**Note:** The 3DS SDK *shall never* prompt the user for run-time permissions. Similarly, the 3DS SDK *shall not* mandate the inclusion of additional installation-time permissions on the 3DS Requestor App.

# 2.4 Common Device Identification Parameters Available in All Platforms

In addition to the platform-specific device parameters discussed later in this document, Table 2.2 lists the device parameters that shall be collected from all mobile platforms for Device ID validation and risk analysis.

The availability of these parameters is subject to change in future OS versions.

**Note:** Each parameter listed in this table shall be collected by the SDK unless the parameter cannot be collected for any of the reasons stated in Table 2.6.

Table 2.2: Common Parameters Available in Android, iOS and Windows 10 Mobile Platforms

Identifier	Parameter	Description	Permissions
C001	Platform	Platform that the device is using.	Not applicable.
		For example, Android, iOS, Windows 10 Mobile.	
C002	Device Model	Mobile device manufacturer and model.	No permissions required.
		For example, In Android,	
		Build.Model returns the model name.	

Identifier	Parameter	Description	Permissions
C003	OS Name	Operating system name.  For example, in iOS, the systemName property of the UIDevice class returns the name of the operating system.	No permissions required.
C004	OS Version	Operating system version.  For example, in iOS, the systemVersion property of the UIDevice class returns the version of the operating system.	No permissions required.
C005	Locale	Device locale set by the user.  For example, in Windows 10 Mobile, the CurrentCulture property of the CultureInfo class returns the locale.	No permissions required.
C006	Time zone	Device time zone.  For example, in Android, the TimeZone.getDefault() method returns a time zone based on the time zone where the program is running.	No permissions required.
C007	Advertising ID	Unique ID available for advertising and fraud detection purposes.  For example, in Windows 10 Mobile, AdvertisingManager. AdvertisingId retrieves a unique ID used to provide more relevant advertising.	No permissions required.
C008	Screen Resolution	Pixel width and pixel height, i.e., 1080x1920.  For example, in Android, the screen resolution can be obtained from the heightPixels and widthPixels fields of the DisplayMetrics class.	No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at  $\underline{www.emvco.com}$ . EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Identifier	Parameter	Description	Permissions
C009	Device Name	User-assigned device name.  For example, in iOS, the localizedModel property of the UIDevice class returns the Device Name.	On Android, this parameter requires Bluetooth permission during installation.  No permissions required on iOS or Windows 10 Mobile.
C010	IP Address	IP address of device.	On Android, this parameter requires the following permissions during installation.  android.permission .INTERNET
			android.permission .ACCESS_NETWORK_ST ATE
			No permissions required on iOS or Windows 10 Mobile.
C011	Latitude	Device physical location latitude.	Run-time permissions required on Android API 23 and later, iOS and Windows 10 Mobile. Installation-time permissions required on Android 22 and earlier.
C012	Longitude	Device physical location longitude.	Run-time permissions required on Android API 23 and later, iOS and Windows 10 Mobile.  Installation-time permissions required on Android 22 and earlier.

### 2.5 Android-Specific Device Parameters

Table 2.3 provides information about the device parameters that shall be collected by the 3DS SDK from the Android mobile platform for risk analysis by the ACS.

In this table, the Group or Identifier column contains the name of the parameter group or parameter identifier.

**Table 2.3: Android-Specific Device Parameters** 

Group or Identifier	Element	Description	Comments	Permissions
Telephon Y Manager		Telephony Manager provides access to information about the telephony services on the device.	This group of parameters requires the following permissions: android.permission. SEND_SMS android.permission. READ_PHONE_STATE  User approval is not required for API 22 and earlier because these permissions are granted during installation.	Run-time permissions
A001	DeviceId	Unique identifier of the device. For example, IMEI for GSM phones and MEID or ESN for CDMA phones.		Run-time permissions
A002	SubscriberI d	Unique subscriber ID. For example, IMSI for GSM phones.		Run-time permissions
A003	IMEI/SV	IMEI software version.		Run-time permissions
A004	Group Identifier Level1	Group identifier level 1 for a GSM phone.	Available only for API 18 or higher.	Run-time permissions

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="https://www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A005	Line1 Number	Phone number string for line 1.  For example, the MSISDN for a GSM phone.		Run-time permissions
A006	MmsUAProfUr	MMS user agent profile URL.	Available only for API 19 or higher.	Run-time permissions
A007	MmsUserAgen t	MMS user agent.	Available only for API 19 or higher.	Run-time permissions
A008	NetworkCoun tryIso	ISO country code equivalent of the current registered operator's MCC (Mobile Country Code).		Run-time permissions
A009	NetworkOper ator	Numeric name (mobile country code + mobile network code) of the current registered operator.		Run-time permissions
A010	NetworkOper atorName	Alphabetic name of the current registered operator.		Run-time permissions
A011	NetworkType	NETWORK_TYPE_xx xx for the current data connection.		Run-time permissions
A012	PhoneCount	Number of phones available. Returns 1 for single standby mode (single SIM functionality). Returns 2 for dual standby mode (dual SIM functionality).	Available only for API 23 or higher.	Run-time permissions

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at  $\underline{www.emvco.com}$ . EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A013	PhoneType	Constant that indicates the device phone type. This indicates the type of radio used to transmit voice calls.		Run-time permissions
A014	SimCountryI so	ISO country code equivalent for the SIM provider's country code.		Run-time permissions
A015	SimOperator	MCC+MNC (mobile country code + mobile network code) of the SIM provider.		Run-time permissions
A016	SimOperator Name	Service Provider Name (SPN).		Run-time permissions
A017	SimSerialNu mber	Serial number of the SIM, if applicable.		Run-time permissions
A018	SimState	Constant that indicates the state of the default SIM card.		Run-time permissions
A019	VoiceMailAl phaTag	Alphabetic identifier associated with the voice mail number.		Run-time permissions
A020	VoiceMailNu mber	Voice mail number.		Run-time permissions
A021	hasIccCard	Returns true if an ICC card is present.		Run-time permissions
A022	isHearingAi dCompatibil itySupporte d	Indicates whether the phone supports hearing aid compatibility.	Available only for API 23 or higher.	Run-time permissions

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at  $\underline{www.emvco.com}$ . EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A023	isNetworkRo aming	Determines if the device is considered roaming on the current network, for GSM purposes.		Run-time permissions
A024	isSmsCapabl e	Determines if the current device supports SMS service.	Available only for API 21 or higher.	Run-time permissions
A025	isTtyModeSu pported	Determines whether the phone supports TTY mode.	Available only for API 23 or higher.	Run-time permissions
A026	isVoiceCapa ble	Determines if the current device is "voice capable".	Available only for API 22 or higher.	Run-time permissions
A027	isWorldPhon e	Determines whether the device is a world phone.	Available only for API 23 or higher.	Run-time permissions
WifiMana ger		WifiManager provides the primary API for managing all aspects of Wi-Fi connectivity.	This group of parameters requires the following permission: android.permission. ACCESS_WIFI_STATE	Installation- time permissions
A028	Wifi - Mac Address	Returns the wireless MAC address of the device.		Installation- time permissions
A029	BSSID	Returns the basic service set identifier (BSSID) of the current access point.		Installation- time permissions
A030	SSID	Returns the service set identifier (SSID) of the current 802.11 network.		Installation- time permissions

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A031	Network ID	Each configured network has a unique small integer ID, used to identify the network when performing operations on the supplicant.		Installation- time permissions
A032	is5GHzBandS upported	Determines if this adapter supports the 5 GHz band.	Available only for API 21 or higher.	Installation- time permissions
A033	isDeviceToA pRttSupport ed	Determines if this adapter supports Device-to-AP RTT.	Available only for API 21 or higher.	Installation- time permissions
A034	isEnhancedP owerReporti ngSupported	Determines if this adapter supports advanced power and performance counters.	Available only for API 21 or higher.	Installation- time permissions
A035	isP2pSuppor ted	Determines if this adapter supports WifiP2pManager.	Available only for API 21 or higher.	Installation- time permissions
A036	isPreferred NetworkOffl oadSupporte d	Determines if this adapter supports offloaded connectivity scan.	Available only for API 21 or higher.	Installation- time permissions
A037	isScanAlway sAvailable	Determines if scanning is always available.	Available only for API 18 or higher.	Installation- time permissions
A038	isTdlsSuppo rted	Determines if this adapter supports Tunnel Directed Link Setup.	Available only for API 21 or higher.	Installation- time permissions

Group or Identifier	Element	Description	Comments	Permissions
Bluetoot h Manager		Bluetooth Manager is used to conduct overall Bluetooth Management.  Through Bluetooth Adapter, it facilitates in performing fundamental Bluetooth tasks, such as initiate device discovery, query a list of bonded (paired) devices, instantiate a BluetoothDevice using a known MAC address, and create a BluetoothServerSocke t to listen for connection requests from other devices, and start a scan for Bluetooth LE devices.	This group of parameters requires following permission: android.permission. BLUETOOTH	Installation-time permissions
A039	Address	Hardware address of the local Bluetooth adapter.	Available only for API 18 or higher.	Installation- time permissions
A040	BondedDevic es	Returns the set of BluetoothDevice ob jects that are bonded (paired) to the local adapter.	Available only for API 18 or higher.	Installation- time permissions
A041	isEnabled	Returns true if Bluetooth is currently enabled and ready for use.		Installation- time permissions

Group or Identifier	Element	Description	Comments	Permissions
Build		Build is used to determine information about the current build, extracted from system properties.		No permissions required.
A042	BOARD	Name of the underlying board, such as "goldfish".		No permissions required.
A043	BOOTLOADER	System bootloader version number.		No permissions required.
A044	BRAND	Consumer-visible brand with which the product/hardware will be associated, if any.		No permissions required.
A045	DEVICE	Name of the industrial design.		No permissions required.
A046	DISPLAY	Build ID string that is displayed to the user.		No permissions required.
A047	FINGERPRINT	String that uniquely identifies this build.		No permissions required.
A048	HARDWARE	Name of the hardware (from the kernel command line or /proc).		No permissions required.
A049	ID	Either a changelist number, or a label like "M4-rc20".		No permissions required.
A050	MANUFACTURE R	Manufacturer of the product/hardware.		No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A051	PRODUCT	Name of the overall product.		No permissions required.
A052	RADIO	Radio firmware version number.		No permissions required.
A053	SERIAL	Hardware serial number, if available.		No permissions required.
A054	SUPPORTED_3 2_BIT_ABIS	Ordered list of 32- bit ABIs supported by this device. The most preferred ABI is the first element in the list.	Available only for API 21 or higher.	No permissions required.
A055	SUPPORTED_6 4_BIT_ABIS	Ordered list of 64- bit ABIs supported by this device. The most preferred ABI is the first element in the list	Available only for API 21 or higher.	No permissions required.
A056	TAGS	Comma-separated tags describing the build, such as "unsigned, debug".		No permissions required.
A057	TIME	Build time.		No permissions required.
A058	TYPE	Type of build, such as "user" or "eng".		No permissions required.
A059	USER			No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="https://www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
Build.VE RSION		Indicates various version strings.		No permissions required.
A060	CODENAME	The current development codename, or the string "REL" if this is a release build.		No permissions required.
A061	INCREMENTAL	The internal value used by the underlying source control to represent this build.		No permissions required.
A062	PREVIEW_SDK _INT	The developer preview revision of a prerelease SDK.		No permissions required.
A063	SDK_INT	The user-visible SDK version of the framework; its possible values are defined in Build.VERSION_CO DES.		No permissions required.
A064	SECURITY_PA TCH	The user-visible security patch level.		No permissions required.
Settings Secure		Secure system settings, containing system preferences that applications can read but are not allowed to write.		No permissions required.
A065	ACCESSIBILI TY_DISPLAY_ INVERSION_E NABLED	Specifies whether display color inversion is enabled.		No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="https://www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A066	ACCESSIBILI TY_ENABLED	Specifies whether accessibility is enabled.		No permissions required.
A067	ACCESSIBILI TY_SPEAK_PA SSWOR9D	Specifies whether to speak passwords while in accessibility mode.		No permissions required.
A068	ALLOWED_GEO LOCATION_OR IGINS	Origins for which browsers should allow geolocation by default. The value is a space-separated list of origins.		No permissions required.
A069	ANDROID_ID	64-bit number (as a hex string) that is randomly generated when the end user first sets up the device. This number should remain constant for the lifetime of the end user's device. The value may change if a factory reset is performed on the device.		No permissions required.
A070	DATA_ROAMIN	Determines whether or not data roaming is enabled.	Available only for API 17 or higher.	No permissions required.
A071	DEFAULT_INP UT_METHOD	Setting to record the input method used by default.		No permissions required.
A072	DEVICE_PROV ISIONED	Determines whether the device has been provisioned.	Available only for API 17 or higher.	No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A073	ENABLED_ACC ESSIBILITY_ SERVICES	List of enabled accessibility providers.		No permissions required.
A074	ENABLED_INP UT_METHODS	List of input methods that are currently enabled.		No permissions required.
A075	INPUT_METHO D_SELECTOR_ VISIBILITY	Setting to record the visibility of the input method selector.		No permissions required.
A076	INSTALL_NON _MARKET_APP S	Specifies whether applications can be installed for this user via the system's ACTION_IN STALL_PACKAGE mec hanism.		No permissions required.
A077	LOCATION_MO DE	Degree of location access enabled by the end user.		No permissions required.
A078	SKIP_FIRST_ USE_HINTS	If enabled, apps should try to skip any introductory hints on first launch.		No permissions required.
A079	SYS_PROP_SE TTING_VERSI ON	Secure system settings, containing system preferences that applications can read but are not allowed to write.	Available only for APIs below 24.	No permissions required.
A080	TTS_DEFAULT _PITCH	Default text-to-speech engine pitch.		No permissions required.
A081	TTS_DEFAULT _RATE	Default text-to-speech engine speech rate.		No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="https://www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A082	TTS_DEFAULT _SYNTH	Default text-to-speech engine.		No permissions required.
A083	TTS_ENABLED _PLUGINS	Space delimited list of plugin packages that are enabled.		No permissions required.
Settings Global		Global system settings, containing preferences that always apply identically to all defined users.		No permissions required.
A084	ADB_ENABLED	Specifies whether ADB is enabled.	Available only for API 17 or higher.	No permissions required.
A085	AIRPLANE_MO DE_RADIOS	Comma-separated list of radios that need to be disabled when airplane mode is on.	Available only for API 17 or higher.	No permissions required.
A086	ALWAYS_FINI SH_ACTIVITI ES	If 1, the activity manager will aggressively finish activities and processes as soon as they are no longer needed.	Available only for API 17 or higher.	No permissions required.
A087	ANIMATOR_DU RATION_SCAL E	Scaling factor for animator-based animations.	Available only for API 17 or higher.	No permissions required.
880A	AUTO_TIME	Value to specify whether the user prefers the date, time and time zone to be automatically fetched from the network (NITZ).	Available only for API 17 or higher.	No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="https://www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A089	AUTO_TIME_Z ONE	Value to specify whether the user prefers the time zone to be automatically fetched from the network (NITZ).	Available only for API 17 or higher.	No permissions required.
A090	DEVELOPMENT _SETTINGS_E NABLED	Determines whether the end user has enabled development settings.	Available only for API 17 or5 higher.	No permissions required.
A091	HTTP_PROXY	Host name and port for global http proxy.	Available only for API 17 or higher.	No permissions required.
A092	NETWORK_PRE FERENCE	User preference for which networks should be used.	Available only for API 17 or higher.	No permissions required.
A093	STAY_ON_WHI LE_PLUGGED_ IN	Determines whether the device must remain switched on while it is plugged in.	Available only for API 17 or higher.	No permissions required.
A094	TRANSITION_ ANIMATION_S CALE	Scaling factor for activity transition animations.	Available only for API 17 or higher.	No permissions required.
A095	USB_MASS_ST ORAGE_ENABL ED	Indicates whether USB mass storage is enabled.	Available only for API 17 or higher.	No permissions required.
A096	USE_GOOGLE_ MAIL	If this setting is set (to anything), then all references to Gmail on the device must change to Google Mail.	Available only for API 17 or higher.	No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A097	WAIT_FOR_DE BUGGER	If 1, when launching DEBUG_APP it will wait for the debugger before starting user code.	Available only for API 17 or higher.	No permissions required.
A098	WIFI_NETWOR KS_AVAILABL E_NOTIFICAT ION_ON	Determines whether the end user should be notified of open networks.	Available only for API 17 or higher.	No permissions required.
Settings System		System settings, containing miscellaneous system preferences.		No permissions required.
A099	ACCELEROMET ER_ROTATION	Control whether the accelerometer will be used to change screen orientation.		No permissions required.
A100	BLUETOOTH_D ISCOVERABIL ITY	Determines whether remote devices may discover and/or connect to this device.		No permissions required.
A101	BLUETOOTH_D ISCOVERABIL ITY_TIMEOUT	Bluetooth discoverability timeout.		No permissions required.
A102	DATE_FORMAT	Date format string mm/dd/yyyy dd/mm/yyyy yyyy/mm/dd.		No permissions required.
A103	DTMF_TONE_T YPE_WHEN_DI ALING	CDMA only settings + DTMF tone type played by the dialer when dialing		No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A104	DTMF_TONE_W HEN_DIALING	Whether the audible DTMF tones are played by the dialer when dialing.		No permissions required.
A105	END_BUTTON_ BEHAVIOR	The behavior when the user presses the end call button if they're not on a call.		No permissions required.
A106	FONT_SCALE	Scaling factor for fonts, float.		No permissions required.
A107	HAPTIC_FEED BACK_ENABLE D	Whether the haptic feedback (long presses) is enabled.		No permissions required.
A108	MODE_RINGER _STREAMS_AF FECTED	Determines which streams are affected by ringer mode changes.		No permissions required.
A109	NOTIFICATIO N_SOUND	Persistent store for the system-wide default notification sound.		No permissions required.
A110	MUTE_STREAM S_AFFECTED	Determines which streams are affected by mute.		No permissions required.
A111	RINGTONE	Persistent store for the system-wide default ringtone URI.		No permissions required.
A112	SCREEN_BRIG HTNESS	The screen backlight brightness between 0 and 255.		No permissions required.
A113	SCREEN_BRIG HTNESS_MODE	Control whether to enable automatic brightness mode.		No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A114	SCREEN_OFF_ TIMEOUT	The amount of time in milliseconds before the device goes to sleep or begins to dream after a period of inactivity. This value is also known as the user activity timeout period since the screen isn't necessarily turned off when it expires.		No permissions required.
A115	SOUND_EFFEC TS_ENABLED	Whether sounds effects (key clicks, lid open) are enabled.		No permissions required.
A116	TEXT_AUTO_C APS	Setting to enable Auto Caps in text editors.		No permissions required.
A117	TEXT_AUTO_P UNCTUATE	Setting to enable Auto Punctuate in text editors		No permissions required.
A118	TEXT_AUTO_R EPLACE	Setting to enable Auto Replace (AutoText) in text editors.		No permissions required.
A119	TEXT_SHOW_P ASSWORD	Setting to showing password characters in text editors.		No permissions required.
A120	TIME_12_24	Display time in the 12-hour format or the 24-hour format.		No permissions required.
A121	USER_ROTATI ON	Default screen rotation when no other policy applies.		No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
A122	VIBRATE_ON	Whether vibrate is on for different events.		No permissions required.
A123	VIBRATE_WHE N_RINGING	Whether the phone vibrates when it is ringing during an incoming call.		No permissions required.
Package Manager		Package Manager is used to retrieve various kinds of information related to the application packages that are currently installed on the device.		No permissions required.
A124	isSafeMode	Returns whether the device has been booted into safe mode.		No permissions required.
A125	getInstalle dApplicatio ns	Returns a list of application packages that are installed on the device.		No permissions required.
A126	getInstalle rPackageNam e	Retrieves the package name of the application that installed a package. This identifies which market the package came from.		No permissions required.

Group or Identifier	Element	Description	Comments	Permissions
A127	getSystemAv ailableFeat ures	Retrieves a list of features that are available on the device.  The 3DS SDK shall share only the length of this list and not the full list itself.		No permissions required.
A128	getSystemSh aredLibrary Names	Retrieves a list of shared libraries that are available on the device.  The 3DS SDK shall share only the length of this list and not the full list itself.		No permissions required.
Environm ent		Environment provides access to environment variables.		No permissions required.
A129	getExternal StorageStat e	Returns the current state of the primary shared/external storage media.		No permissions required.
Locale		Represents a specific geographical, political, or cultural region.		No permissions required.
A130	getAvailabl eLocales	Returns the system's installed locales.  The 3DS SDK shall share only the length of this list and not the full list itself.		No permissions required.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="https://www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Element	Description	Comments	Permissions
DisplayM etrics		DisplayMetrics describes general information about a display, such as its size, density, and font scaling.		No permissions required.
A131	density	The logical density of the display.		No permissions required.
A132	densityDpi	The screen density expressed as dotsper-inch.		No permissions required.
A133	scaledDensi ty	A scaling factor for fonts displayed on the display.		No permissions required.
A134	xdpi	The exact physical pixels per inch of the screen in the X dimension.		No permissions required.
A135	ydpi	The exact physical pixels per inch of the screen in the Y dimension.		No permissions required.
StatFs		StatFs retrieves overall information about the space on a filesystem.		No permissions required.
A136	getTotalByt es	The total number of bytes supported by the filesystem.		No permissions required.

# 2.6 iOS-Specific Device Parameters

Table 2.4 provides information about the device parameters that shall be collected by the 3DS SDK from the iOS mobile platform for risk analysis by the ACS.

In this table, the Group or Identifier column contains the name of the parameter group or parameter identifier.

**Note:** The 3DS SDK does not require any permissions to collect these parameters.

**Note:** Each parameter listed in this table shall be collected by the 3DS SDK unless the parameter cannot be collected for any of the reasons stated in Table 2.6.

**Table 2.4: iOS-Specific Device Parameters** 

Group or Identifier	Attribute	Description
UIDevice		UIDevice provides a singleton instance representing the current device.
1001	Identifier For Vendor	Alphanumeric string that uniquely identifies a device to the app's vendor.
1002	UserInterfaceIdiom	Style of interface to use on the current device.
UIFont		UIFont provides the interface for getting and setting font information.
1003	familyNames	Returns an array of font family names available on the system.
1004	fontNamesForFamilyName	Returns an array of font names available in a particular font family using the system font family.
1005	systemFont	System font
1006	labelFontSize	Returns the standard font size used for labels.
1007	buttonFontSize	Returns the standard font size used for buttons.
1008	smallSystemFontSize	Returns the size of the standard small system font.
1009	systemFontSize	Returns the size of the standard system font.

<sup>© 2017</sup> EMVCo, LLC. All rights reserved. Reproduction, distribution and other use of this document is permitted only pursuant to the applicable agreement between the user and EMVCo found at <a href="www.emvco.com">www.emvco.com</a>. EMV<sup>®</sup> is a registered trademark or trademark of EMVCo, LLC in the United States and other countries.

Group or Identifier	Attribute	Description
NSLocale		NSLocale encapsulates all of the conventions about language and culture for a particular locale.
1010	systemLocale	Returns the ID of the generic locale that contains fixed "backstop" settings that provide values for otherwise undefined keys.
1011	availableLocaleIdentifie rs	Returns an array of NSString objects, each of which identifies a locale available on the system.
1012	preferredLanguages	Returns the user's language preference order as an array of strings.
NSTimeZone		NSTimeZone defines the behavior of time zone objects.
1013	defaultTimeZone	Returns the default time zone for the current application.

### 2.7 Windows 10 Mobile-Specific Device Parameters

Table 2.5 provides information about the device parameters that shall be collected by the 3DS SDK from the Windows 10 Mobile mobile platform for risk analysis by the ACS.

In this table, the Group or Identifier column contains the name of the parameter group or parameter identifier.

Note: The 3DS SDK does not require any permissions to collect these parameters.

**Note:** Each parameter listed in this table shall be collected by the 3DS SDK unless the parameter cannot be collected for any of the reasons stated in Table 2.6.

**Table 2.5: Windows 10 Mobile-Specific Device Parameters** 

Group or Identifier	Attribute	Description
Globalizati on Preferences		GlobalizationPreferences is used to obtain the user's globalization preferences.
W001	Calendars	Gets the set of calendars that are preferred by the user, in the order of preference.
W002	Clocks	Gets the set of clocks that are preferred by the user, in the order of preference.
W003	Currencies	Gets the set of currencies that are preferred by the user, in the order of preference.
W004	HomeGeographicRegion	Gets the user's home geographic region.
W005	Languages	Gets the set of languages preferred by the user, in the order of preference.
W006	WeekStartsOn	Gets the day of the week that is considered to be the first day of the week.
External Storage Device		
W007	ExternalStorageID	Gets the ID value that uniquely identifies the SD card.
AnalyticsIn fo		AnalyticsInfo provides information about the device for profiling purposes.
W008	DeviceForm	Gets the device form.
EasClientDe viceInforma tion		EasClientDeviceInformation provides apps the ability to retrieve device information from the local device.
W009	Id	Returns the identifier of the local device.

Group or Identifier	Attribute	Description
W010	SystemFirmwareVersio n	Returns the system firmware version of the local device.
W011	SystemHardwareVersio n	Returns the system hardware version of the local device.
W012	SystemManufacturer	Returns the system manufacturer of the local device.
W013	SystemProductName	Returns the system product name of the local device.
W014	SystemSku	Returns the system SKU of the local device.
DisplayInfo rmation		DisplayInformation monitors and controls physical display information.
W015	AutoRotationPreferen ces	Gets and sets the preferred orientation of the app.
W016	CurrentOrientation	Gets the current orientation of a rectangular monitor.
W017	LogicalDpi	Gets the pixels per logical inch of the current environment.
W018	NativeOrientation	Gets the native orientation of the display monitor, which is typically the orientation where the buttons on the device match the orientation of the monitor.
W019	RawDpiX	Gets the raw dots per inch (DPI) along the X-axis of the display monitor.
W020	RawDpiY	Gets the raw dots per inch (DPI) along the Y-axis of the display monitor.
W021	RawPixelsPerViewPixe	Gets a value representing the number of raw (physical) pixels for each view (layout) pixel.
W022	ResolutionScale	Gets the scale factor of the immersive environment.

Group or Identifier	Attribute	Description
W023	StereoEnabled	Gets a value that indicates whether the device supports stereoscopic 3D.
Network Information		Network Information provides access to network connection information for the local machine.
W024	GetNetworkNames	Retrieves names associated with the network with which the connection is currently established.
HostInforma tion		HostInformation provides access to a string that uniquely identifies a device per publisher.
W025	PublisherHostId	A string that uniquely identifies a device. This string is unique per device and per publisher, which means that no two publishers will receive the same value for the same device.

### 2.8 Reasons for Device Parameters Unavailability

Table 2.6 provides a list of reason codes and descriptions to address the unavailability of a device parameter. In case a 3DS SDK is unable to collect a particular device parameter, then the reason for the same shall be sent in the device parameters JSON with the key as "DPNA", as shown in the sample provided in Table 2.7.

**Table 2.6: Device Parameter Unavailability Reasons** 

Reason Code	Description
RE01	Market or regional restriction on the parameter.
RE02	Platform version does not support the parameter or the parameter has been deprecated.
RE03	Parameter collection not possible without prompting the user for permission.

### 2.9 Device Information JSON Data

Table 2.7 provides a sample device parameters JSON. As shown in the sample JSON, the following keys are used in conjunction with the keys for the device identification parameters:

- DV: Data Version
- DD: Device Data
- DPNA: Device Parameter Not Available
- SW: Security Warning. For information about Security Warning, refer to the EMV 3-D Secure SDK Specification.

**Table 2.7: Device Parameters JSON Structure** 

Platform	Device Information
Android	{"DV":"1.0", "DD": {"C001": "Android", "C002": "HTC One_M8", "C004": "5.0.1", "C005": "en_US", "C006": "Eastern Standard Time", "C007": "06797903-fb61-41ed-94c2-4d2b74e27d18", "C009": "John's Android Device",}, "DPNA": {"C010": "RE01", "C011": "RE03"}, "SW": ["SW01", "SW04"]}
iOS	{"DV":"1.0","DD":{"C001":"iOS","C002":"iPhone 5c","C003":" iPhone OS  ","C004":"9.2","C005":"en-US","C006":"GMT- 6","C009":"John's iPhone",},"  DPNA":{"C010":"RE01","C011":"RE03"},"SW":["SW0 1","SW04"]}
Windows 10 Mobile	{"DV":"1.0","DD":{"C001":"Windows","C002":"NOK IA RM- 984_1006","C003":"WindowPhone","C004":"10.0.10 586.11","C005":"en-US","C006":"(UTC-06:00) Central Time (US & Canada)","C007":"1bbd95da4520a6dfe7b94480d69f3 cbb","C008":"1280x720","C009":"My Phone",},"DPNA":{"C010":"RE02","C011":"RE0 3"},"SW":["SW01","SW04"]}



Page 40 / 39

\*\*\* END OF DOCUMENT \*\*\*