
3 Router Static Configuration



Router R1 configuration:

Router>enable

Router#conf t

Router(config)#hostname R1

R1(config)#interface fastEthernet 0/0

R1(config-if)#ip address 192.168.10.100 255.255.255.0

R1(config-if)#no shutdown

R1(config-if)#exit

R1(config)#interface fastEthernet 0/1

R1(config-if)#ip address 112.1.1.1 255.255.255.252

R1(config-if)#no shut

R1(config-if)#^Z

R1#wr

Building configuration...

[OK]

Router R2 config:

Router>en

Router#conf t

Router(config)#hostname R2

R2(config)#interface fa0/1

R2(config-if)#ip add 112.1.1.2 255.255.255.252

R2(config-if)#no shut

R2(config-if)#exit

R2(config)#interface fa0/0

R2(config-if)#ip add 192.168.20.100 255.255.255.0

R2(config-if)#no shut

R2(config-if)#exit

R2(config)#int fa1/0

R2(config-if)#ip add 113.1.1.1 255.255.255.252

R2(config-if)#no shut

R2(config-if)#exit

 $R2(config)\#^{Z}$

R2#wr

Building configuration...

[OK]

R2#

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

Router R3 config:

Router>en

Router#conf t

Router(config)#hostname R3

R3(config)#int fa0/1

R3(config-if)#ip add 113.1.1.2 255.255.255.252

R3(config-if)#no shut

R3(config-if)#exit

R3(config)#int fa0/0

R3(config-if)#ip add 192.168.30.100 255.255.255.0

R3(config-if)#no shut

R3(config-if)#^Z

R3#wr

Building configuration...

[OK]

R3#

To config static routing for Router R1:

R1#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R1(config)#ip route 192.168.20.0 255.255.255.0 112.1.1.2

R1(config)#ip route 192.168.30.0 255.255.255.0 112.1.1.2

R1(config)#ip route 113.1.1.0 255.255.255.252 112.1.1.2

R1(config)#^Z

R1#

%SYS-5-CONFIG I: Configured from console by console

R1#wr

Building configuration...

[OK]

R1#

To config static routing for Router R2:

R2#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R2(config)#

R2(config)#ip route 192.168.10.0 255.255.255.0 112.1.1.1

R2(config)#ip route 192.168.30.0 255.255.255.0 113.1.1.2

R2(config)#^Z

R2#

%SYS-5-CONFIG I: Configured from console by console

R2#wr

Building configuration...

[OK]

R2#

To config static routing for Router R3:

R3>

R3>en

R3#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R3(config)#ip route 192.168.10.0 255.255.255.0 113.1.1.1

R3(config)#ip route 192.168.20.0 255.255.255.0 113.1.1.1

R3(config)#ip route 112.1.1.0 255.255.255.252 113.1.1.1

R3(config)#^Z

R3#

%SYS-5-CONFIG I: Configured from console by console

R3#wr

Building configuration...

[OK]

R3#

