Configuring Basic MPLS Using OSPF

Document ID: 13736

Contents

Introduction

Prerequisites

Requirements

Components Used

Conventions

Mechanism

Configure

Network Diagram

Quick Configuration Guide

Configurations

Verify

Troubleshoot

Related Information

Introduction

This document shows how to configure a basic Multiprotocol Label Switching (MPLS) network. Refer to Configuration Examples and TechNotes on the MPLS Support Page for more information on how to configure advanced topics such as VPN or Traffic Engineering (TE).

Prerequisites

Requirements

Cisco recommends that you are familiar with the basic operation of MPLS. Refer to Multiprotocol Label Switching Overview for an overview of MPLS.

Components Used

The information in this document is based on these software and hardware versions:

- Cisco IOS® Software Releases 12.2(28)
- Cisco 3600 routers

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, make sure that you understand the potential impact of any command.

Conventions

Refer to Cisco Technical Tips Conventions for more information on document conventions.

Mechanism

An MPLS network is commonly a backbone network comprised of MPLS—enabled routers called Label Switch Routers (LSR). Generally, the network consists of a core LSR with an edge LSR that applies labels to packets.


This is the setup mechanism of an MPLS network:

- 1. Routing tables of the different LSRs are computed with an Interior Gateway Protocol (IGP). A link-state protocol, such as Open Shortest Path First (OSPF) or Intermediate System-to-Intermediate System (IS-IS), is required if you plan to deploy MPLS TE.
- 2. A label distribution protocol (LDP) advertises the bindings between routes and labels. These bindings are checked against the routing table. If the route (prefix/mask and next hop) learned from the LDP matches the route learned from IGP in the routing table, an entry is created in the label that forwards information bases (LFIB) on the LSR.

The LSR uses this forwarding mechanism:

- 1. Once an edge LSR receives an unlabelled packet, the Cisco Express Forwarding table is checked and a label is imposed on the packet if needed. This LSR is called the ingress LSR.
- 2. Upon the arrival of a labelled packet at the inbound interface of a core LSR, the LFIB provides the outbound interface and the new label that is associated with the outbound packet.
- 3. The router before the last LSR (the penultimate hop) pops the label and transmits the packet without the label. The last hop is called the egress LSR.

This diagram illustrates this network setup:




Configure

In this section, you are presented with the information to configure the features described in this document.

Note: In order fo find additional information on the commands used in this document, use the Command Lookup Tool (registered customers only).

Network Diagram

This document uses this network setup:



Quick Configuration Guide

Use this procedure as a quick configuration guide.

- 1. Set up your network as usual. MPLS needs a standard IP connection in order to establish forwarding bases.
- 2. Ensure that the routing protocol (OSPF or IS–IS) works correctly. These commands are italicized in the configurations in the next section.
- 3. Enable **ip cef**, for better performances use **ip cef distributed** when available, in the general configuration mode. This is shown in bold in the configurations in the next section.
- 4. Enable **mpls ip**, or **tag–switching ip** on older Cisco IOS software releases, in the general configuration mode and in each interface, as shown in bold in the configurations in the next section. Even when the **mpls ip** command is used, the **show running** output can still show the command as **tag–switching ip** in some Cisco IOS software releases, as shown in the configurations in the next section.

Note: The LSRs must have (up) Loopback interfaces with an address mask of 32 bits and these interfaces must be reachable with the global IP routing table.

Configurations

This document uses these configurations:

- Pomerol
- Pulligny
- Pauillac
- Pescara
- Pesaro
- Perugia

```
version 12.2
hostname Pomerol
ip subnet-zero
ip cef
interface Loopback0
ip address 10.10.10.3 255.255.255.255
interface Serial2/0
ip address 10.1.1.21 255.255.255.252
mpls ip
interface Serial3/0
ip address 10.1.1.6 255.255.255.252
mpls ip
interface Serial4/0
ip address 10.1.1.9 255.255.255.252
mpls ip
router ospf 10
log-adjacency-changes
network 10.0.0.0 0.255.255.255 area 9
ip classless
end
```

Pulligny

```
version 12.2
hostname Pulligny
ip subnet-zero
ip cef
interface Loopback0
ip address 10.10.10.2 255.255.255.255
interface Serial2/0
ip address 10.1.1.2 255.255.255.252
mpls ip
interface Serial3/0
ip address 10.1.1.10 255.255.255.252
mpls ip
router ospf 10
log-adjacency-changes
network 10.0.0.0 0.255.255.255 area 9
ip classless
!
end
```

Pauillac version 12.2 hostname Pauillac ip subnet-zero ip cef ! interface Loopback0 ip address 10.10.10.1 255.255.255.255 interface Serial2/0 ip address 10.1.1.13 255.255.255.252 mpls ip interface Serial3/0 ip address 10.1.1.17 255.255.255.252 mpls ip interface Serial4/0 ip address 10.1.1.1 255.255.255.252 mpls ip interface Serial5/0 ip address 10.1.1.5 255.255.255.252 mpls ip router ospf 10 log-adjacency-changes

Pescara

network 10.0.0.0 0.255.255.255 area 9

ip classless

end

```
!
version 12.2
!
hostname Pescara
!
ip subnet-zero
!
ip cef
!
interface Loopback0
  ip address 10.10.10.4 255.255.255.255
!
interface Serial2/0
  ip address 10.1.1.14 255.255.255.252
mpls ip
!
router ospf 10
  log-adjacency-changes
  network 10.0.0.0 0.255.255.255 area 9
!
ip classless
!
end
```

```
Pesaro
version 12.2
hostname Pesaro
ip subnet-zero
ip cef
!
interface Loopback0
ip address 10.10.10.6 255.255.255.255
interface Serial2/0
ip address 10.1.1.22 255.255.255.252
mpls ip
router ospf 10
log-adjacency-changes
network 10.0.0.0 0.255.255.255 area 9
ip classless
end
```

```
Perugia

!
version 12.2
!
hostname Perugia
!
ip subnet-zero
!
ip cef
!
interface Loopback0
ip address 10.10.10.5 255.255.255.255
!
interface Serial2/0
ip address 10.1.1.18 255.255.255.252
mpls ip
!
router ospf 10
log-adjacency-changes
network 10.0.0.0 0.255.255.255 area 9
!
ip classless
!
end
```

Verify

This section provides information you can use to confirm your configuration works properly.

Commands used in the Configuring Basic MPLS Using IS-IS sample configuration are also applicable.

In order to illustrate this sample configuration, look at a particular destination, for example **10.10.10.4**, on the **Pomerol** LSR.

Certain **show** commands are supported by the Output Interpreter Tool (registered customers only), which allows you to view an analysis of **show** command output.

• show ip route Used to check the IP route for this destination in the IP routing table:

```
Pomerol#show ip route 10.10.10.4
Routing entry for 10.10.10.4/32
  Known via "ospf 10", distance 110, metric 129, type intra area
  Last update from 10.1.1.5 on Serial3/0, 17:29:23 ago
  Routing Descriptor Blocks:
  * 10.1.1.5, from 10.10.10.4, 17:29:23 ago, via Serial3/0
       Route metric is 129, traffic share count is 1
```

• show mpls forwarding—table Used to check the MPLS forwarding table, which is the label switching equivalent of the IP routing table for standard IP routing. It contains inbound and outbound labels and descriptions of the packets.

Pomero	l#show mpls	forwarding-table			
Local	Outgoing	Prefix	Bytes tag	Outgoing	Next Hop
tag	tag or VC	or Tunnel Id	switched	interface	
16	Pop tag	10.1.1.12/30	636	Se3/0	point2point
17	Pop tag	10.10.10.1/32	0	Se3/0	point2point
18	21	10.10.10.4/32	0	Se3/0	point2point
19	Pop tag	10.1.1.0/30	0	Se4/0	point2point
	Pop tag	10.1.1.0/30	0	Se3/0	point2point
20	Pop tag	10.10.10.6/32	612	Se2/0	point2point
21	Pop tag	10.1.1.16/30	0	Se3/0	point2point
22	16	10.10.10.5/32	0	Se3/0	point2point
23	Pop tag	10.10.10.2/32	0	Se4/0	point2point

• show mpls forwarding-table detail Used to see MPLS forwarding table details:

```
Pomerol#show mpls forwarding-table 10.10.10.4 32 detail

Local Outgoing Prefix Bytes tag Outgoing Next Hop

tag tag or VC or Tunnel Id switched interface

18 21 10.10.10.4/32 0 Se3/0 point2point

MAC/Encaps=4/8, MRU=1500, Tag Stack{21}

0F008847 00015000

No output feature configured

Per-packet load-sharing
```

• show mpls ldp bindings or show tag—switching tdp bindings (based on which Cisco IOS software release you use) Used to see the label bindings associated with a particular destination. Both the local as well as the remote bindings can be seen.

```
Pomerol#show mpls tdp bindings 10.10.10.4 32
tib entry: 10.10.10.4/32, rev 14
    local binding: tag: 18
    remote binding: tsr: 10.10.10.1:0, tag: 21
    remote binding: tsr: 10.10.10.2:0, tag: 23
    remote binding: tsr: 10.10.10.6:612, tag: 20
```

• **show ip cef detail** Used to check that Cisco Express Forwarding works properly and that tags are swapped correctly:

```
Pomerol#show ip cef 10.10.10.4 detail
10.10.10.4/32, version 37, cached adjacency to Serial3/0
0 packets, 0 bytes
tag information set
```

```
local tag: 18
fast tag rewrite with Se3/0, point2point, tags imposed: {21}
via 10.1.1.5, Serial3/0, 0 dependencies
next hop 10.1.1.5, Serial3/0
valid cached adjacency
tag rewrite with Se3/0, point2point, tags imposed: {21}
```

Troubleshoot

Refer to MPLS Troubleshooting for information on how to troubleshoot MPLS.

Related Information

- Configuring Basic MPLS Using IS-IS
- Configuring Multiprotocol Label Switching
- Configuring a Basic MPLS VPN
- MPLS Technology Support Page
- Technical Support Cisco Systems

Contacts & Feedback | Help | Site Map

© 2014 – 2015 Cisco Systems, Inc. All rights reserved. Terms & Conditions | Privacy Statement | Cookie Policy | Trademarks of Cisco Systems, Inc.

Updated: Aug 10, 2005 Document ID: 13736