#### **NAME**

matherr - SVID math library exception handling

## **SYNOPSIS**

#include <math.h>

int matherr(struct exception \*exc);

extern \_LIB\_VERSION\_TYPE \_LIB\_VERSION;

Link with -lm.

#### DESCRIPTION

*Note*: the mechanism described in this page is no longer supported by glibc. Before glibc 2.27, it had been marked as obsolete. Since glibc 2.27, the mechanism has been removed altogether. New applications should use the techniques described in **math\_error**(7) and **fenv**(3). This page documents the **matherr**() mechanism as an aid for maintaining and porting older applications.

The System V Interface Definition (SVID) specifies that various math functions should invoke a function called **matherr**() if a math exception is detected. This function is called before the math function returns; after **matherr**() returns, the system then returns to the math function, which in turn returns to the caller.

To employ **matherr**(), the programmer must define the \_SVID\_SOURCE feature test macro (before including *any* header files), and assign the value \_SVID\_ to the external variable \_LIB\_VERSION.

The system provides a default version of **matherr**(). This version does nothing, and returns zero (see below for the significance of this). The default **matherr**() can be overridden by a programmer-defined version, which will be invoked when an exception occurs. The function is invoked with one argument, a pointer to an *exception* structure, defined as follows:

The *type* field has one of the following values:

**DOMAIN** A domain error occurred (the function argument was outside the range for which the function is defined). The return value depends on the function; *errno* is set to **EDOM**.

SING A pole error occurred (the function result is an infinity). The return value in most cases is **HUGE** (the largest single precision floating-point number), appropriately signed. In most cases, *errno* is set to **EDOM**.

#### **OVERFLOW**

An overflow occurred. In most cases, the value **HUGE** is returned, and *errno* is set to **ERANGE**.

#### **UNDERFLOW**

An underflow occurred. 0.0 is returned, and *errno* is set to **ERANGE**.

**TLOSS** Total loss of significance. 0.0 is returned, and *errno* is set to **ERANGE**.

**PLOSS** Partial loss of significance. This value is unused on glibc (and many other systems).

The *arg1* and *arg2* fields are the arguments supplied to the function (*arg2* is undefined for functions that take only one argument).

The *retval* field specifies the return value that the math function will return to its caller. The programmer-defined **matherr**() can modify this field to change the return value of the math function.

If the **matherr**() function returns zero, then the system sets *errno* as described above, and may print an error message on standard error (see below).

If the matherr() function returns a nonzero value, then the system does not set errno, and doesn't print an error message.

#### **Math functions that employ matherr()**

The table below lists the functions and circumstances in which matherr() is called. The "Type" column indicates the value assigned to exc->type when calling matherr(). The "Result" column is the default return value assigned to *exc->retval*.

The "Msg?" and "errno" columns describe the default behavior if matherr() returns zero. If the "Msg?" columns contains "y", then the system prints an error message on standard error.

The table uses the following notations and abbreviations:

- first argument to function X second argument to function finite value for argument fin
- neg negative value for argument int integral value for argument
- o/f result overflowed u/f result underflowed  $|\mathbf{x}|$ absolute value of x

X\_TLOSS is a constant defined in <math.h>

Function	Type	Result	Msg?	errno
acos( x >1)	DOMAIN	HUGE	y	EDOM
asin( x >1)	DOMAIN	HUGE	y	EDOM
atan2(0,0)	DOMAIN	HUGE	y	EDOM
$a\cosh(x<1)$	DOMAIN	NAN	y	EDOM
atanh( x >1)	DOMAIN	NAN	y	EDOM
atanh( x ==1)	SING	(x>0.0)?	y	EDOM
		HUGE_VAL : -HUGE_VAL		
cosh(fin) o/f	OVERFLOW	HUGE	n	<b>ERANGE</b>
sinh(fin) o/f	OVERFLOW	(x>0.0)?	n	<b>ERANGE</b>
		HUGE: -HUGE		
sqrt(x<0)	DOMAIN	0.0	y	EDOM
hypot(fin,fin) o/f	OVERFLOW	HUGE	n	<b>ERANGE</b>
exp(fin) o/f	OVERFLOW	HUGE	n	<b>ERANGE</b>
exp(fin) u/f	UNDERFLOW	0.0	n	<b>ERANGE</b>
exp2(fin) o/f	OVERFLOW	HUGE	n	<b>ERANGE</b>
exp2(fin) u/f	UNDERFLOW	0.0	n	<b>ERANGE</b>
exp10(fin) o/f	<b>OVERFLOW</b>	HUGE	n	<b>ERANGE</b>
exp10(fin) u/f	UNDERFLOW	0.0	n	<b>ERANGE</b>
$j0( x >X_TLOSS)$	TLOSS	0.0	y	<b>ERANGE</b>
$j1( x >X_TLOSS)$	TLOSS	0.0	y	<b>ERANGE</b>
$jn( x >X_TLOSS)$	TLOSS	0.0	y	<b>ERANGE</b>
$y0(x>X_TLOSS)$	TLOSS	0.0	y	<b>ERANGE</b>
$y1(x>X_TLOSS)$	TLOSS	0.0	y	<b>ERANGE</b>
$yn(x>X_TLOSS)$	TLOSS	0.0	y	<b>ERANGE</b>
y0(0)	DOMAIN	-HUGE	y	EDOM
y0(x<0)	DOMAIN	-HUGE	y	EDOM
y1(0)	DOMAIN	-HUGE	y	EDOM
y1(x<0)	DOMAIN	-HUGE	y	EDOM
yn(n,0)	DOMAIN	-HUGE	y	EDOM
yn(x<0)	DOMAIN	-HUGE	y	EDOM
lgamma(fin) o/f	OVERFLOW	HUGE	n	ERANGE

lgamma(-int) or	SING	HUGE	y	EDOM
lgamma(0)				
tgamma(fin) o/f	OVERFLOW	HUGE_VAL	n	ERANGE
tgamma(-int)	SING	NAN	y	EDOM
tgamma(0)	SING	copysign(	y	ERANGE
		$HUGE_VAL,x)$		
log(0)	SING	-HUGE	y	EDOM
log(x<0)	DOMAIN	-HUGE	y	EDOM
log2(0)	SING	-HUGE	n	EDOM
log2(x<0)	DOMAIN	-HUGE	n	EDOM
log10(0)	SING	-HUGE	y	EDOM
log10(x<0)	DOMAIN	-HUGE	y	EDOM
pow(0.0,0.0)	DOMAIN	0.0	y	EDOM
pow(x,y) o/f	OVERFLOW	HUGE	n	ERANGE
pow(x,y) u/f	UNDERFLOW	0.0	n	ERANGE
pow(NaN,0.0)	DOMAIN	X	n	<b>EDOM</b>
0**neg	DOMAIN	0.0	y	<b>EDOM</b>
neg**non-int	DOMAIN	0.0	y	EDOM
scalb() o/f	OVERFLOW	(x>0.0) ?	n	ERANGE
		HUGE_VAL:		
		-HUGE_VAL		
scalb() u/f	UNDERFLOW	copysign(	n	<b>ERANGE</b>
		0.0,x)		
fmod(x,0)	DOMAIN	X	y	EDOM
remainder(x,0)	DOMAIN	NAN	У	EDOM

#### **ATTRIBUTES**

For an explanation of the terms used in this section, see **attributes**(7).

Interface Attribute		Value	
matherr()	Thread safety	MT-Safe	

## **EXAMPLE**

The example program demonstrates the use of **matherr**() when calling **log**(3). The program takes up to three command-line arguments. The first argument is the floating-point number to be given to **log**(3). If the optional second argument is provided, then **\_LIB\_VERSION** is set to **\_SVID\_** so that **matherr**() is called, and the integer supplied in the command-line argument is used as the return value from **matherr**(). If the optional third command-line argument is supplied, then it specifies an alternative return value that **matherr**() should assign as the return value of the math function.

The following example run, where **log**(3) is given an argument of 0.0, does not use **matherr**():

In the following run, **matherr**() is called, and returns 0:

The message "log: SING error" was printed by the C library.

In the following run, **matherr**() is called, and returns a nonzero value:

```
$ ./a.out 0.0 1
```

```
matherr SING exception in log() function

args: 0.000000, 0.000000

retval: -340282346638528859811704183484516925440.000000

x=-340282346638528859811704183484516925440.000000
```

In this case, the C library did not print a message, and *errno* was not set.

In the following run, **matherr**() is called, changes the return value of the math function, and returns a non-zero value:

## \$ ./a.out 0.0 1 12345.0

```
matherr SING exception in log() function args: 0.000000, 0.000000 retval: -340282346638528859811704183484516925440.000000 x=12345.000000
```

### **Program source**

```
#define _SVID_SOURCE
#include <errno.h>
#include <math.h>
#include <stdio.h>
#include <stdlib.h>
static int matherr_ret = 0; /* Value that matherr()
                                    should return */
static int change_retval = 0;  /* Should matherr() change
                                    function's return value? */
static double new_retval; /* New function return value */
matherr(struct exception *exc)
    fprintf(stderr, "matherr %s exception in %s() function\n",
            (exc->type == DOMAIN) ? "DOMAIN" :
            (exc->type == OVERFLOW) ? "OVERFLOW" :
            (exc->type == UNDERFLOW) ? "UNDERFLOW" :
           (exc->type == SING) ? "SING" :
(exc->type == TLOSS) ? "TLOSS" :
(exc->type == PLOSS) ? "PLOSS" : "???",
            exc->name);
    fprintf(stderr, "
                             args: %f, %f\n",
            exc->arg1, exc->arg2);
    fprintf(stderr, "
                             retval: %f\n", exc->retval);
    if (change_retval)
        exc->retval = new_retval;
    return matherr_ret;
}
main(int argc, char *argv[])
    double x;
```

```
if (argc < 2) {
        fprintf(stderr, "Usage: %s <argval>"
                " [<matherr-ret> [<new-func-retval>]]\n", argv[0]);
        exit(EXIT_FAILURE);
    if (argc > 2) {
       _LIB_VERSION = _SVID_;
       matherr_ret = atoi(argv[2]);
    }
    if (argc > 3) {
       change_retval = 1;
       new_retval = atof(argv[3]);
    }
    x = log(atof(argv[1]));
   if (errno != 0)
        perror("errno");
    printf("x=%f\n", x);
    exit(EXIT_SUCCESS);
}
```

### **SEE ALSO**

 $fenv(3), math\_error(7), standards(7)$ 

# **COLOPHON**

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.