NAME

mysqlshow - display database, table, and column information

SYNOPSIS

mysqlshow [options] [db_name [tbl_name [col_name]]]

DESCRIPTION

The mysqlshow client can be used to quickly see which databases exist, their tables, or a table's columns or indexes.

mysqlshow provides a command-line interface to several SQL SHOW statements. See Section 13.7.7, "SHOW Syntax". The same information can be obtained by using those statements directly. For example, you can issue them from the **mysql** client program.

Invoke **mysqlshow** like this:

shell> mysqlshow [options] [db_name [tbl_name [col_name]]]

- If no database is given, a list of database names is shown.
- If no table is given, all matching tables in the database are shown.
- If no column is given, all matching columns and column types in the table are shown.

The output displays only the names of those databases, tables, or columns for which you have some privileges.

If the last argument contains shell or SQL wildcard characters (*, ?, %, or _), only those names that are matched by the wildcard are shown. If a database name contains any underscores, those should be escaped with a backslash (some Unix shells require two) to get a list of the proper tables or columns. * and ? characters are converted into SQL % and _ wildcard characters. This might cause some confusion when you try to display the columns for a table with a _ in the name, because in this case, mysqlshow shows you only the table names that match the pattern. This is easily fixed by adding an extra % last on the command line as a separate argument.

mysqlshow supports the following options, which can be specified on the command line or in the [mysqlshow] and [client] groups of an option file. For information about option files used by MySQL programs, see Section 4.2.2.2, "Using Option Files".

• --help, -?

Display a help message and exit.

• --bind-address=ip address

On a computer having multiple network interfaces, use this option to select which interface to use for connecting to the MySQL server.

• --character-sets-dir=dir_name

The directory where character sets are installed. See Section 10.15, "Character Set Configuration".

• --compress, -C

Compress all information sent between the client and the server if possible. See Section 4.2.6, "Connection Compression Control".

As of MySQL 8.0.18, this option is deprecated. It will be removed in a future MySQL version. See the section called "Legacy Connection Compression Configuration".

--compression-algorithms=*value* The permitted compression algorithms for connections to the server. The available algorithms are the same as for the protocol_compression_algorithms system variable. The default value is uncompressed.

For more information, see Section 4.2.6, "Connection Compression Control".

This option was added in MySQL 8.0.18.

--count

Show the number of rows per table. This can be slow for non-MyISAM tables.

• **--debug**[=debug_options], **-#** [debug_options]

Write a debugging log. A typical *debug_options* string is d:t:o,*file_name*. The default is d:t:o.

· --debug-check

Print some debugging information when the program exits.

· --debug-info

Print debugging information and memory and CPU usage statistics when the program exits.

• --default-character-set=charset_name

Use charset_name as the default character set. See Section 10.15, "Character Set Configuration".

• --default-auth=plugin

A hint about which client–side authentication plugin to use. See Section 6.2.17, "Pluggable Authentication".

• --defaults-extra-file=file name

Read this option file after the global option file but (on Unix) before the user option file. If the file does not exist or is otherwise inaccessible, an error occurs. *file_name* is interpreted relative to the current directory if given as a relative path name rather than a full path name.

For additional information about this and other option–file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• **--defaults-file=***file_name*

Use only the given option file. If the file does not exist or is otherwise inaccessible, an error occurs. *file_name* is interpreted relative to the current directory if given as a relative path name rather than a full path name.

Exception: Even with **--defaults-file**, client programs read .mylogin.cnf.

For additional information about this and other option–file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• --defaults-group-suffix=str

Read not only the usual option groups, but also groups with the usual names and a suffix of *str*. For example, **mysqlshow** normally reads the [client] and [mysqlshow] groups. If the **—defaults-group-suffix=_other** option is given, **mysqlshow** also reads the [client_other] and [mysqlshow_other] groups.

For additional information about this and other option–file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• --enable-cleartext-plugin

Enable the mysql_clear_password cleartext authentication plugin. (See Section 6.4.1.4, "Client-Side Cleartext Pluggable Authentication".)

• --get-server-public-key

Request from the server the RSA public key that it uses for key pair—based password exchange. This option applies to clients that connect to the server using an account that authenticates with the caching_sha2_password authentication plugin. For connections by such accounts, the server does not send the public key to the client unless requested. The option is ignored for accounts that do not authenticate with that plugin. It is also ignored if RSA—based password exchange is not needed, as is the case when the client connects to the server using a secure connection.

If **—-server-public-key-path**=*file_name* is given and specifies a valid public key file, it takes precedence over **—-get-server-public-key**.

For information about the caching_sha2_password plugin, see Section 6.4.1.3, "Caching SHA-2 Pluggable Authentication".

• **--host**=host_name, **-h** host_name

Connect to the MySQL server on the given host.

• --kevs, -k

Show table indexes.

• --login-path=name

Read options from the named login path in the .mylogin.cnf login path file. A "login path" is an option group containing options that specify which MySQL server to connect to and which account to authenticate as. To create or modify a login path file, use the **mysql_config_editor** utility. See **mysql_config_editor**(1).

For additional information about this and other option—file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• --no-defaults

Do not read any option files. If program startup fails due to reading unknown options from an option file, **—-no-defaults** can be used to prevent them from being read.

The exception is that the .mylogin.cnf file, if it exists, is read in all cases. This permits passwords to be specified in a safer way than on the command line even when **—no–defaults** is used. (.mylogin.cnf is created by the **mysql_config_editor** utility. See **mysql_config_editor**(1).)

For additional information about this and other option–file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• --password[=password], -p[password]

The password of the MySQL account used for connecting to the server. The password value is optional. If not given, **mysqlshow** prompts for one. If given, there must be *no space* between **—password=** or **–p** and the password following it. If no password option is specified, the default is to send no password.

Specifying a password on the command line should be considered insecure. To avoid giving the

password on the command line, use an option file. See Section 6.1.2.1, "End-User Guidelines for Password Security".

To explicitly specify that there is no password and that **mysqlshow** should not prompt for one, use the **—-skip-password** option.

• --pipe, -W

On Windows, connect to the server using a named pipe. This option applies only if the server was started with the named_pipe system variable enabled to support named_pipe connections. In addition, the user making the connection must be a member of the Windows group specified by the named_pipe_full_access_group system variable.

• --plugin-dir=dir_name

The directory in which to look for plugins. Specify this option if the **—default—auth** option is used to specify an authentication plugin but **mysqlshow** does not find it. See Section 6.2.17, "Pluggable Authentication".

• --port=port_num, -P port_num

For TCP/IP connections, the port number to use.

• --print-defaults

Print the program name and all options that it gets from option files.

For additional information about this and other option–file options, see Section 4.2.2.3, "Command-Line Options that Affect Option-File Handling".

• --protocol={TCP|SOCKET|PIPE|MEMORY}

The connection protocol to use for connecting to the server. It is useful when the other connection parameters normally result in use of a protocol other than the one you want. For details on the permissible values, see Section 4.2.4, "Connecting to the MySQL Server Using Command Options".

• --secure-auth

This option was removed in MySQL 8.0.3.

• --server-public-key-path=file_name

The path name to a file containing a client–side copy of the public key required by the server for RSA key pair–based password exchange. The file must be in PEM format. This option applies to clients that authenticate with the sha256_password or caching_sha2_password authentication plugin. This option is ignored for accounts that do not authenticate with one of those plugins. It is also ignored if RSA-based password exchange is not used, as is the case when the client connects to the server using a secure connection.

If **—-server-public-key-path**=*file_name* is given and specifies a valid public key file, it takes precedence over **—-get-server-public-key**.

For sha256_password, this option applies only if MySQL was built using OpenSSL.

For information about the sha256_password and caching_sha2_password plugins, see Section 6.4.1.2, "SHA-256 Pluggable Authentication", and Section 6.4.1.3, "Caching SHA-2 Pluggable Authentication".

• --shared-memory-base-name=name

On Windows, the shared–memory name to use for connections made using shared memory to a local server. The default value is MYSQL. The shared–memory name is case–sensitive.

This option applies only if the server was started with the shared_memory system variable enabled to support shared—memory connections.

• --show-table-type, -t

Show a column indicating the table type, as in SHOW FULL TABLES. The type is BASE TABLE or VIEW.

• --socket=path, -S path

For connections to localhost, the Unix socket file to use, or, on Windows, the name of the named pipe to use.

On Windows, this option applies only if the server was started with the named_pipe system variable enabled to support named_pipe connections. In addition, the user making the connection must be a member of the Windows group specified by the named_pipe_full_access_group system variable.

--ssl*

Options that begin with **—-ssl** specify whether to connect to the server using SSL and indicate where to find SSL keys and certificates. See the section called "Command Options for Encrypted Connections".

• —ssl-fips-mode={OFF|ON|STRICT} Controls whether to enable FIPS mode on the client side. The —ssl-fips-mode option differs from other —ssl-xxx options in that it is not used to establish encrypted connections, but rather to affect which cryptographic operations are permitted. See Section 6.5, "FIPS Support".

These **--ssl-fips-mode** values are permitted:

- OFF: Disable FIPS mode.
- ON: Enable FIPS mode.
- STRICT: Enable "strict" FIPS mode.

Note

If the OpenSSL FIPS Object Module is not available, the only permitted value for **—-ssl-fips-mode** is OFF. In this case, setting **—-ssl-fips-mode** to ON or STRICT causes the client to produce a warning at startup and to operate in non–FIPS mode.

• --status, -i

Display extra information about each table.

• --tls-ciphersuites=ciphersuite_list

The permissible ciphersuites for encrypted connections that use TLSv1.3. The value is a list of one or more colon–separated ciphersuite names. The ciphersuites that can be named for this option depend on the SSL library used to compile MySQL. For details, see Section 6.3.2, "Encrypted Connection TLS Protocols and Ciphers".

This option was added in MySQL 8.0.16.

• --tls-version=protocol_list

The permissible TLS protocols for encrypted connections. The value is a list of one or more comma–separated protocol names. The protocols that can be named for this option depend on the SSL library used to compile MySQL. For details, see Section 6.3.2, "Encrypted Connection TLS Protocols and Ciphers".

• --user=user_name, -u user_name

The user name of the MySQL account to use for connecting to the server.

• --verbose, -v

Verbose mode. Print more information about what the program does. This option can be used multiple times to increase the amount of information.

· --version, -V

Display version information and exit.

• —zstd—compression—level=level The compression level to use for connections to the server that use the zstd compression algorithm. The permitted levels are from 1 to 22, with larger values indicating increasing levels of compression. The default zstd compression level is 3. The compression level setting has no effect on connections that do not use zstd compression.

For more information, see Section 4.2.6, "Connection Compression Control".

This option was added in MySQL 8.0.18.

COPYRIGHT

Copyright © 1997, 2019, Oracle and/or its affiliates. All rights reserved.

This documentation is free software; you can redistribute it and/or modify it only under the terms of the GNU General Public License as published by the Free Software Foundation; version 2 of the License.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with the program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA or see http://www.gnu.org/licenses/.

SEE ALSO

For more information, please refer to the MySQL Reference Manual, which may already be installed locally and which is also available online at http://dev.mysql.com/doc/.

AUTHOR

Oracle Corporation (http://dev.mysql.com/).