NAME

strcasecmp, strncasecmp - compare two strings ignoring case

SYNOPSIS

#include <strings.h>

int streasecmp(const char *s1, const char *s2);

int strncasecmp(const char *s1, const char *s2, size_t n);

DESCRIPTION

The **strcasecmp**() function performs a byte-by-byte comparison of the strings s1 and s2, ignoring the case of the characters. It returns an integer less than, equal to, or greater than zero if s1 is found, respectively, to be less than, to match, or be greater than s2.

The **strncasecmp**() function is similar, except that it compares no more than n bytes of s1 and s2.

RETURN VALUE

The **strcasecmp**() and **strncasecmp**() functions return an integer less than, equal to, or greater than zero if sI is, after ignoring case, found to be less than, to match, or be greater than s2, respectively.

ATTRIBUTES

For an explanation of the terms used in this section, see **attributes**(7).

| Interface | Attribute | Value |
|-----------------------------|---------------|----------------|
| strcasecmp(), strncasecmp() | Thread safety | MT-Safe locale |

CONFORMING TO

4.4BSD, POSIX.1-2001, POSIX.1-2008.

NOTES

The **strcasecmp**() and **strncasecmp**() functions first appeared in 4.4BSD, where they were declared in <*string.h>*. Thus, for reasons of historical compatibility, the glibc <*string.h>* header file also declares these functions, if the **_DEFAULT_SOURCE** (or, in glibc 2.19 and earlier, **_BSD_SOURCE**) feature test macro is defined.

The POSIX.1-2008 standard says of these functions:

When the LC_CTYPE category of the locale being used is from the POSIX locale, these functions shall behave as if the strings had been converted to lowercase and then a byte comparison performed. Otherwise, the results are unspecified.

SEE ALSO

bcmp(3), memcmp(3), strcmp(3), strcoll(3), string(3), strncmp(3), wescasecmp(3), wescasecmp(3)

COLOPHON

This page is part of release 5.02 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

2017-09-15