

ARMIS Platform

REST API Reference — v2.4

1. Base URL & Versioning

All API endpoints are served through the API Gateway. The base URL for all requests:

- Production: <https://api.armis.defencetech.com.tr/v2>
- Staging: <https://api-staging.armis.defencetech.com.tr/v2>
- Local development: <http://localhost:8080/v2>

API versioning is path-based (/v2). The /v1 prefix is deprecated and will be removed in Q4 2026.

2. Authentication

2.1 Obtaining a Token

POST /v2/auth/login

Request body:

```
{ "username": "operator1", "password": "your_password" }
```

Success response (200 OK):

```
{ "accessToken": "eyJhbGciOi...", "refreshToken": "eyJhbGciOi...", "expiresIn": 28800 }
```

2.2 Using the Token

Include the accessToken as a Bearer token in the Authorization header of every request:

```
Authorization: Bearer eyJhbGciOi...
```

2.3 Refreshing a Token

POST /v2/auth/refresh

Request body:

```
{ "refreshToken": "eyJhbGciOi..." }
```

Returns a new accessToken. If the refreshToken is expired or invalid, returns 401 and the user must log in again.

2.4 Why Does My Request Return 403?

A 403 Forbidden means the token is valid but the user lacks the required role for the endpoint. Common causes:

- Trying to create or approve a mission as ROLE_VIEWER — only ROLE_OPERATOR and ROLE_ADMIN can do this

- Trying to access admin-only endpoints (e.g., POST /v2/users) as ROLE_OPERATOR
 - Token was issued before a role change — obtain a new token after role changes
- A 401 Unauthorized means the token is missing, expired, or malformed.

3. Asset Endpoints

Method	Path	Role Required	Description
GET	/v2/assets	VIEWER+	List all assets with pagination
GET	/v2/assets/{id}	VIEWER+	Get single asset by ID
POST	/v2/assets	OPERATOR+	Register a new asset
PUT	/v2/assets/{id}	OPERATOR+	Update asset metadata
DELETE	/v2/assets/{id}	ADMIN	Deregister an asset
GET	/v2/assets/{id}/location	VIEWER+	Get current location
GET	/v2/assets/{id}/track	VIEWER+	Get location history
WS	/v2/assets/stream	VIEWER+	WebSocket: live location stream

3.1 List Assets

GET /v2/assets?page=0&size=20&type=VEHICLE

Query parameters:

- page (integer, default 0) — zero-based page index
- size (integer, default 20, max 100) — items per page
- type (string, optional) — filter by asset type: VEHICLE, PERSONNEL, EQUIPMENT
- unitId (UUID, optional) — filter by owning unit

Response (200 OK):

```
{ "content": [...], "totalElements": 142, "totalPages": 8, "page": 0 }
```

4. Mission Endpoints

Method	Path	Role Required	Description
GET	/v2/missions	VIEWER+	List missions
GET	/v2/missions/{id}	VIEWER+	Get mission details
POST	/v2/missions	OPERATOR+	Create mission (status: DRAFT)
PUT	/v2/missions/{id}	OPERATOR+	Update DRAFT mission
POST	/v2/missions/{id}/approve	ADMIN	Transition DRAFT -> APPROVED

POST	/v2/missions/{id}/activate	OPERATOR+	Transition APPROVED -> ACTIVE
POST	/v2/missions/{id}/complete	OPERATOR+	Transition ACTIVE -> COMPLETED
POST	/v2/missions/{id}/cancel	ADMIN	Cancel mission (any state)

4.1 Mission Status Rules

Missions follow a strict state machine. Attempting an invalid transition returns 409 Conflict with body:

```
{ "error": "INVALID_STATE_TRANSITION", "from": "DRAFT", "attempted": "COMPLETED" }
```

Valid transitions:

- DRAFT -> APPROVED (requires ADMIN role, via POST /approve)
- APPROVED -> ACTIVE (requires OPERATOR+ role, via POST /activate)
- ACTIVE -> COMPLETED (requires OPERATOR+ role, via POST /complete)
- Any state -> CANCELLED (requires ADMIN role, via POST /cancel)

5. Common HTTP Error Codes

Code	Error Key	Meaning
400	VALIDATION_ERROR	Request body failed validation — check errors[] array in response
401	UNAUTHORIZED	Missing or expired token — re-authenticate
403	FORBIDDEN	Token valid but insufficient role for this action
404	RESOURCE_NOT_FOUND	Entity does not exist or caller lacks visibility
409	INVALID_STATE_TRANSITION	Mission state machine violation
429	RATE_LIMIT_EXCEEDED	100 req/min per token exceeded — back off and retry
500	INTERNAL_ERROR	Unexpected server error — include X-Request-Id from response header when reporting
503	SERVICE_UNAVAILABLE	Downstream service is unhealthy — check /actuator/health

6. Pagination

All list endpoints return a standard paginated envelope:

```
{ "content": [], "page": 0, "size": 20, "totalElements": 0, "totalPages": 0 }
```

The maximum page size is 100. Requesting size > 100 returns 400 VALIDATION_ERROR.

7. Report Endpoints

7.1 Request a Report

POST /v2/reports

Request body:

```
{ "type": "MISSION_SUMMARY", "missionId": "uuid", "format": "PDF" }
```

Supported types: MISSION_SUMMARY, ASSET_INVENTORY, ACTIVITY_LOG

Supported formats: PDF, EXCEL

Response (202 Accepted):

```
{ "reportId": "uuid", "status": "PENDING", "estimatedSeconds": 15 }
```

7.2 Poll Report Status

GET /v2/reports/{reportId}/status

Response when complete:

```
{ "reportId": "uuid", "status": "COMPLETED", "downloadUrl":  
  "https://s3.aws.../...", "expiresAt": "2026-06-08T15:00:00Z" }
```