

GeoViewer

Interactive GeoJSON Map Viewer for WordPress

Plugin Documentation

Version 1.0.0

BhoomiTech Heritage and Development Foundation

<https://bhoomitech.org>

1. Overview

© BhoomiTech Heritage and Development Foundation

GeoViewer is an open-source WordPress plugin that embeds a fully interactive GeoJSON map viewer anywhere on a WordPress site — in any post, page, or widget area — via a shortcode or a Gutenberg block. Built on the Leaflet.js mapping library, it provides everything needed to display, explore, and annotate geographic data without requiring any external GIS platform or paid tile service.

The plugin is designed for a wide range of users: a community organisation mapping local heritage sites, a researcher displaying field-survey data, a classroom exploring world geography, or a museum embedding a collection of historic land-use layers. Any WordPress site can become a capable, self-hosted map viewer in minutes.

1.1 What GeoViewer Does

Visitors to a page with an embedded GeoViewer map can:

- Load their own GeoJSON files directly in the browser by dragging and dropping them onto the map.
- Switch between a wide range of basemaps — from familiar street maps to satellite imagery and a blank canvas — without leaving the page.
- Manage layers in a side panel: toggle visibility, rename layers, reorder them, and delete unwanted ones.
- Inspect feature properties in an interactive attribute table, edit values, add custom columns, and save the modified data back to a file using the browser's File System Access API.
- Measure straight-line haversine distances or calculate a road route between two or more points on the map using the built-in Routing and Distance tab.
- Save their current workspace (all loaded layers, styles, and settings) as a named project linked to their WordPress account, then reload it later.

Site administrators can:

- Upload and manage a library of server-side GeoJSON layers from the WordPress dashboard.
- Pre-load one or more library layers into any map instance using the `layer_id` shortcode attribute.
- Preview the live map directly in the wp-admin area before deploying it to a public page.
- Configure site-wide map defaults — basemap, initial coordinates, zoom level, height, and feature toggles — from a settings page.

1.2 Key Features at a Glance

Feature	Details
Basemaps	OpenStreetMap, Carto Dark, Carto Light, ESRI Topo, ESRI Imagery, Google Street, Google Hybrid, Google Terrain, OpenCycleMap, Blank
GeoJSON loading	Drag-and-drop onto the map; or pre-load admin layers via shortcode attribute
Layer panel	Toggle visibility, rename, reorder, delete
Attribute table	View and edit feature properties; add columns; export via File System Access API
Routing	Click-to-measure haversine distance or road route between points (Leaflet Routing Machine)
Project storage	Logged-in users save and reload workspaces server-side; guests export a .geoviewer file
Embedding	[geoviewer] shortcode and GeoViewer Map Gutenberg block
Admin layer library	Upload GeoJSON layers from wp-admin; reference by ID in shortcodes
Theme isolation	All styles scoped to .geoviewer-embed; CSS resets prevent theme interference
Multi-instance	Multiple map instances per page, each with independent state
Licence	GPLv2 or later

2. Installation

© BhoomiTech Heritage and Development Foundation

Plugin slug: `geoviewer` **Version:** `1.0.0` **Requires:** `WordPress 6.0+, PHP 8.0+`

1. Upload the
2. Upload the `geoviewer` folder to `/wp-content/plugins/`, or install the .zip via **Plugins** → **Add New** → **Upload Plugin**.
3. Activate the plugin from the WordPress **Plugins** menu.
4. Navigate to **GeoViewer** → **Settings** to configure the default basemap, map height, initial coordinates, and feature toggles.
5. (Optional) Go to **GeoViewer** → **Layers** to upload server-side GeoJSON layers that can be pre-loaded into any map instance.
6. Add `[geoviewer]` to any post or page, or insert the **GeoViewer Map** block in the Gutenberg editor.

2.1 Requirements

Requirement	Value
WordPress	6.0 or later
PHP	8.0 or later
Browser (general)	Any modern browser (Chrome, Edge, Firefox, Safari)
Browser (attribute export)	Chromium-based (Chrome or Edge) — requires File System Access API
Browser (routing)	Any modern browser with internet access for OSRM tile routing
Server requirement	None beyond standard WordPress hosting

3. The Embedded Map

© BhoomiTech Heritage and Development Foundation

Every embedded GeoViewer map — whether placed via the shortcode or the Gutenberg block — renders a self-contained interactive application inside a scoped wrapper element (

Every embedded GeoViewer map — whether placed via the `[geoviewer]` shortcode or the **GeoViewer Map** Gutenberg block — renders a self-contained interactive application inside a scoped wrapper element (`.geoviewer-embed`). All CSS is scoped to this wrapper to prevent conflicts with the active WordPress theme.

3.1 Map Canvas and Basemaps

The central pane of every map instance is a Leaflet.js map canvas. The basemap switcher (accessible via the layers control in the top-right corner) allows the visitor to change the tile background without affecting loaded data layers. The following basemaps are available:

Key	Basemap Name
osm	OpenStreetMap (default)
carto-dark	Carto Dark
carto-light	Carto Light
esri-topo	ESRI Topo
esri-imagery	ESRI Imagery
google-street	Google Street
google-hybrid	Google Hybrid
google-terrain	Google Terrain
cycle	OpenCycleMap

Key	Basemap Name
blank	Blank canvas (no tiles)

3.2 Loading GeoJSON

If the Load GeoJSON button is enabled (it is by default, controlled by the `show_upload` shortcode attribute), visitors can load their own GeoJSON files in two ways:

- **Drag and drop** — drag a `.geojson` or `.json` file from the desktop directly onto the map canvas.
- **File picker** — click the **+ Load GeoJSON** button to open a file chooser dialog.

Loaded files are parsed and validated as GeoJSON. If the file cannot be parsed, an error message is shown and no layer is added. Successfully loaded layers appear immediately on the map and in the Layer Panel.

3.3 Layer Panel

The Layer Panel lists every loaded layer with its name, a colour swatch showing its current style, and a set of controls:

- Visibility toggle — show or hide the layer on the map without removing it.
- Rename — click the layer name to rename it inline.
- Reorder — drag layers in the panel to change their stacking order on the map.
- Delete — remove the layer from the map and from the panel.
- Colour swatch — click to open a style editor where fill colour, stroke colour, and opacity can be adjusted.

3.4 Attribute Table

Clicking a feature on the map opens an information popup. The Attribute Table tab (accessible from the side panel) shows all properties of a selected feature in an editable grid:

- Property values can be edited directly in the table cells.
- New columns (custom properties) can be added to all features in a layer.
- Modified data can be saved back to a file via the browser's File System Access API (Chrome and Edge only). The saved file is a valid GeoJSON FeatureCollection reflecting all edits. On browsers that do not support the File System Access API, a standard download is offered instead.

3.5 Routing and Distance

The Routing tab is shown by default (controlled by the `show_routing` shortcode attribute). It provides two measurement modes:

- **Distance measurement** — click two or more points on the map to see the straight-line haversine distance between consecutive points and the total distance of the path.

- **Road routing** — uses Leaflet Routing Machine (powered by OSRM) to calculate a turn-by-turn road route between two points. Requires an internet connection. The route is drawn on the map and a step-by-step instruction list is displayed in the panel.

3.6 Project Save and Load

Logged-in WordPress users see Save Project and Load Project buttons in the map toolbar. Projects store the complete workspace state: all loaded layers (as GeoJSON), their styles, visibility settings, and the current basemap and map position.

- **Save Project** — prompts for a project name. If a project with that name already exists for the current user, it is overwritten. Projects are stored server-side in the WordPress database.
- **Load Project** — opens a list of the user's saved projects. Selecting one replaces the current map state with the saved state.
- Guest users (not logged in) can export the current workspace as a .geoviewer file (a JSON document) and re-import it later using the file picker or drag-and-drop.

4. Shortcode Reference

© BhoomiTech Heritage and Development Foundation

Place `[geoviewer]` in any post, page, or widget area to embed a map. Every attribute is optional; omitted attributes use the site-wide defaults configured on the Settings page.

4.1 Shortcode Attributes

Attribute	Default	Type	Description
height	600	integer	Map height in pixels. Minimum 200.
basemap	osm	string	Starting basemap key (see Section 3.1 for valid keys).
lat	20	float	Initial map centre latitude (−90 to 90).
lng	0	float	Initial map centre longitude (−180 to 180).
zoom	2	integer	Initial zoom level (1 = world, 18 = street level).
layer_id	(empty)	string	Comma-separated post IDs of admin layers to pre-load on the map.
show_upload	true	boolean	Show the Load GeoJSON button. Set to false to hide it.
show_routing	true	boolean	Show the Routing & Distance tab. Set to false to hide it.
class	(empty)	string	Extra CSS class added to the wrapper element for custom styling.

4.2 Examples

Basic embed with all defaults:

```
[[geoviewer]]
```

Map centred on London at zoom 12, using the Carto Dark basemap, 500 px tall:

```
[[geoviewer height="500" basemap="carto-dark" lat="51.5" lng="-0.12" zoom="12"]]
```

Map with two pre-loaded admin layers and routing hidden:

```
[[geoviewer layer_id="42,57" show_routing="false"]]
```

Map with file upload disabled and an extra CSS class:

```
[[geoviewer show_upload="false" class="my-fullwidth-map"]]
```

4.3 Multiple Maps on One Page

Each `[[geoviewer]]` shortcode (or block) creates an independent map instance with its own Leaflet map object, layer state, and project context. There is no limit to the number of instances on a single page. The shared Leaflet.js and application scripts are enqueued only once regardless of the number of instances.

5. Gutenberg Block

© BhoomiTech Heritage and Development Foundation

In the WordPress block editor (Gutenberg), search for **GeoViewer Map** to insert a map block. The block provides the same functionality as the `[[geoviewer]]` shortcode, with all attributes exposed as visual controls in the block sidebar:

- Height — a numeric input for map height in pixels.
- Basemap — a dropdown of all available basemap keys.
- Default latitude and longitude — numeric inputs for the initial map centre.
- Zoom — a numeric input for the initial zoom level.
- Preloaded layers — a text field for comma-separated layer IDs from the admin layer library.
- Show upload button — a toggle.
- Show routing tab — a toggle.

The block renders server-side (via the same PHP render callback as the shortcode) so the block editor shows a live server-side preview of the map. Changes to block controls update the preview in real time.

6. Admin Area (wp-admin)

© BhoomiTech Heritage and Development Foundation

The plugin adds a **GeoViewer** top-level menu to wp-admin with four sections:

6.1 Dashboard

The Dashboard is the first page shown when the GeoViewer menu is opened. It provides:

- A summary of the current site-wide defaults: number of saved layers, the active default basemap, and the default map height.
- A quick-start shortcode helper with copy buttons for the most common shortcode patterns.
- A note about the Gutenberg block and its available controls.
- A Recent Layers table listing the five most recently modified layers with their IDs and ready-to-use shortcodes.

6.2 Layers

The Layers page is the admin layer library. It allows editors and administrators to upload and manage server-side GeoJSON layers that can be pre-loaded into any map instance.

Uploading layers:

- Drag one or more .geojson or .json files onto the upload zone, or click Choose Files to open a file picker.
- Multiple files can be uploaded in a single operation; a progress bar and status message are shown during upload.
- Each file is validated as GeoJSON on upload. Invalid files are rejected with an error message.

Managing layers:

- The layer list shows every saved layer with its name, post ID, feature count, a ready-to-use shortcode, a visibility toggle, and Rename / Delete action buttons.
- Renaming — click Rename next to a layer to edit its name inline and save.
- Deleting — click Delete to permanently remove a layer. Bulk deletion is available via the checkboxes and the Delete Selected button.
- Visibility toggle — marking a layer inactive in the admin list does not prevent it from being pre-loaded via layer_id; it only affects the admin preview.

Note the post ID of each layer (shown in the ID column) to use in the `layer_id` shortcode attribute. For example, a layer with ID 42 is pre-loaded with `[geoviewer layer_id="42"]`.

6.3 Map Preview

The Map Preview page renders a live, fully functional embedded map directly inside wp-admin. It is intended for testing layer combinations and shortcode attributes before deploying them to a public page. The preview uses the current site-wide settings as defaults. Layers can be loaded from the admin library or by dragging GeoJSON files onto the preview map.

6.4 Settings

The Settings page configures site-wide defaults that apply to every map instance where the corresponding shortcode attribute is omitted. All settings can be overridden per-instance using shortcode attributes.

Map Defaults

Setting	Description
Default Basemap	The basemap selected when the map first loads. Defaults to OpenStreetMap (osm).
Map Height (px)	Default map height in pixels. Minimum 200 px. Override with height="" per instance.
Default Centre	Latitude and longitude of the initial map view. Defaults to 20°N, 0°E (approximate world centre).
Default Zoom	Initial zoom level (1 = world view, 18 = street level). Defaults to 2.

Feature Toggles

Setting	Description
Allow File Upload	Show the Load GeoJSON button on embedded maps. Disable to prevent visitors from loading their own files. Override with show_upload="false" per instance.
Show Routing Tab	Display the Routing & Distance tab on embedded maps. Override with show_routing="false" per instance.

Data and Uninstall

The **Delete All Data on Uninstall** checkbox controls what happens when the plugin is deleted from the Plugins screen (not merely deactivated). When unchecked (the default), all data is preserved across deactivations. When checked, deleting the plugin permanently removes all layers, saved projects, and plugin options. A warning message is shown when this option is enabled. See Section 9 (Uninstallation) for full details.

7. Access Control and Capabilities

© BhoomiTech Heritage and Development Foundation

GeoViewer uses WordPress roles and capabilities to control access to different parts of the plugin.

7.1 Capabilities

Capability	Description
manage_geoviewer	Access to the Settings page and to the /settings REST endpoint. Assigned to Administrators on activation.
edit_geoviewer_layers	Upload, edit, and delete layers in the admin library. Assigned to Administrators and Editors on activation.

These capabilities are added to the Administrator and Editor roles when the plugin is activated, and removed from those roles when the plugin is deleted with the "Delete all data on uninstall" option enabled.

7.2 Front-End Access

The embedded map is accessible to all visitors (logged-in or not). The following features require a logged-in WordPress account:

- Save Project — store a named workspace server-side.
- Load Project — retrieve a previously saved workspace.

Guests can still load GeoJSON files locally, interact with layers, use the attribute table, measure distances, and calculate routes. They can export their workspace as a .geoviewer file for later re-import.

7.3 Admin Area Access

Access to the GeoViewer wp-admin menu requires the edit_posts capability at minimum (Dashboard, Layers, and Map Preview pages) or manage_options for the Settings page. This aligns with the standard WordPress editor/administrator distinction.

8. REST API

© BhoomiTech Heritage and Development Foundation

The plugin exposes a REST API under the namespace `geoviewer/v1`. The full base URL is <https://yoursite.com/wp-json/geoviewer/v1>. All front-end interactions — map embeds, project save/load, and layer fetching — go through this API.

8.1 Projects Endpoints

Projects are scoped to the currently authenticated WordPress user. All project endpoints require an active login session.

Method + Endpoint	Auth Required	Description
GET /projects	Logged-in user	List all saved projects for the current user (id, name, updated_at).

Method + Endpoint	Auth Required	Description
POST /projects	Logged-in user	Create or update a named project. Body: name (string), project (JSON string). If a project with the same name exists for this user, it is overwritten.
GET /projects/{id}	Logged-in user	Retrieve a single project including the full project JSON payload.
DELETE /projects/{id}	Logged-in user	Delete a project. Users can only delete their own projects.

8.2 Layers Endpoints

Layer read endpoints are publicly accessible. Write endpoints require the `edit_geoviewer_layers` capability (Editors and Administrators).

Method + Endpoint	Auth Required	Description
GET /layers	Public	List all published layers (id, title, geojson, style, visible). Returns up to 200 layers.
POST /layers	<code>edit_geoviewer_layers</code>	Create a new layer. Body: title (required), geojson (required, must be valid JSON), style (optional), visible (optional boolean, default true).
GET /layers/{id}	Public	Retrieve a single layer with full GeoJSON payload.
PUT /layers/{id}	<code>edit_geoviewer_layers</code>	Update an existing layer. Any combination of title, geojson, style, or visible may be sent; only provided fields are updated.
DELETE /layers/{id}	<code>edit_geoviewer_layers</code>	Permanently delete a layer. Cannot be undone.

8.3 Settings Endpoints

Method + Endpoint	Auth Required	Description
GET /settings	<code>manage_options</code> (Admin)	Read current site-wide settings merged with defaults.
POST /settings	<code>manage_options</code> (Admin)	Save site-wide settings. Unknown keys are ignored; only keys present in the default settings schema are accepted.

9. Data Storage

Data Type	Storage Location
Admin GeoJSON layers (GeoJSON content)	WordPress custom post type post_content (post_type: geoviewer_layer)
Admin layer style	WordPress post meta: _geoviewer_style
Admin layer visibility	WordPress post meta: _geoviewer_visible
User project workspaces	Custom database table: {prefix}geoviewer_projects (columns: id, user_id, name, project, created_at, updated_at)
Plugin settings	WordPress options table: geoviewer_settings
Database schema version	WordPress options table: geoviewer_db_ver

10. Uninstallation

© BhoomiTech Heritage and Development Foundation

Deactivating the plugin (Plugins → Deactivate) does not remove any data. The plugin can be re-activated at any time and all layers, projects, and settings will be intact.

Deleting the plugin (Plugins → Delete) triggers the uninstall routine. By default, all data is **preserved** on deletion — GeoViewer's guiding principle is to never destroy data without explicit consent.

To remove all data permanently, go to **GeoViewer** → **Settings** and check **Delete All Data on Uninstall** before deleting the plugin. Once this option is enabled and the plugin is deleted from the Plugins screen, the following is removed irreversibly:

- The wp_{prefix}geoviewer_projects database table is dropped.
- All GeoViewer Layer custom post type posts and their associated post meta are permanently deleted.
- Plugin options (geoviewer_settings and geoviewer_db_ver) are deleted.
-
- The `manage_geoviewer` and `edit_geoviewer_layers` capabilities are removed from the Administrator and Editor roles.
- On WordPress Multisite installations, the cleanup above is repeated for every sub-site.

Export any layers you want to keep as GeoJSON files before deleting the plugin. Use **GeoViewer** → **Layers** to download individual layer files, or use the REST API (`GET /wp-json/geoviewer/v1/layers/{id}`) to retrieve the GeoJSON content programmatically.

11. Troubleshooting

© BhoomiTech Heritage and Development Foundation

Map does not appear — only a grey box is shown

This is almost always caused by a JavaScript conflict or a missing Leaflet initialisation. Check the browser developer console for errors. Common causes:

- Another plugin or theme is loading a different version of Leaflet.js. GeoViewer vendors its own copy of Leaflet 1.9.4 and enqueues it in the <head> to ensure window.L is defined before footer scripts run. If another plugin replaces window.L after page load, the map will fail to initialise.
- The page uses a page builder or caching plugin that strips or defers scripts. Ensure GeoViewer's scripts (geoviewer-leaflet, geoviewer-lrm, geoviewer-app) are not excluded from loading or deferred.
- The map container height is zero. Check that the height attribute is set to at least 200, and that no theme CSS is overriding the height.

Drag-and-drop does not work

Drag-and-drop GeoJSON loading is handled by the browser's standard drag event API. If it is not working, check that:

- The browser is not in a restricted mode that blocks the clipboard or file APIs.
- The show_upload attribute is not set to false.
- The file is a valid .geojson or .json file. Files with other extensions are not accepted.

"Could not parse file as GeoJSON" error on upload

The file content is not valid GeoJSON. Ensure the file is a valid `FeatureCollection` or `Feature` object. Validate the file using an online GeoJSON validator (such as geojsonlint.com) before uploading. Common issues include trailing commas, unquoted property names, or coordinate arrays with incorrect precision.

Attribute table Save button does nothing or is greyed out

The attribute table's save-to-file feature requires the browser's File System Access API, which is only available in Chromium-based browsers (Chrome and Edge). In Firefox and Safari, the button is replaced by a standard download prompt. If neither is working, check the browser console for permission errors — the user may have denied the file system access permission.

Routing does not draw a route

Road routing is powered by Leaflet Routing Machine using the public OSRM demo server. This requires an active internet connection from the user's browser. If routing fails:

- Check that the browser has internet access.
- Confirm that the two points clicked are in a region supported by OSRM (most of the world is covered, but some remote areas are not).

- Check the browser console — OSRM may return a "No route found" response if the two points are on different road networks (e.g. different islands with no road connection).
- For production deployments with heavy routing usage, consider configuring Leaflet Routing Machine to use a self-hosted OSRM instance rather than the public demo server.

Projects do not save — "Save Project" button is not visible

Project save and load requires an active WordPress login. If the user is not logged in, the Save Project and Load Project buttons are not shown. Ensure the user has a WordPress account and is logged in before attempting to save a project.

Layer uploaded in admin does not appear in the shortcode

The `layer_id` attribute must match the WordPress post ID of the layer — not its title or slug. The post ID is shown in the ID column on the **GeoViewer** → **Layers** page and in the ready-to-use shortcode snippet on the Dashboard. Verify the correct ID is used and that the layer's post status is Published.

Map is styled incorrectly — layout broken by theme CSS

GeoViewer scopes all of its CSS to the `.geoviewer-embed` wrapper and applies internal resets for common theme overrides (`max-width` on images, `list-style` on lists, `box-sizing`). If a theme is still interfering, add a more specific CSS rule targeting `.geoviewer-embed` in the theme's custom CSS section to override the conflicting declaration.

12. Quick Reference

© BhoomiTech Heritage and Development Foundation

12.1 Shortcodes

Shortcode	Effect
<code>[geoviewer]</code>	Embeds a map with all site-wide defaults.
<code>[geoviewer height="500" basemap="carto-dark"]</code>	Embeds a 500 px tall map with Carto Dark basemap.
<code>[geoviewer layer_id="42,57"]</code>	Embeds a map with layers 42 and 57 pre-loaded.
<code>[geoviewer show_routing="false"]</code>	Embeds a map with the Routing tab hidden.
<code>[geoviewer show_upload="false"]</code>	Embeds a map with the Load GeoJSON button hidden.
<code>[geoviewer lat="51.5" lng="-0.12" zoom="12"]</code>	Embeds a map centred on London at street level.

12.2 Key REST Endpoints

URL Pattern	Description
<code>https://yoursite.com/wp-json/geoviewer/v1/layers</code>	List all admin layers (public).
<code>https://yoursite.com/wp-json/geoviewer/v1/layers/{id}</code>	Get a single layer with full GeoJSON (public).
<code>https://yoursite.com/wp-json/geoviewer/v1/projects</code>	List current user's saved projects (login required).
<code>https://yoursite.com/wp-json/geoviewer/v1/settings</code>	Read or update site-wide settings (admin only).

12.3 File and Directory Reference

Path	Contents
<code>wp-content/plugins/geoviewer/geoviewer.php</code>	Plugin entry point: constants, includes, hook registrations.
<code>wp-content/plugins/geoviewer/includes/</code>	Core PHP classes: activator, custom post type, REST API, shortcode, block.
<code>wp-content/plugins/geoviewer/admin/</code>	Admin PHP class and wp-admin views (dashboard, layers, preview, settings).
<code>wp-content/plugins/geoviewer/public/js/leaflet.js</code>	Vendored Leaflet.js 1.9.4.
<code>wp-content/plugins/geoviewer/public/js/geoviewer.js</code>	GeoViewer application script (IIFE, all map logic).
<code>wp-content/plugins/geoviewer/public/css/geoviewer.css</code>	Public map styles (scoped to <code>.geoviewer-embed</code>).
<code>wp-content/plugins/geoviewer/admin/js/admin.js</code>	Admin JavaScript (layer upload, settings form).
<code>wp-content/plugins/geoviewer/admin/js/block-editor.js</code>	Gutenberg block registration and editor controls.
<code>wp-content/plugins/geoviewer/uninstall.php</code>	Uninstall routine (drops tables, removes CPT posts and options).

12.4 Browser Support

Feature	Chrome	Edge	Firefox / Safari
Map display and layer loading	✓	✓	✓
Drag-and-drop GeoJSON	✓	✓	✓
Routing & Distance	✓	✓	✓ (internet required)
Attribute table editing	✓	✓	✓
Attribute table File Save (File System Access API)	✓	✓	✗ (download fallback)
PWA Install	✓	✓	✓ (Safari 16.4+)

13. Changelog

© BhoomiTech Heritage and Development Foundation

Version 1.0.0 (Current)

- Initial public release.
- Leaflet.js 1.9.4 map canvas with basemap switcher (10 basemaps).
- Drag-and-drop and file-picker GeoJSON loading.
- Layer panel with visibility toggle, rename, reorder, and delete.
- Attribute table with property editing, custom columns, and File System Access API save.
- Routing and Distance tab (haversine distance measurement and Leaflet Routing Machine road routing).
- Server-side project storage for logged-in users; .geoviewer file export for guests.
- Admin layer library with drag-and-drop upload, layer management, and Map Preview page.
- [geoviewer] shortcode with full attribute set.
- GeoViewer Map Gutenberg block with server-side render and visual sidebar controls.
- Settings page with site-wide defaults and optional data-on-uninstall deletion.
- REST API (geoviewer/v1) for projects, layers, and settings.
- Full multisite support for uninstall cleanup.
- Theme-safe CSS scoped entirely to .geoviewer-embed.

14. Appendix

© BhoomiTech Heritage and Development Foundation

A. Minimum Requirements

Component	Requirement
WordPress	6.0 or later
PHP	8.0 or later
Browser (all features)	Chrome or Edge (Chromium)
Browser (all features except file save)	Firefox or Safari
Internet connection	Required for map tiles and road routing; not required for USB-mode offline data
Server	Standard WordPress hosting; no additional dependencies

B. Licencing

Component	Licence
GeoViewer Plugin v1.0.0	GPLv2 or later
Leaflet.js 1.9.4 (vendored)	BSD 2-Clause
Leaflet Routing Machine 3.2.12 (CDN)	MIT

Full GPL licence text: <https://www.gnu.org/licenses/gpl-2.0.html>

C. Links

Resource	URL
Developer / Author	https://bhoomitech.org
GeoViewer Plugin documentation	https://bhoomitechapps.github.io/documentation/geoviewer
GNU GPLv2 Licence	https://www.gnu.org/licenses/gpl-2.0.html
Leaflet.js	https://leafletjs.com
Leaflet Routing Machine	https://www.liedman.net/leaflet-routing-machine/