



IAngleMateFeatureData Interface

Allows access to an angle mate or a limit angle mate feature.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IAngleMateFeatureData
```

Visual Basic (Usage)

```
Dim instance As IAngleMateFeatureData
```

C#

```
public interface IAngleMateFeatureData
```

C++/CLI

```
public interface class IAngleMateFeatureData
```

Example

[Create and Edit Limit Angle Mate \(VBA\)](#)

[Create and Edit Limit Angle Mate \(C#\)](#)

Remarks

An angle mate places selected items at a specified angle. A limit angle mate is an advanced mate that allows items to move within a range of angles. Use [IAngleMateFeatureData::IsAdvancedMate](#) to determine whether this is a limit angle mate.

[IMateFeatureData](#) is the parent of this mate interface.

To create either an angle mate or a limit angle mate:

Follow general instructions in the [IAssemblyDoc::CreateMate](#) Remarks.

Specify [IAngleMateFeatureData::EntitiesToMate](#) or use [IModelDocExtension::SelectByID2](#) to pre-select the entities using Mark = 1.

Specify [IAngleMateFeatureData::ReferenceEntity](#) or use [IModelDocExtension::SelectByID2](#) to pre-select the reference entity using Mark = 67108864.

Specify other properties of the AngleMateFeatureData object.

To edit an angle mate:

Access its feature and call [IFeature::GetDefinition](#) to get the MateFeatureData object.

Cast the MateFeatureData object to an AngleMateFeatureData object.

Modify the AngleMateFeatureData object.

Call [IFeature::ModifyDefinition](#).

To delete this angle mate, use [IModelDocExtension::DeleteSelection2](#).

Access Diagram

See Also

[IAngleMateFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)



IAngleMateFeatureData Interface Members

The following tables list the members exposed by [IAngleMateFeatureData](#).

Public Properties

Name	Description
 Angle	Gets or sets the angle of this angle mate.
 EntitiesToMate	Gets or sets the entities to mate in this angle mate.
 FlipDimension	Gets or sets whether to move entities to opposite sides of the dimension in this angle mate.
 IsAdvancedMate	Gets or sets whether this angle mate is a limit angle mate.
 MateAlignment	Gets or sets the alignment of this angle mate.
 MaximumAngle	Gets or sets the maximum angle of this limit angle mate.
 MinimumAngle	Gets or sets the minimum angle of this limit angle mate.
 ReferenceEntity	Gets or sets the direction reference entity for this angle mate.

[Top](#)

See Also

[IAngleMateFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)