

SOLIDWORKS API (.NET VBA C#) — Reference (83/337): IDrawingComponent

SOLIDWORKS API Documentation (converted from CHM)

IDrawingComponent (Type)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IDrawingComponent Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IDrawingComponent Interface

Represents the referenced component in a drawing view.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IDrawingComponent
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent
```

C#

```
public interface IDrawingComponent
```

C++/CLI

```
public interface class IDrawingComponent
```

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent](#).

Example

[Get Components in Drawing View \(VBA\)](#)
[Get Components in Drawing View \(VB.NET\)](#)
[Get Components in Drawing View \(C#\)](#)
[Select Drawing Component \(C#\)](#)
[Select Drawing Component \(VB.NET\)](#)
[Select Drawing Component \(VBA\)](#)

Remarks

This object ties the [IComponent2](#) object of the [IAssemblyDoc](#) object with the [IView](#) object of the [IDrawingDoc](#) object. This functionality allows an application to manipulate the drawing-related settings of a referenced component without having to preselect that component.

Accessors

[IComponent2::GetDrawingComponent](#)
[IDrawingComponent::GetChildren](#) and [IDrawingComponent::IGetChildren](#)
[IEntity::GetDrawingComponent](#)
[ISelectionMgr::GetSelectedObjectsComponent4](#)
[IView::GetVisibleDrawingComponents](#)
[IView::RootDrawingComponent](#)

Access Diagram

[DrawingComponent](#)

See Also

[IDrawingComponent Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

IDrawingComponent Interface Methods

[See Also](#)

[SolidWorks.Interop.sldworks Namespace](#) : IDrawingComponent Interface

For a list of all members of this type, see [IDrawingComponent members](#).

Public Methods

Name	Description
 DeSelect	Deselects this drawing component.
 GetChildren	Gets the child components for this drawing component.
 GetChildrenCount	Gets the number of child components for this drawing component.
 GetLineStyle	Gets the line style for the drawing component.
 GetLineThickness	Gets the line thickness for the drawing component.
 IGetChildren	Gets the child components for this drawing component.
 IsRoot	Gets whether this is the root drawing component.
 Select	Selects the specified drawing component.
 SetLineStyle	Sets the line style for the drawing component.
 SetLineThickness	Sets the line thickness for the drawing component.

[Top](#)

See Also

[IDrawingComponent Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

IDrawingComponent Interface Members

[See Also](#) [Properties](#) [Methods](#)

[SolidWorks.Interop.sldworks Namespace](#) : IDrawingComponent Interface

The following tables list the members exposed by [IDrawingComponent](#).

Public Properties

Name	Description
 Component	Gets the assembly component referenced in this drawing component.
 Layer	Gets or sets the name of the layer on which the component resides in the view.
 LayerOverride	Gets or sets whether the drawing component has properties that override the default properties of the layer.
 Name	Gets the name of the drawing component.
 Style	Gets or sets the style for the line for this component in this drawing view.
 UseDocumentDefaults	Gets or sets whether to use the document default settings for the component's line fonts.
 View	Gets the drawing view on which this component resides.
 Visible	Gets or sets the visibility state for this component for this drawing view.
 Width	Gets or sets the width of the line for this component for this drawing view.

[Top](#)

Public Methods

Name	Description
 DeSelect	Deselects this drawing component.
 GetChildren	Gets the child components for this drawing component.
 GetChildrenCount	Gets the number of child components for this drawing component.

		
	GetLineStyle	Gets the line style for the drawing component.
	GetLineThickness	Gets the line thickness for the drawing component.
	IGetChildren	Gets the child components for this drawing component.
	IsRoot	Gets whether this is the root drawing component.
	Select	Selects the specified drawing component.
	SetLineStyle	Sets the line style for the drawing component.
	SetLineThickness	Sets the line thickness for the drawing component.

[Top](#)

See Also

[IDrawingComponent Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IDrawingComponent Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IDrawingComponent Interface

For a list of all members of this type, see [IDrawingComponent members](#).

Public Properties

Name	Description
 Component	Gets the assembly component referenced in this drawing component.
 Layer	Gets or sets the name of the layer on which the component resides in the view.
 LayerOverride	Gets or sets whether the drawing component has properties that override the default properties of the layer.
 Name	Gets the name of the drawing component.
 Style	Gets or sets the style for the line for this component in this drawing view.
 UseDocumentDefaults	Gets or sets whether to use the document default settings for the component's line fonts.
 View	Gets the drawing view on which this component resides.
 Visible	Gets or sets the visibility state for this component for this drawing view.
 Width	Gets or sets the width of the line for this component for this drawing view.

[Top](#)

See Also

[IDrawingComponent Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

Component Property (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : Component Property (IDrawingComponent)

Gets the assembly component referenced in this drawing component.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Component As Component2

Visual Basic (Usage)



```
Dim instance As IDrawingComponent
Dim value As Component2

value = instance.Component
```

C#

```
Component2 Component {get;}
```

C++/CLI

```
property Component2^ Component {
    Component2^ get();
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Associated [IComponent2](#) object for the referenced assembly document

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::Component](#).

Example

[Get Components in Drawing View \(VBA\)](#)
[Get Components in Drawing View \(VB.NET\)](#)
[Get Components in Drawing View \(C#\)](#)
[Select Drawing Component \(C#\)](#)
[Select Drawing Component \(VB.NET\)](#)
[Select Drawing Component \(VBA\)](#)

Remarks

The associated [IComponent2](#) object should have the same properties as the referenced configuration. For example, if the component is suppressed in the reference configuration, then the returned component should also be suppressed.

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

DeSelect Method (IDrawingComponent)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : DeSelect Method (IDrawingComponent)

Deselects this drawing component.

.NET Syntax

Visual Basic (Declaration)

```
Function DeSelect() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent
Dim value As System.Boolean

value = instance.DeSelect()
```

C#

```
System.bool DeSelect()
```

C++/CLI

```
System.bool DeSelect();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True to remove the component from the selection list if it is selected, false if not

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::DeSelect](#).

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent::Select Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetChildren Method (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : GetChildren Method (IDrawingComponent)

Gets the child components for this drawing component.

.NET Syntax

Visual Basic (Declaration)

```
Function GetChildren() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim value As System.Object
```

```
value = instance.GetChildren()
```

C#

```
System.object GetChildren()
```

C++/CLI

```
System.Object^ GetChildren();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [IDrawingComponent](#) objects that are child components of the drawing component

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::GetChildren](#).

Example

[Create Section View at Specified Location \(VBA\)](#)
[Get Components' Properties in Drawing View \(VBA\)](#)
[Hide Drawing Components \(VBA\)](#)

[Put Assembly Components in Drawing View on Different Layers \(VBA\)](#)
[Get Components in Drawing View \(C#\)](#)
[Get Components in Drawing View \(VB.NET\)](#)
[Get Components in Drawing View \(VBA\)](#)

Remarks

This method traverses the referenced component tree in a given view. Use [IDrawingComponent.Visible](#) to get or set the visibility of individual components in the given view.

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent.GetChildrenCount Method](#)
[IDrawingComponent.IGetChildren Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetChildrenCount Method (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : GetChildrenCount Method (IDrawingComponent)

Gets the number of child components for this drawing component.

.NET Syntax

Visual Basic (Declaration)

```
Function GetChildrenCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim value As System.Integer  
  
value = instance.GetChildrenCount()
```

C#

```
System.int GetChildrenCount()
```

C++/CLI

```
System.int GetChildrenCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of child components for this drawing component

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent.GetChildrenCount](#).

Example

[Create Section View at Specified Location \(VBA\)](#)

Remarks

Call this method before calling [IDrawingComponent.IGetChildren](#).

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent::GetChildren Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetLineStyle Method (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : GetLineStyle Method (IDrawingComponent)

Gets the line style for the drawing component.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLineStyle( _  
    ByVal LineFontOption As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim LineFontOption As System.Integer  
Dim value As System.Integer  
  
value = instance.GetLineStyle(LineFontOption)
```

C#

```
System.int GetLineStyle(  
    System.int LineFontOption  
)
```

C++/CLI

```
System.int GetLineStyle(  
& System.int LineFontOption  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

LineFontOption

Line font style of the component as defined in [swDrawingComponentLineFontOption_e](#)

Return Value

Line style as defined in [swLineStyles_e](#)

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::GetLineStyle](#).

Example

[Get Components in Drawing View \(C#\)](#)
[Get Components in Drawing View \(VB.NET\)](#)
[Get Components in Drawing View \(VBA\)](#)

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)

[IDrawingComponent::SetLineStyle Method](#)
[IDrawingComponent::GetLineThickness Method](#)
[IDrawingComponent::SetLineThickness Method](#)
[IDrawingComponent::UseDocumentDefaults Property](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

[SOLIDWORKS API Help](#)

[Send comments on this topic.](#)

GetLineThickness Method (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : GetLineThickness Method (IDrawingComponent)

Gets the line thickness for the drawing component.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLineThickness( _  
    ByVal LineFontOption As System.Integer, _  
    ByRef Thickness As System.Double _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim LineFontOption As System.Integer  
Dim Thickness As System.Double  
Dim value As System.Integer  
  
value = instance.GetLineThickness(LineFontOption, Thickness)
```

C#

```
System.int GetLineThickness(  
    System.int LineFontOption,  
    out System.double Thickness  
)
```

C++/CLI

```
System.int GetLineThickness(  
& System.int LineFontOption,  
& [Out] System.double Thickness  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

LineFontOption

Line font style of the component as defined in [swDrawingComponentLineFontOption e](#)

Thickness

Thickness of line

Return Value

Line weight style as defined in [swLineWeights e](#)

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::GetLineThickness](#).

Example

[Get Components in Drawing View \(C#\)](#)
[Get Components in Drawing View \(VB.NET\)](#)
[Get Components in Drawing View \(VBA\)](#)

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent::SetLineThickness Method](#)
[IDrawingComponent::GetLineStyle Method](#)
[IDrawingComponent::SetLineStyle Method](#)
[IDrawingComponent::UseDocumentDefaults Property](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetChildren Method (IDrawingComponent)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : IGetChildren Method (IDrawingComponent)

Gets the child components for this drawing component.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetChildren( _  
    ByVal Count As System.Integer _  
) As DrawingComponent
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim Count As System.Integer  
Dim value As DrawingComponent  
  
value = instance.IGetChildren(Count)
```

C#

```
DrawingComponent IGetChildren(  
    System.int Count  
)
```

C++/CLI

```
DrawingComponent^ IGetChildren(  
& System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of drawing component objects that are child components of this drawing component

Return Value

Array of [IDrawingComponent](#) objects that are child components of the drawing component

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::IGetChildren](#).

Remarks

This method traverses the referenced component tree in a given view. Use [IDrawingComponent::Visible](#) to get or set the visibility of individual components in the given view.

Before calling this method, call [IDrawingComponent::GetChildrenCount](#) to determine the size of the array.

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent::GetChildren Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IsRoot Method (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : IsRoot Method (IDrawingComponent)

Gets whether this is the root drawing component.

.NET Syntax

Visual Basic (Declaration)

```
Function IsRoot() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim value As System.Boolean  
  
value = instance.IsRoot()
```

C#

```
System.bool IsRoot()
```

C++/CLI

```
System.bool IsRoot();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if this component is the root drawing component, false if not

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent.IsRoot](#).

Example

[Get Components' Properties in Drawing View \(VBA\)](#)

Remarks

This method assists with traversal.

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Layer Property (IDrawingComponent)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : Layer Property (IDrawingComponent)

Gets or sets the name of the layer on which the component resides in the view.

.NET Syntax

Visual Basic (Declaration)

Property Layer As System.String

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim value As System.String
```

```
instance.Layer = value
```

```
value = instance.Layer
```

C#

```
System.string Layer {get; set;}
```

C++/CLI

```
property System.String^ Layer {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Name of the layer on which this component resides

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent.Layer](#).

Remarks

If you specify...

Then...

Empty string

Name of the component's layer is set to None or to the name of the default layer.

Name of an existing layer

Component is placed on that layer.

Name of a non-existent layer

Layer does not change.

If the drawing component is an assembly:

- you can set the layer, and the layers of child drawing components will also be set.
- the query returns an empty string because the layer is uniquely defined in case child drawing components reside on different layers.

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent.Layer Property](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

LayerOverride Property (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : LayerOverride Property (IDrawingComponent)

Gets or sets whether the drawing component has properties that override the default properties of the layer.

Visual Basic Syntax

Visual Basic (Declaration)

Property LayerOverride As System.Integer

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim value As System.Integer
```

```
instance.LayerOverride = value
```

```
value = instance.LayerOverride
```

C#

```
System.int LayerOverride {get; set;}
```

C++/CLI

```
property System.int LayerOverride {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Properties that have been overridden or should be overridden as defined in [swLayerOverride_e](#) (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent.LayerOverride](#).

Example

[Get Components' Properties in Drawing View \(VBA\)](#)

Remarks

Currently, only SOLIDWORKS drawing documents support layers.

You should set this property only when you want to reset specific visual properties to the default visual properties of the owning layer. If you want to change or set specific values for the visual property of this component, use [IDrawingComponent.Style](#) or [IDrawingComponent.Width](#).

In drawing documents, components can be created on a layer that has specific visual properties. By default, the component takes on the visual properties defined by the layer. However, for a specific component, you can override these visual properties (style or width).

When the component is not on any layer, this property returns an undefined value. You can use [IDrawingComponent.Layer](#) to determine the name of the layer that this component is on. If an empty string is returned by this property, then this property is not used.

When you get this property, the returned bit value indicates which properties have been overridden. The bit indicators are:

- color = 0x1
- style = 0x2
- width = 0x4

Therefore, if the return value is returned as 2, then you know style has been specifically set for this component and might not match the default value associated with this component's layer.

When you set this property, the input bit value indicates which properties should maintain their current override values. Therefore, if the return value is passed as 0x4, you know width should keep its current override value and style should be reset to use the style settings for the component's layer. If you pass 0, all visual properties are reset to use the default settings of the component's layer.

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Name Property (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : Name Property (IDrawingComponent)

Gets the name of the drawing component.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property Name As System.String
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim value As System.String  
  
value = instance.Name
```

C#

```
System.string Name {get;}
```

C++/CLI

```
property System.String^ Name {  
    System.String^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Name of the drawing component

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::Name](#).

Example

[Hide Drawing Components \(VBA\)](#)

[Put Assembly Components in Drawing View on Different Layers \(VBA\)](#)

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Select Method (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : Select Method (IDrawingComponent)

Selects the specified drawing component.

.NET Syntax

Visual Basic (Declaration)

```
Function Select( _  
    ByVal Append As System.Boolean, _  
    ByVal Data As SelectData _  
    ) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim Append As System.Boolean  
Dim Data As SelectData  
Dim value As System.Boolean  
  
value = instance.Select(Append, Data)
```

C#

```
System.bool Select(  
    System.bool Append,  
    SelectData Data  
)
```

C++/CLI

```
System.bool Select(  
& System.bool Append,  
& SelectData^ Data  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Append

True to append this selection to the selection list, false to replace the selection list with this selection

Data

Pointer to the [ISelectData](#) object

Return Value

True if the drawing component is selected, false if not

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::Select](#).

Example

[Get Components in Drawing View \(C#\)](#)

[Get Components in Drawing View \(VB.NET\)](#)

[Get Components in Drawing View \(VBA\)](#)

See Also

[IDrawingComponent Interface](#)

[IDrawingComponent Members](#)

[IDrawingComponent::Select Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SetLineStyle Method (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : SetLineStyle Method (IDrawingComponent)

Sets the line style for the drawing component.

.NET Syntax

```
Sub SetLineStyle( _
    ByVal LineFontOption As System.Integer, _
    ByVal Style As System.Integer _
)
```

```
Dim instance As IDrawingComponent
Dim LineFontOption As System.Integer
Dim Style As System.Integer

instance.SetLineStyle(LineFontOption, Style)
```

```
void SetLineStyle(
    System.int LineFontOption,
    System.int Style
)
```

```
void SetLineStyle(
    & System.int LineFontOption,
    & System.int Style
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

LineFontOption

Line font style of the component as defined in [swDrawingComponentLineFontOption_e](#)

Style

Line style as defined in [swLineStyles_e](#)

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::SetLineStyle](#).

Example

[Get Components in Drawing View \(C#\)](#)

[Get Components in Drawing View \(VB.NET\)](#)

[Get Components in Drawing View \(VBA\)](#)

See Also

[IDrawingComponent Interface](#)

[IDrawingComponent Members](#)

[IDrawingComponent::GetLineStyle Method](#)

[IDrawingComponent::GetLineThickness Method](#)

[IDrawingComponent::SetLineThickness Method](#)

[IDrawingComponent::UseDocumentDefaults Property](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SetLineThickness Method (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : SetLineThickness Method (IDrawingComponent)

Sets the line thickness for the drawing component.

.NET Syntax


```

Sub SetLineThickness( _
    ByVal LineFontOption As System.Integer, _
    ByVal LineWeights As System.Integer, _
    ByVal Thickness As System.Double _
)

```

Visual Basic (Usage)



```

Dim instance As IDrawingComponent
Dim LineFontOption As System.Integer
Dim LineWeights As System.Integer
Dim Thickness As System.Double

instance.SetLineThickness(LineFontOption, LineWeights, Thickness)

```

C#

```

void SetLineThickness(
    System.int LineFontOption,
    System.int LineWeights,
    System.double Thickness
)

```

C++/CLI

```

void SetLineThickness(
    & System.int LineFontOption,
    & System.int LineWeights,
    & System.double Thickness
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

LineFontOption
Line font style of the component as defined in [swDrawingComponentLineFontOption_e](#)

LineWeights
Line weight style as defined in [swLineWeights_e](#)

Thickness
Thickness of line; only valid if LineWeights set to swLW_CUSTOM

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::SetLineThickness](#).

Example

[Get Components in Drawing View \(C#\)](#)
[Get Components in Drawing View \(VB.NET\)](#)
[Get Components in Drawing View \(VBA\)](#)

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent::GetLineThickness Method](#)
[IDrawingComponent::GetLineStyle Method](#)
[IDrawingComponent::SetLineStyle Method](#)
[IDrawingComponent::UseDocumentDefaults Property](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Style Property (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : Style Property (IDrawingComponent)

Gets or sets the style for the line for this component in this drawing view.

.NET Syntax

Visual Basic (Declaration)

Property Style As System.Integer

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim value As System.Integer
```

```
instance.Style = value
```

```
value = instance.Style
```

C#

```
System.int Style {get; set;}
```

C++/CLI

```
property System.int Style {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Line style as defined in [swLineStyles_e](#)

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent.Style](#).

Example

[Get Components' Properties in Drawing View \(VBA\)](#)

Remarks

Use [IDrawingComponent.LayerOverride](#) to determine whether or not this component is currently using its default layer line style.

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent.Layer Property](#)
[IDrawingComponent.Width Property](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

UseDocumentDefaults Property (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : UseDocumentDefaults Property (IDrawingComponent)

Gets or sets whether to use the document default settings for the component's line fonts.

.NET Syntax

Visual Basic (Declaration)

Property UseDocumentDefaults As System.Boolean

```
Dim instance As IDrawingComponent
Dim value As System.Boolean

instance.UseDocumentDefaults = value

value = instance.UseDocumentDefaults
```

C#

```
System.bool UseDocumentDefaults {get; set;}
```

C++/CLI

```
property System.bool UseDocumentDefaults {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to use the document default settings for the component's line fonts, false to use the selected settings

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::UseDocumentDefaults](#).

Example

[Get Components in Drawing View \(C#\)](#)
[Get Components in Drawing View \(VB.NET\)](#)
[Get Components in Drawing View \(VBA\)](#)

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent::GetLineStyle Method](#)
[IDrawingComponent::GetLineThickness Method](#)
[IDrawingComponent::SetLineStyle Method](#)
[IDrawingComponent::SetLineThickness Method](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

View Property (IDrawingComponent)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : View Property (IDrawingComponent)

Gets the drawing view on which this component resides.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property View As View
```

Visual Basic (Usage)

 Copy Code

```
Dim instance As IDrawingComponent
Dim value As View

value = instance.View
```

C#

```
View View {get;}
```

C++/CLI

```
property View^ View {  
    View^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Pointer to the [IView](#) object on which this component resides

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::View](#).

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Visible Property (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : Visible Property (IDrawingComponent)

Gets or sets the visibility state for this component for this drawing view.

.NET Syntax

Visual Basic (Declaration)

```
Property Visible As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim value As System.Boolean
```

```
instance.Visible = value
```

```
value = instance.Visible
```

C#

```
System.bool Visible {get; set;}
```

C++/CLI

```
property System.bool Visible {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True if the component is visible, false if hidden

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent::Visible](#).

Example

[Get Components' Properties in Drawing View \(VBA\)](#)
[Hide Drawing Components \(VBA\)](#)

Remarks

Call the [IModelDoc2::Rebuild](#) after setting this method.

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Width Property (IDrawingComponent)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IDrawingComponent Interface](#) : Width Property (IDrawingComponent)

Gets or sets the width of the line for this component for this drawing view.

.NET Syntax

Visual Basic (Declaration)

Property Width As System.Integer

Visual Basic (Usage)



```
Dim instance As IDrawingComponent  
Dim value As System.Integer
```

```
instance.Width = value
```

```
value = instance.Width
```

C#

```
System.int Width {get; set;}
```

C++/CLI

```
property System.int Width {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Line width as defined in [swLineWeights_e](#)

Visual Basic for Applications (VBA) Syntax

See [DrawingComponent.Width](#).

Example

[Get Components' Properties in Drawing View \(VBA\)](#)

Remarks

Use [IDrawingComponent::LayerOverride](#) to determine if this component is using its default layer line width.

See Also

[IDrawingComponent Interface](#)
[IDrawingComponent Members](#)
[IDrawingComponent::Style Property](#)
[IDrawingComponent::Layer Property](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0