

SOLIDWORKS API (.NET, VBA, C#) — Reference

(146/337) · [ILocalSketchPatternFeatureData](#) · [ILoftedBendsFeatureData](#)

SOLIDWORKS API Documentation (converted from CHM)

ILocalSketchPatternFeatureData (Type)

ILocalSketchPatternFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ILocalSketchPatternFeatureData Interface

Allows access to a sketch-driven component pattern feature in an assembly.
NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ILocalSketchPatternFeatureData

Visual Basic (Usage)



Dim instance As [ILocalSketchPatternFeatureData](#)

C#

public interface ILocalSketchPatternFeatureData

C++/CLI

public interface class ILocalSketchPatternFeatureData

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData](#).

Example

[Create Local Sketch-driven Pattern \(C#\)](#)
[Create Local Sketch-driven Pattern \(VB.NET\)](#)
[Create Local Sketch-driven Pattern \(VBA\)](#)

Remarks

Read [Pattern Features and their Feature Data Objects](#).
Before calling IFeatureManager::CreateDefinition, you must pre-select the entities needed to create the sketch-driven component pattern feature

To select...	Use a mark of...
Components to pattern	1
Sketch to define the pattern	16
Reference point as defined in swLocalSketchPatternReferencePoint_e	32

You must call [IFeatureManager::CreateFeature](#) after initializing this feature data object in order to successfully create the local sketch-driven pattern feature.

Accessors

[IFeature::GetDefinition](#)
[IFeatureManager::CreateDefinition](#)

Access Diagram

[LocalSketchPatternFeatureData](#)

See Also

[ILocalSketchPatternFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISketchPatternFeatureData Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ILocalSketchPatternFeatureData Interface Methods

[See Also](#)

[SolidWorks.Interop.sldworks Namespace](#) : ILocalSketchPatternFeatureData Interface

For a list of all members of this type, see [ILocalSketchPatternFeatureData members](#).

Public Methods

Name	Description
 AccessSelections	Gains access to the selections used to define this sketch-driven component pattern feature.
 GetBasePoint	Gets the data for the base point from which this sketch-driven component pattern feature is created.
 GetPatternComponentCount	Gets the number of components in this sketch-driven component pattern feature.
 GetReferencePointType	Gets the type of reference point of this sketch-driven component pattern feature.
 GetSkippedItemCount	Gets the number of components skipped in this sketch-driven component pattern feature.
 GetTransform	Gets the transform for the specified instance in this sketch-driven component pattern feature.
 ReleaseSelectionAccess	Releases access to the selections for this sketch-driven component pattern feature.

[Top](#)

See Also

[ILocalSketchPatternFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISketchPatternFeatureData Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ILocalSketchPatternFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)

[SolidWorks.Interop.sldworks Namespace](#) : ILocalSketchPatternFeatureData Interface

The following tables list the members exposed by [ILocalSketchPatternFeatureData](#).

Public Properties

Name	Description
 ForceUseSeedConfiguration	Gets or sets whether to synchronize the configuration of pattern components with the configuration of the seed component in this local sketch pattern feature.
 PatternComponentArray	Gets or sets the components to pattern for this sketch-driven component pattern feature.
 ReferencePoint	Gets or sets the type of reference point for this sketch-driven component pattern feature.
 SelectedPoint	Gets or sets the selected point for this sketch-driven component pattern feature.
 Sketch	Gets or sets the sketch for this sketch-driven component pattern feature.
 SkippedItemArray	Gets or sets the array of skipped components in this sketch-driven component pattern feature.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Gains access to the selections used to define this sketch-driven component pattern feature.
 GetBasePoint	Gets the data for the base point from which this sketch-driven component pattern feature is created.
 GetPatternComponentCount	Gets the number of components in this sketch-driven component pattern feature.
 GetReferencePointType	Gets the type of reference point of this sketch-driven component pattern feature.
 GetSkippedItemCount	Gets the number of components skipped in this sketch-driven component pattern feature.



[GetTransform](#)

Gets the transform for the specified instance in this sketch-driven component pattern feature.

[ReleaseSelectionAccess](#)

Releases access to the selections for this sketch-driven component pattern feature.

[Top](#)

See Also

[ILocalSketchPatternFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISketchPatternFeatureData Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ILocalSketchPatternFeatureData Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ILocalSketchPatternFeatureData Interface

For a list of all members of this type, see [ILocalSketchPatternFeatureData members](#).

Public Properties

Name	Description
 ForceUseSeedConfiguration	Gets or sets whether to synchronize the configuration of pattern components with the configuration of the seed component in this local sketch pattern feature.
 PatternComponentArray	Gets or sets the components to pattern for this sketch-driven component pattern feature.
 ReferencePoint	Gets or sets the type of reference point for this sketch-driven component pattern feature.
 SelectedPoint	Gets or sets the selected point for this sketch-driven component pattern feature.
 Sketch	Gets or sets the sketch for this sketch-driven component pattern feature.
 SkippedItemArray	Gets or sets the array of skipped components in this sketch-driven component pattern feature.

[Top](#)

See Also

[ILocalSketchPatternFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISketchPatternFeatureData Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

AccessSelections Method (ILocalSketchPatternFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : AccessSelections Method (ILocalSketchPatternFeatureData)

Gains access to the selections used to define this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections( _  
    ByVal TopDoc As System.Object, _  
    ByVal Component As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData  
Dim TopDoc As System.Object  
Dim Component As System.Object  
Dim value As System.Boolean  
  
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(
    System.object TopDoc,
    System.object Component
)
```

C++/CLI

```
System.bool AccessSelections(
    & System.Object^ TopDoc,
    & System.Object^ Component
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Top-level document (see **Remarks**)

Component

Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections are successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::AccessSelections](#).

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) if you modified the feature
- [ILocalSketchPatternFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ForceUseSeedConfiguration Property (ILocalSketchPatternFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : ForceUseSeedConfiguration Property (ILocalSketchPatternFeatureData)

Gets or sets whether to synchronize the configuration of pattern components with the configuration of the seed component in this local sketch pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Property ForceUseSeedConfiguration As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData
Dim value As System.Boolean
```

```
instance.ForceUseSeedConfiguration = value
```

```
value = instance.ForceUseSeedConfiguration
```

C#

```
System.bool ForceUseSeedConfiguration {get; set;}
```

C++/CLI

```
property System.bool ForceUseSeedConfiguration {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to use the seed component configuration for all pattern components, false to not

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::ForceUseSeedConfiguration](#).

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)

Availability

SOLIDWORKS 2021 FCS, Revision Number 29

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetBasePoint Method (ILocalSketchPatternFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : GetBasePoint Method (ILocalSketchPatternFeatureData)

Gets the data for the base point from which this sketch-driven component pattern feature is created.

.NET Syntax

Visual Basic (Declaration)

```
Function GetBasePoint() As System.Object
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData  
Dim value As System.Object  
  
value = instance.GetBasePoint()
```

C#

```
System.object GetBasePoint()
```

C++/CLI

```
System.Object^ GetBasePoint();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of doubles describing the x, y, and z values of the base point

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::GetBasePoint](#).

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetPatternComponentCount Method (ILocalSketchPatternFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : GetPatternComponentCount Method (ILocalSketchPatternFeatureData)

Gets the number of components in this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPatternComponentCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData  
Dim value As System.Integer  
  
value = instance.GetPatternComponentCount()
```

C#

```
System.int GetPatternComponentCount()
```

C++/CLI

```
System.int GetPatternComponentCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of components

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::GetPatternComponentCount](#).

Example

[Create Local Sketch-driven Pattern \(C#\)](#)
[Create Local Sketch-driven Pattern \(VB.NET\)](#)
[Create Local Sketch-driven Pattern \(VBA\)](#)

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)
[ILocalSketchPatternFeatureData::PatternComponentArray Property\(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetReferencePointType Method (ILocalSketchPatternFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : GetReferencePointType Method (ILocalSketchPatternFeatureData)

Gets the type of reference point of this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetReferencePointType() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData  
Dim value As System.Integer  
  
value = instance.GetReferencePointType()
```

C#

```
System.int GetReferencePointType()
```

C++/CLI

```
System.int GetReferencePointType();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Type of reference point as defined in [swLocalSketchPatternReferencePoint_e](#); -1 for default, origin, or none

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::GetReferencePointType](#).

Example

[Create Local Sketch-driven Pattern \(C#\)](#)
[Create Local Sketch-driven Pattern \(VB.NET\)](#)
[Create Local Sketch-driven Pattern \(VBA\)](#)

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)
[ILocalSketchPatternFeatureData::ReferencePoint Property\(\)](#)
[ILocalSketchPatternFeatureData::SelectedPoint Property\(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSkippedItemCount Method (ILocalSketchPatternFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : GetSkippedItemCount Method (ILocalSketchPatternFeatureData)

Gets the number of components skipped in this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSkippedItemCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData  
Dim value As System.Integer
```



```
value = instance.GetSkippedItemCount()
```

C#

```
System.int GetSkippedItemCount()
```

C++/CLI

```
System.int GetSkippedItemCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of components skipped

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::GetSkippedItemCount](#).

Example

[Create Local Sketch-driven Pattern \(C#\)](#)
[Create Local Sketch-driven Pattern \(VB.NET\)](#)
[Create Local Sketch-driven Pattern \(VBA\)](#)

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)
[ILocalSketchPatternFeatureData::SkippedItemArray Property\(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetTransform Method (ILocalSketchPatternFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : GetTransform Method (ILocalSketchPatternFeatureData)

Gets the transform for the specified instance in this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetTransform( _  
    ByVal Instance As System.Integer _  
) As MathTransform
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData  
Dim Instance As System.Integer  
Dim value As MathTransform  
  
value = instance.GetTransform(Instance)
```

C#

```
MathTransform GetTransform(  
    System.int Instance  
)
```

C++/CLI

```
MathTransform^ GetTransform(  
& System.int Instance  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Instance
Index of one repeating element in this local sketch-driven pattern feature (see **Remarks**)

Return Value

[Transform](#)

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::GetTransform](#).

Remarks

Valid values for Instance are 1 <= Instance <= [ILocalSketchPatternFeatureData::GetPatternComponentCount](#)

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PatternComponentArray Property (ILocalSketchPatternFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : PatternComponentArray Property (ILocalSketchPatternFeatureData)

Gets or sets the components to pattern for this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Property PatternComponentArray As System.Object
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData  
Dim value As System.Object
```

```
instance.PatternComponentArray = value  
value = instance.PatternComponentArray
```

C#

```
System.object PatternComponentArray {get; set;}
```

C++/CLI

```
property System.Object^ PatternComponentArray {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of [components](#)

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::PatternComponentArray](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this property.

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)
[ILocalSketchPatternFeatureData::GetPatternComponentCount Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ReferencePoint Property (ILocalSketchPatternFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : ReferencePoint Property (ILocalSketchPatternFeatureData)

Gets or sets the type of reference point for this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Property ReferencePoint As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData  
Dim value As System.Integer
```

```
instance.ReferencePoint = value
```

```
value = instance.ReferencePoint
```

C#

```
System.int ReferencePoint {get; set;}
```

C++/CLI

```
property System.int ReferencePoint {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of reference point as defined in [swLocalSketchPatternReferencePoint_e](#)

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::ReferencePoint](#).

Example

[Create Local Sketch-driven Pattern \(C#\)](#)
[Create Local Sketch-driven Pattern \(VB.NET\)](#)
[Create Local Sketch-driven Pattern \(VBA\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this property.

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)
[ILocalSketchPatternFeatureData::GetReferencePointType Method \(\)](#)
[ILocalSketchPatternFeatureData::SelectedPoint Property \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ReleaseSelectionAccess Method (ILocalSketchPatternFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : ReleaseSelectionAccess Method (ILocalSketchPatternFeatureData)

Releases access to the selections for this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ReleaseSelectionAccess()
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData
```

```
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::ReleaseSelectionAccess](#).

Remarks

[ILocalSketchPatternFeatureData::AccessSelections](#) puts the model into a rollback state to allow access to the selections that define this feature. Use this method to restore the rollback state if you did not modify the feature, or use [IFeature::ModifyDefinition](#) if you did.

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SelectedPoint Property (ILocalSketchPatternFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : SelectedPoint Property (ILocalSketchPatternFeatureData)

Gets or sets the selected point for this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Property SelectedPoint As SketchPoint
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData  
Dim value As SketchPoint
```

```
instance.SelectedPoint = value
```

```
value = instance.SelectedPoint
```

C#

```
SketchPoint SelectedPoint {get; set;}
```

C++/CLI

```
property SketchPoint^ SelectedPoint {  
    SketchPoint^ get();  
    void set ( & SketchPoint^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[Point](#)

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::SelectedPoint](#).

Remarks

This property is valid only if [ILocalSketchPatternFeatureData::ReferencePoint](#) is set to [swLocalSketchPatternReferencePoint_e.swLocalSketchPatternSelectedPoint](#).

See [Accessing Selections that Define Features](#) for additional details on using this property.

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)
[ILocalSketchPatternFeatureData::GetReferencePointType Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Sketch Property (ILocalSketchPatternFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : Sketch Property (ILocalSketchPatternFeatureData)

Gets or sets the sketch for this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

Property Sketch As System.Object

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData
Dim value As System.Object

instance.Sketch = value

value = instance.Sketch
```

C#

```
System.object Sketch {get; set;}
```

C++/CLI

```
property System.Object^ Sketch {
    System.Object^ get();
    void set ( & System.Object^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[Sketch](#)

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::Sketch](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this property.

See Also

[ILocalSketchPatternFeatureData Interface](#)
[ILocalSketchPatternFeatureData Members](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SkippedItemArray Property (ILocalSketchPatternFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILocalSketchPatternFeatureData Interface](#) : SkippedItemArray Property (ILocalSketchPatternFeatureData)

Gets or sets the array of skipped components in this sketch-driven component pattern feature.

.NET Syntax

Visual Basic (Declaration)

```
Property SkippedItemArray As System.Object
```

Visual Basic (Usage)



```
Dim instance As ILocalSketchPatternFeatureData
Dim value As System.Object

instance.SkippedItemArray = value

value = instance.SkippedItemArray
```

C#

```
System.Object SkippedItemArray {get; set;}
```

C++/CLI

```
property System.Object^ SkippedItemArray {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of integers representing skipped components

Visual Basic for Applications (VBA) Syntax

See [LocalSketchPatternFeatureData::SkippedItemArray](#).

Remarks

This array is 0-based. If you skip the third and fifth components, then the array looks like ArrayOut[0]=3 and ArrayOut[1]=5.

See [Accessing Selections that Define Features](#) for additional details on using this property.

See Also

[ILocalSketchPatternFeatureData Interface](#)

[ILocalSketchPatternFeatureData Members](#)

[ILocalSketchPatternFeatureData::GetSkippedItemCount Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

ILockMateFeatureData (Type)

ILockMateFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ILockMateFeatureData Interface

Allows access to lock mate features.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface ILockMateFeatureData

Visual Basic (Usage)

Dim instance As [ILockMateFeatureData](#)

C#

public interface ILockMateFeatureData

C++/CLI

public interface class ILockMateFeatureData

Visual Basic for Applications (VBA) Syntax

See [LockMateFeatureData](#).

Example

[Create Standard Mates \(VBA\)](#)
[Create Standard Mates \(C#\)](#)

Remarks

A lock mate:

- Maintains the position and orientation between two components.
- Fully constrains the components.
- Is like a rigid subassembly of components.

[IMateFeatureData](#) is the parent of this mate interface.

To create a lock mate:

1. Follow general instructions in the [IAssemblyDoc::CreateMate](#) Remarks.
2. Specify [ILockMateFeatureData::EntitiesToMate](#) or use [IModelDocExtension::SelectById2](#) to pre-select the entities to mate using Mark = 1.

To edit a lock mate:

1. Access its feature and call [IFeature::GetDefinition](#) to get the MateFeatureData object.
2. Cast the MateFeatureData object to a LockMateFeatureData object.
3. Modify the LockMateFeatureData object.
4. Call [IFeature::ModifyDefinition](#).

To delete this lock mate, use [IModelDocExtension::DeleteSelection2](#).

Access Diagram

[LockMateFeatureData](#)

See Also

[ILockMateFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

ILockMateFeatureData Interface Members

[See Also](#) [Properties](#)



[SolidWorks.Interop.sldworks Namespace](#) : ILockMateFeatureData Interface

The following tables list the members exposed by [ILockMateFeatureData](#).

Public Properties

Name	Description
EntitiesToMate	Gets or sets the entities to mate in this lock mate.

[Top](#)

See Also

[ILockMateFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ILockMateFeatureData Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ILockMateFeatureData Interface

For a list of all members of this type, see [ILockMateFeatureData members](#).

Public Properties

Name	Description
EntitiesToMate	Gets or sets the entities to mate in this lock mate.

[Top](#)

See Also

[ILockMateFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

EntitiesToMate Property (ILockMateFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILockMateFeatureData Interface](#) : EntitiesToMate Property (ILockMateFeatureData)

Gets or sets the entities to mate in this lock mate.

.NET Syntax

Visual Basic (Declaration)

```
Property EntitiesToMate As System.Object
```

Visual Basic (Usage)



```
Dim instance As ILockMateFeatureData  
Dim value As System.Object
```

```
instance.EntitiesToMate = value
```

```
value = instance.EntitiesToMate
```

C#

```
System.Object EntitiesToMate {get; set;}
```

C++/CLI

```
property System.Object^ EntitiesToMate {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of entities to mate (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [LockMateFeatureData::EntitiesToMate](#).

Example

See the [ILockMateFeatureData](#) example.

Remarks

Instead of specifying this property, you can use [IModelDocExtension::SelectByID2](#) to pre-select the entities to mate using Mark = 1. You can pre-select mate entities during mate creation, but not during mate editing.

See Also

[ILockMateFeatureData Interface](#)
[ILockMateFeatureData Members](#)

Availability

SOLIDWORKS 2019 FCS, Revision Number 27.0

ILoftedBendsFeatureData (Type)

ILoftedBendsFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ILoftedBendsFeatureData Interface

Allows access to display information for a lofted bends feature.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ILoftedBendsFeatureData
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData
```

C#

```
public interface ILoftedBendsFeatureData
```

C++/CLI

```
public interface class ILoftedBendsFeatureData
```

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData](#).

Example

[Insert Lofted Bend Feature \(VBA\)](#)
[Insert Lofted Bend Feature \(VB.NET\)](#)
[Insert Lofted Bend Feature \(C#\)](#)

Accessors

[IFeature::GetDefinition](#) and [IFeature::!GetDefinition](#)

Access Diagram

[LoftedBendsFeatureData](#)

See Also

[ILoftedBendsFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertSheetMetalLoftedBend Method](#)
[ISheetMetalFeatureData Interface](#)

ILoftedBendsFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ILoftedBendsFeatureData Interface

The following tables list the members exposed by [ILoftedBendsFeatureData](#).

Public Properties

Name	Description
 BendLineControlOption	Gets or sets the lofted bend line control options.
Direction	Gets or sets the thickness direction of this lofted bends feature.

		
	FacetingOption	Gets or sets how facets are created in this lofted bend feature.
	FacetValue	Gets or sets the value corresponding to ILoftedBendsFeatureData.FacetingOption .
	FormedMethod	Gets or sets whether this lofted bend feature is formed.
	MaximumDeviation	Gets or sets the maximum deviation for the bend lines in a lofted bend feature.
	NumberOfBendLines	Gets or sets the number of bend lines in this lofted bend feature.
	Profiles	Gets or sets the profiles for this lofted bends feature.
	ReferToEndPoint	Gets or sets whether to calculate facet transitions using theoretical vertexes.
	SymmetricThickness	Gets or sets whether to symmetrically thicken this bi-directional lofted bends feature.
	Thickness	Gets or sets the thickness for this lofted bends feature.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Accesses the selections used to define the lofted bends feature.
 CanCreateBendLines	Gets whether the bend lines parameters affect this lofted bend feature.
 GetProfileCount	Gets the number of profiles in this lofted bends feature.
 IAccessSelections	Accesses the selections used to define the lofted bends feature
 IGetProfiles	Gets the profiles for this lofted bends feature.
 ISetProfiles	Sets the profiles for this lofted bends feature.
 ReleaseSelectionAccess	Releases access to the selections for this lofted bends feature.

[Top](#)

See Also

[ILoftedBendsFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager.InsertSheetMetalLoftedBend Method](#)
[ISheetMetalFeatureData Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ILoftedBendsFeatureData Interface Methods

[See Also](#)

	SolidWorks.Interop.sldworks Namespace : ILoftedBendsFeatureData Interface
---	---

For a list of all members of this type, see [ILoftedBendsFeatureData members](#).

Public Methods

Name	Description
 AccessSelections	Accesses the selections used to define the lofted bends feature.
 CanCreateBendLines	Gets whether the bend lines parameters affect this lofted bend feature.
 GetProfileCount	Gets the number of profiles in this lofted bends feature.
 IAccessSelections	Accesses the selections used to define the lofted bends feature
 IGetProfiles	Gets the profiles for this lofted bends feature.
 ISetProfiles	Sets the profiles for this lofted bends feature.
 ReleaseSelectionAccess	Releases access to the selections for this lofted bends feature.

[Top](#)

See Also

ILoftedBendsFeatureData Interface Properties

[See Also](#)

[SolidWorks.Interop.sldworks Namespace](#) : ILoftedBendsFeatureData Interface

For a list of all members of this type, see [ILoftedBendsFeatureData members](#).

Public Properties

Name	Description
 BendLineControlOption	Gets or sets the lofted bend line control options.
 Direction	Gets or sets the thickness direction of this lofted bends feature.
 FacetingOption	Gets or sets how facets are created in this lofted bend feature.
 FacetValue	Gets or sets the value corresponding to ILoftedBendsFeatureData.FacetingOption .
 FormedMethod	Gets or sets whether this lofted bend feature is formed.
 MaximumDeviation	Gets or sets the maximum deviation for the bend lines in a lofted bend feature.
 NumberOfBendLines	Gets or sets the number of bend lines in this lofted bend feature.
 Profiles	Gets or sets the profiles for this lofted bends feature.
 ReferToEndPoint	Gets or sets whether to calculate facet transitions using theoretical vertexes.
 SymmetricThickness	Gets or sets whether to symmetrically thicken this bi-directional lofted bends feature.
 Thickness	Gets or sets the thickness for this lofted bends feature.

[Top](#)

See Also

[ILoftedBendsFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertSheetMetalLoftedBend Method](#)
[ISheetMetalFeatureData Interface](#)

AccessSelections Method (ILoftedBendsFeatureData)

[See Also](#)

[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : AccessSelections Method (ILoftedBendsFeatureData)

Accesses the selections used to define the lofted bends feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections( _  
    ByVal TopDoc As System.Object, _  
    ByVal Component As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)

```
Dim instance As ILoftedBendsFeatureData  
Dim TopDoc As System.Object  
Dim Component As System.Object  
Dim value As System.Boolean  
  
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(  
    System.object TopDoc,  
    System.object Component  
)
```

C++/CLI

```
System.bool AccessSelections(  
& System.Object^ TopDoc,  
& System.Object^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Top-level document (see **Remarks**)

Component

Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections were accessed successfully, false if not

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::AccessSelections](#).

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) if you modified the feature
- [ILoftedBendsFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[ILoftedBendsFeatureData Interface](#)

[ILoftedBendsFeatureData Members](#)

[ILoftedBendsFeatureData::AccessSelections Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

BendLineControlOption Property (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : BendLineControlOption Property (ILoftedBendsFeatureData)

Gets or sets the lofted bend line control options.

.NET Syntax

Visual Basic (Declaration)

```
Property BendLineControlOption As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData
```

```
Dim value As System.Integer
```

```
instance.BendLineControlOption = value
```

```
value = instance.BendLineControlOption
```

C#

```
System.int BendLineControlOption {get; set;}
```

C++/CLI

```
property System.int BendLineControlOption {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Lofted bend line control options as defined in [swBendLineControlOption_e](#)

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::BendLineControlOption](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::CanCreateBendLines Method](#)
[ILoftedBendsFeatureData::MaximumDeviation Property](#)
[ILoftedBendsFeatureData::NumberOfBendLines Property](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

CanCreateBendLines Method (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : CanCreateBendLines Method (ILoftedBendsFeatureData)

Gets whether the bend lines parameters affect this lofted bend feature.

.NET Syntax

Visual Basic (Declaration)

```
Function CanCreateBendLines() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData  
Dim value As System.Boolean
```

```
value = instance.CanCreateBendLines()
```

C#

```
System.bool CanCreateBendLines()
```

C++/CLI

```
System.bool CanCreateBendLines();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if bend lines parameters affect this lofted bend feature, false if not

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::CanCreateBendLines](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::BendLineControlOption Property](#)
[ILoftedBendsFeatureData::MaximumDeviation Property](#)
[ILoftedBendsFeatureData::NumberOfBendLines Property](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Direction Property (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : Direction Property (ILoftedBendsFeatureData)

Gets or sets the thickness direction of this lofted bends feature.

.NET Syntax

Visual Basic (Declaration)

Property Direction As System.Boolean

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData  
Dim value As System.Boolean
```

```
instance.Direction = value
```

```
value = instance.Direction
```

C#

```
System.bool Direction {get; set;}
```

C++/CLI

```
property System.bool Direction {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True reverses the direction, false does not

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::Direction](#).

Example

See examples for [ILoftedBendsFeatureData](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)

Availability

FacetingOption Property (ILoftedBendsFeatureData)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : FacetingOption Property (ILoftedBendsFeatureData)

Gets or sets how facets are created in this lofted bend feature.

.NET Syntax

Visual Basic (Declaration)

Property FacetingOption As System.Integer

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData
Dim value As System.Integer
```

```
instance.FacetingOption = value
```

```
value = instance.FacetingOption
```

C#

```
System.int FacetingOption {get; set;}
```

C++/CLI

```
property System.int FacetingOption {
    System.int get();
    void set ( & System.int value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).**Property Value**Faceting option as defined in [swLoftedBendFacetOptions_e](#)

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::FacetingOption](#).

Example

See examples for [ILoftedBendsFeatureData](#).

Remarks

This property is valid only if [ILoftedBendsFeatureData::FormedMethod](#) is false.After setting this property, set [ILoftedBendsFeatureData::FacetValue](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::ReferToEndPoint Property\(\)](#)

Availability

SOLIDWORKS 2014 FCS, Revision Number 22.0

FacetValue Property (ILoftedBendsFeatureData)

[See Also](#)

Gets or sets the value corresponding to [ILoftedBendsFeatureData::FacetingOption](#).

.NET Syntax

Visual Basic (Declaration)

```
Property FacetValue As System.Double
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData
Dim value As System.Double

instance.FacetValue = value

value = instance.FacetValue
```

C#

```
System.double FacetValue {get; set;}
```

C++/CLI

```
property System.double FacetValue {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Faceting option value

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::FacetValue](#).

Example

See examples for [ILoftedBendsFeatureData](#).

Remarks

This property is valid only if [ILoftedBendsFeatureData::FormedMethod](#) is false.

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::ReferToEndPoint Property \(\)](#)

Availability

SOLIDWORKS 2014 FCS, Revision Number 22.0

FormedMethod Property (ILoftedBendsFeatureData)

[See Also](#)



Gets or sets whether this lofted bend feature is formed.

.NET Syntax

Visual Basic (Declaration)

Property FormedMethod As System.Boolean

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData  
Dim value As System.Boolean  
  
instance.FormedMethod = value  
  
value = instance.FormedMethod
```

C#

```
System.bool FormedMethod {get; set;}
```

C++/CLI

```
property System.bool FormedMethod {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True if this lofted bend feature is formed, false if it is bent

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::FormedMethod](#).

Example

See examples for [ILoftedBendsFeatureData](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::FacetingOption Property \(\)](#)
[ILoftedBendsFeatureData::FacetValue Property \(\)](#)
[ILoftedBendsFeatureData::ReferToEndPoint Property \(\)](#)

Availability

SOLIDWORKS 2014 FCS, Revision Number 22.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetProfileCount Method (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : GetProfileCount Method (ILoftedBendsFeatureData)

Gets the number of profiles in this lofted bends feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetProfileCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData  
Dim value As System.Integer  
  
value = instance.GetProfileCount()
```

C#

```
System.int GetProfileCount()
```

C++/CLI

```
System.int GetProfileCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of profiles

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::GetProfileCount](#).

Example

See examples for [ILoftedBendsFeatureData](#).

Remarks

Call this method before calling [ILoftedBendsFeatureData::IGetProfiles](#) to determine the size of the array for that method.

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::ISetProfiles Method](#)
[ILoftedBendsFeatureData::Profiles Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

IAccessSelections Method (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : IAccessSelections Method (ILoftedBendsFeatureData)

Accesses the selections used to define the lofted bends feature

.NET Syntax

Visual Basic (Declaration)

```
Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
    ) As System.Boolean
```

Visual Basic (Usage)

```
Dim instance As ILoftedBendsFeatureData  
Dim TopDoc As ModelDoc2  
Dim Component As Component2  
Dim value As System.Boolean  
  
value = instance.IAccessSelections(TopDoc, Component)
```

C#



```
System.bool IAccessSelections(  
    ModelDoc2 TopDoc,  
    Component2 Component  
)
```

C++/CLI

```
System.bool IAccessSelections(  
& ModelDoc2^ TopDoc,  
& Component2^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Top-level document (see **Remarks**)

Component

Component in which the feature is to be modified (see **Remarks**)

Return Value

Component in which the feature is to be modified (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::IAccessSelections](#).

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::IModifyDefinition2](#) if you modified the feature
- [ILoftedBendsFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[ILoftedBendsFeatureData Interface](#)

[ILoftedBendsFeatureData Members](#)

[ILoftedBendsFeatureData::AccessSelections Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetProfiles Method (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : IGetProfiles Method (ILoftedBendsFeatureData)

Gets the profiles for this lofted bends feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetProfiles( _  
    ByVal Count As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData  
Dim Count As System.Integer
```

```
Dim value As System.Object  
  
value = instance.IGetProfiles(Count)
```

C#

```
System.object IGetProfiles(  
    System.int Count  
)
```

C++/CLI

```
System.Object^ IGetProfiles(  
& System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count
Number of profiles

Return Value

- in-process, unmanaged C++: Pointer to an array profiles of size Count
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Call [ILoftedBendsFeatureData::GetProfileCount](#) before calling this method to get the size for Count.

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::ISetProfiles Method](#)
[ILoftedBendsFeatureData::Profiles Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISetProfiles Method (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : ISetProfiles Method (ILoftedBendsFeatureData)

Sets the profiles for this lofted bends feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetProfiles(  
    ByVal Count As System.Integer, _  
    ByRef PDisp As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData  
Dim Count As System.Integer  
Dim PDisp As System.Object  
  
instance.ISetProfiles(Count, PDisp)
```

C#

```
void ISetProfiles(
    System.int Count,
    ref System.object PDisp
)
```

C++/CLI

```
void ISetProfiles(
    & System.int Count,
    & System.Object^% PDisp
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of profiles

PDisp

in-process, unmanaged C++: Pointer to an array of profiles of size Count

- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::GetProfileCount Method](#)
[ILoftedBendsFeatureData::IGetProfiles Method](#)
[ILoftedBendsFeatureData::Profiles Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

MaximumDeviation Property (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : MaximumDeviation Property (ILoftedBendsFeatureData)

Gets or sets the maximum deviation for the bend lines in a lofted bend feature.

.NET Syntax

Visual Basic (Declaration)

```
Property MaximumDeviation As System.Double
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData
Dim value As System.Double
```

```
instance.MaximumDeviation = value
```

```
value = instance.MaximumDeviation
```

C#

```
System.double MaximumDeviation {get; set;}
```

C++/CLI

```
property System.double MaximumDeviation {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Maximum deviation for the bend lines in a lofted bend feature

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::MaximumDeviation](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::CanCreateBendLines Method](#)
[ILoftedBendsFeatureData::BendLineControlOption Property](#)
[ILoftedBendsFeatureData::NumberOfBendLines Property](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

NumberOfBendLines Property (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : NumberOfBendLines Property (ILoftedBendsFeatureData)

Gets or sets the number of bend lines in this lofted bend feature.

.NET Syntax

Visual Basic (Declaration)

```
Property NumberOfBendLines As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData
Dim value As System.Integer
```

```
instance.NumberOfBendLines = value
```

```
value = instance.NumberOfBendLines
```

C#

```
System.int NumberOfBendLines {get; set;}
```

C++/CLI

```
property System.int NumberOfBendLines {
    System.int get();
    void set ( & System.int value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Number of bend lines in this lofted bend feature

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::NumberOfBendLines](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::CanCreateBendLines Method](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Profiles Property (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : Profiles Property (ILoftedBendsFeatureData)

Gets or sets the profiles for this lofted bends feature.

.NET Syntax

Visual Basic (Declaration)

Property Profiles As System.Object

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData
Dim value As System.Object

instance.Profiles = value
value = instance.Profiles
```

C#

```
System.object Profiles {get; set;}
```

C++/CLI

```
property System.Object^ Profiles {
    System.Object^ get();
    void set ( & System.Object^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of profiles for this lofted bends feature

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::Profiles](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::GetProfileCount Method](#)
[ILoftedBendsFeatureData::GetProfiles Method](#)
[ILoftedBendsFeatureData::SetProfiles Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ReferToEndPoint Property (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : ReferToEndPoint Property (ILoftedBendsFeatureData)

Gets or sets whether to calculate facet transitions using theoretical vertexes.

.NET Syntax

Visual Basic (Declaration)

Property ReferToEndPoint As System.Boolean

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData
Dim value As System.Boolean

instance.ReferToEndPoint = value

value = instance.ReferToEndPoint
```

C#

```
System.bool ReferToEndPoint {get; set;}
```

C++/CLI

```
property System.bool ReferToEndPoint {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to calculate facet transitions using theoretical vertexes, false to calculate them using the smallest possible arcs that avoid interference between bend areas

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::ReferToEndPoint](#).

Example

See examples for [ILoftedBendsFeatureData](#).

Remarks

This property is valid only if [ILoftedBendsFeatureData::FormedMethod](#) is false.

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)
[ILoftedBendsFeatureData::FacetingOption Property\(\)](#)
[ILoftedBendsFeatureData::FacetValue Property\(\)](#)
[ILoftedBendsFeatureData::FormedMethod Property\(\)](#)

Availability

SOLIDWORKS 2014 FCS, Revision Number 22.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ReleaseSelectionAccess Method (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : ReleaseSelectionAccess Method (ILoftedBendsFeatureData)

Releases access to the selections for this lofted bends feature.

.NET Syntax

Visual Basic (Declaration)

Sub ReleaseSelectionAccess()

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData  
  
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::ReleaseSelectionAccess](#).

Remarks

[ILoftedBendsFeatureData::AccessSelections](#) and [ILoftedBendsFeatureData::!AccessSelections](#) put the model into a rollback state to allow access to the selections that define this feature.

Use this method to restore the rollback state if you did not modify the feature or use [IFeature::ModifyDefinition](#) or [IFeature::!ModifyDefintion2](#) if you did.

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SymmetricThickness Property (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : SymmetricThickness Property (ILoftedBendsFeatureData)

Gets or sets whether to symmetrically thicken this bi-directional lofted bends feature.

.NET Syntax

Visual Basic (Declaration)

```
Property SymmetricThickness As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData  
Dim value As System.Boolean  
  
instance.SymmetricThickness = value  
  
value = instance.SymmetricThickness
```

C#

```
System.bool SymmetricThickness {get; set;}
```

C++/CLI

```
property System.bool SymmetricThickness {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to thicken symmetrically, false to not

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::SymmetricThickness](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)

Availability

SOLIDWORKS 2023 FCS, Revision Number 31

SOLIDWORKS API Help

[Send comments on this topic.](#)

Thickness Property (ILoftedBendsFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ILoftedBendsFeatureData Interface](#) : Thickness Property (ILoftedBendsFeatureData)

Gets or sets the thickness for this lofted bends feature.

.NET Syntax

Visual Basic (Declaration)

```
Property Thickness As System.Double
```

Visual Basic (Usage)



```
Dim instance As ILoftedBendsFeatureData
Dim value As System.Double

instance.Thickness = value
value = instance.Thickness
```

C#

```
System.double Thickness {get; set;}
```

C++/CLI

```
property System.double Thickness {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Thickness of this lofted bends feature

Visual Basic for Applications (VBA) Syntax

See [LoftedBendsFeatureData::Thickness](#).

Example

See examples for [ILoftedBendsFeatureData](#).

See Also

[ILoftedBendsFeatureData Interface](#)
[ILoftedBendsFeatureData Members](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0