

SOLIDWORKS API (.NET VBA C#) — Reference (149/337): IMacroFeatureData (part 1 of 2)

SOLIDWORKS API Documentation (converted from CHM)

IMacroFeatureData (part 1 of 2) (Type)

 

[SolidWorks.Interop.sldworks Namespace](#) : IMacroFeatureData Interface

Allows access to the data that defines a macro feature.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IMacroFeatureData

Visual Basic (Usage)

Dim instance As [IMacroFeatureData](#)

C#

public interface IMacroFeatureData

C++/CLI

public interface class IMacroFeatureData

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData](#).

Example

[Create Macro Feature Subfeature \(VBA\)](#)
[Cut Body in Half Using Macro Feature \(VBA\)](#)
[Assign Tracking ID Using Macro Feature \(VBA\)](#)

Remarks

Macro features can...	For the rebuild function only, the macro associated with a macro feature cannot:
- be inserted into a part, assembly, or drawing document - create multiple bodies - edit multiple existing bodies	- insert a feature from a macro feature in the same model - edit definitions of other features if these features are in the same model as the macro feature - rebuild, roll back, or roll forward the FeatureManager design tree NOTE: These limitations are intended to prevent nested-feature regeneration in the model that contains the macro feature.

When the feature is creating multiple bodies, then the return value from the rebuild function should contain the array of bodies that are the result of the operation. [IMacroFeatureData::EditBodies](#) is not expected to contain a body when the rebuild function returns to SOLIDWORKS.

When the feature is modifying a body and the result is multiple bodies, then IMacroFeatureData::EditBodies should contain all of the resulting bodies.

Whether creating multiple bodies or modifying a body that results in multiple bodies, call [IMacroFeatureData::EnableMultiBodyConsume](#) from the [rebuild](#) function to specify whether multiple bodies replace or append the original edit body in the FeatureManager design tree Solid Bodies folder.

If your application allows the user to decide which bodies to keep, your application must determine what it means to select the bodies and subsequently store the selected bodies with the feature.

To edit a macro feature in a drawing, do not use [IMacroFeatureData::AccessSelections](#), [IMacroFeatureData::IAccessSelections](#), or [IMacroFeatureData::ReleaseSelectionAccess](#) because the concept of a rollback bar does not exist. You can still use [IFeature::ModifyDefinition](#) or [IFeature::ModifyDefinition2](#) to update an IMacroFeatureData object.

If the user decides to cancel the changes made to the IMacroFeatureData object, then discard the IMacroFeatureData object. This action is equivalent to using IMacroFeatureData::ReleaseSelectionAccess.

See [Overview of Macro Features](#) for more information.

 Accessors

[IFeature::GetDefinition](#)

 Access Diagram

[MacroFeatureData](#)

 See Also

[IMacroFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertMacroFeature3 Method](#)
[IFeatureManager::InsertMacroFeature3 Method](#)

IMacroFeatureData Interface Methods

[See Also](#)


SolidWorks.Interop.sldworks Namespace : IMacroFeatureData Interface

For a list of all members of this type, see [IMacroFeatureData members](#).

 Public Methods

Name	Description
 AccessSelections	Gains access to the selections associated with this macro feature.
 EmbedMacroFile	Sets whether to embed the macro file in the model with the macro feature.
 GetBaseName	Gets the name of the base feature for this macro feature.
 GetDisplayDimensionCount	Gets the number of display dimensions for this macro feature.
 GetDisplayDimensions	Gets the display dimensions for this macro feature.
 GetDoubleByName	Gets a double value by parameter name.
 GetEdgeIdType	Gets the ID type of the specified edge for the macro feature.
 GetEdgeUserId	Gets the user-defined IDs for the specified edge for the macro feature.
 GetEditBodiesCount	Gets the number of bodies to be modified by this macro feature.
 GetEditTargetTransform	Gets the transform of the component where the macro feature resides if at least one selection in the macro feature belongs to a different component.
 GetEntitiesNeedUserId	Gets a list of faces and edges that need be assigned user IDs for the macro feature.
 GetEntitiesNeedUserIdCount	Gets the number of faces and edges that need to be assigned user IDs for the macro feature.
 GetFacetIdType	Gets the ID type from the face for the macro feature.
 GetFaceUserId	Gets the user-defined IDs for the specified face.
 GetIconFileCount	Gets the number of the files for the icons for this macro feature.
 GetIntegerByName	Gets an integer value by parameter name.
 GetModuleCount	Gets the number of modules for the macro feature.
 GetModuleNames	Gets the names of the modules in the macro for the macro feature.
 GetParameterCount	Gets the number of user-defined parameters.
 GetParameters	Gets the user-defined parameters.
 GetParentsCount	Gets the number of parent features for this macro feature.
 GetProcedureCount	Gets the number of procedures in the specified module in the macro for this macro feature.
 GetProcedureNames	Gets the names of the procedures in the specified module for the macro for the macro feature.
 GetProgId	Gets the version-independent program ID that is valid for this COM feature.

	GetPropertyManagerHandleModuleCount	Gets the number of modules in the macro from the PropertyManager handle for the macro feature.
	GetPropertyManagerHandleModuleNames	Gets the names of the modules in the macro from the PropertyManager handle for the macro feature.
	GetPropertyManagerHandleProcedureCount	Gets the number of procedures in the specified module in the macro from the PropertyManager handle for this macro feature.
	GetPropertyManagerHandleProcedureNames	Gets the names of the procedures in the specified module in the macro from the PropertyManager handle for the macro feature.
	GetSelectionCount	Gets the number of selected objects for the macro feature.
	GetSelections	Obsolete. Superseded by IMacroFeatureData::GetSelections3 .
	GetSelections2	Obsolete. Superseded by IMacroFeatureData::GetSelections3 .
	GetSelections3	Gets the selected objects for the macro feature.
	GetStringByName	Gets a string value by the name of the parameter for the macro feature.
	IAccessSelections	Gains access to the selections associated with this macro feature.
	IAddDisplayDimensions	Adds the specified display dimensions to this macro feature.
	IGetDisplayDimensions	Gets the display dimensions for this macro feature.
	IGetEditBodies	Gets the bodies to be modified by this macro feature.
	IGetEntitiesNeedUserId	Gets a list of faces and edges that need be assigned user IDs for the macro feature.
	IGetIconFiles	Gets the file names for the icons for this macro feature.
	IGetModuleNames	Gets the names of the modules in the macro for the macro feature.
	IGetParameters	Gets the user-defined parameters.
	IGetParents	Gets the parent features of this macro feature.
	IGetProcedureNames	Gets the names of the procedures in the specified module in the macro for the macro feature.
	IGetPropertyManagerHandleModuleNames	Gets the names of the modules in the macro from the PropertyManager handle for the macro feature.
	IGetPropertyManagerHandleProcedureNames	Gets the names of the procedures in the specified module in the macro from the PropertyManager handle for the macro feature.
	IGetSelections	Obsolete. Superseded by IMacroFeatureData::IGetSelections3 .
	IGetSelections2	Obsolete. Superseded by IMacroFeatureData::IGetSelections3 .
	IGetSelections3	Gets the selected objects for the macro feature.
	IsCOMFeature	Gets whether the feature is a COM feature.
	ISetEditBodies	Sets the bodies to be modified by this macro feature.
	ISetIconFiles	Sets the file names for the icons for this macro feature.
	ISetParameters	Sets the user-defined parameters.
	ISetParents	Sets the parent features for this macro feature.
	ISetSelections	Obsolete. Superseded by IMacroFeatureData::ISetSelections2 .
	ISetSelections2	Sets the selected objects for the macro feature.
	ReleaseSelectionAccess	Releases access to the selections associated with this macro feature.
	SetDoubleByName	Sets a double value by parameter name for the macro feature.
	SetEdgeUserId	Sets the user-defined IDs for the specified edge for the macro feature.
	SetFaceUserId	Sets user-defined IDs for the face for the macro feature.
	SetIntegerByName	Sets an integer value by parameter name.
	SetParameters	Sets the user-defined parameters.
	SetProgId	Sets the version-independent program ID that is valid for this COM feature.
	SetSelections	Obsolete. Superseded by IMacroFeatureData::SetSelections2 .
	SetSelections2	Sets the selected objects for the macro feature.
	SetStringByName	Sets a string value by parameter name.

See Also

[IMacroFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertMacroFeature3 Method](#)
[IFeatureManager::InsertMacroFeature3 Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IMacroFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)

[SolidWorks.Interop.sldworks Namespace](#) : IMacroFeatureData Interface

The following tables list the members exposed by [IMacroFeatureData](#).

Public Properties

Name	Description
 CurrentConfiguration	Gets the macro feature configuration being rebuilt.
 EditBodies	Gets or sets the bodies to be modified by this macro feature.
 EditBody	Obsolete. Superseded by IMacroFeatureData::IGetEditBodies , IMacroFeatureData::ISetEditBodies , and IMacroFeatureData::EditBodies .
 EnableMultiBodyConsume	Gets or sets whether to replace the original edit body with multiple solid bodies created during regeneration of a multibody macro feature.
 FeatureTransform	Gets and sets the macro feature transform.
 IconFiles	Gets or sets the file names for the icons for this macro feature.
 MacroFileEmbedded	Gets whether the macro file is embedded in the model with the macro feature.
 MacroFileName	Gets or sets the path and file name for the macro for the macro feature.
 ModuleName	Gets or sets the name of a module in the macro for this macro feature.
 Parents	Gets or sets the parent features for this macro feature.
 PatternTransform	Gets the pattern transform.
 ProcedureName	Gets or sets a name of the procedure in the macro for this macro feature.
 PropertyManagerHandleMacroFileName	Gets or sets the path and file name for the macro file from or to the PropertyManager handle for this macro feature.
 PropertyManagerHandleModuleName	Gets or sets the name of the module in the macro file from or to the PropertyManager handle.
 PropertyManagerHandleProcedureName	Gets or sets the name of the procedure in the macro file from or to the PropertyManager handle.
 Provider	Gets or sets the error message to display in the What's Wrong dialog when a non-embedded macro feature fails to rebuild due to missing files.
 SecurityHandleMacroFileName	Gets or sets the name of the procedure in the macro file from or to the security handle.
 SecurityHandleModuleName	Gets and sets the name of the module in the macro file from or to the security handle.
 SecurityHandleProcedureName	Gets or sets the name of the procedure in the macro file from or to the security handle.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Gains access to the selections associated with this macro feature.
 EmbedMacroFile	Sets whether to embed the macro file in the model with the macro feature.
 GetBaseName	Gets the name of the base feature for this macro feature.
 GetDisplayDimensionCount	Gets the number of display dimensions for this macro feature.
 GetDisplayDimensions	Gets the display dimensions for this macro feature.
 GetDoubleByName	Gets a double value by parameter name.
 GetEdgeIdType	Gets the ID type of the specified edge for the macro feature.
 GetEdgeUserid	Gets the user-defined IDs for the specified edge for the macro feature.
 GetEditBodiesCount	Gets the number of bodies to be modified by this macro feature.
 GetEditTargetTransform	Gets the transform of the component where the macro feature resides if at least one selection in the macro feature belongs to a different component.

		
	GetEntitiesNeedUserId	Gets a list of faces and edges that need be assigned user IDs for the macro feature.
	GetEntitiesNeedUserIdCount	Gets the number of faces and edges that need to be assigned user IDs for the macro feature.
	GetFacetType	Gets the ID type from the face for the macro feature.
	GetFaceUserId	Gets the user-defined IDs for the specified face.
	GetIconFileCount	Gets the number of the files for the icons for this macro feature.
	GetIntegerByName	Gets an integer value by parameter name.
	GetModuleCount	Gets the number of modules for the macro feature.
	GetModuleNames	Gets the names of the modules in the macro for the macro feature.
	GetParameterCount	Gets the number of user-defined parameters.
	GetParameters	Gets the user-defined parameters.
	GetParentsCount	Gets the number of parent features for this macro feature.
	GetProcedureCount	Gets the number of procedures in the specified module in the macro for this macro feature.
	GetProcedureNames	Gets the names of the procedures in the specified module for the macro for the macro feature.
	GetProgid	Gets the version-independent program ID that is valid for this COM feature.
	GetPropertyManagerHandleModuleCount	Gets the number of modules in the macro from the PropertyManager handle for the macro feature.
	GetPropertyManagerHandleModuleNames	Gets the names of the modules in the macro from the PropertyManager handle for the macro feature.
	GetPropertyManagerHandleProcedureCount	Gets the number of procedures in the specified module in the macro from the PropertyManager handle for this macro feature.
	GetPropertyManagerHandleProcedureNames	Gets the names of the procedures in the specified module in the macro from the PropertyManager handle for the macro feature.
	GetSelectionCount	Gets the number of selected objects for the macro feature.
	GetSelections	Obsolete. Superseded by IMacroFeatureData::GetSelections3 .
	GetSelections2	Obsolete. Superseded by IMacroFeatureData::GetSelections3 .
	GetSelections3	Gets the selected objects for the macro feature.
	GetStringByName	Gets a string value by the name of the parameter for the macro feature.
	IAccessSelections	Gains access to the selections associated with this macro feature.
	IAddDisplayDimensions	Adds the specified display dimensions to this macro feature.
	IGetDisplayDimensions	Gets the display dimensions for this macro feature.
	IGetEditBodies	Gets the bodies to be modified by this macro feature.
	IGetEntitiesNeedUserId	Gets a list of faces and edges that need be assigned user IDs for the macro feature.
	IGetIconFiles	Gets the file names for the icons for this macro feature.
	IGetModuleNames	Gets the names of the modules in the macro for the macro feature.
	IGetParameters	Gets the user-defined parameters.
	IGetParents	Gets the parent features of this macro feature.
	IGetProcedureNames	Gets the names of the procedures in the specified module in the macro for the macro feature.
	IGetPropertyManagerHandleModuleNames	Gets the names of the modules in the macro from the PropertyManager handle for the macro feature.
	IGetPropertyManagerHandleProcedureNames	Gets the names of the procedures in the specified module in the macro from the PropertyManager handle for the macro feature.
	IGetSelections	Obsolete. Superseded by IMacroFeatureData::IGetSelections3 .
	IGetSelections2	Obsolete. Superseded by IMacroFeatureData::IGetSelections3 .
	IGetSelections3	Gets the selected objects for the macro feature.
	IsCOMFeature	Gets whether the feature is a COM feature.
	ISetEditBodies	Sets the bodies to be modified by this macro feature.
	ISetIconFiles	Sets the file names for the icons for this macro feature.
	ISetParameters	Sets the user-defined parameters.

		
	ISetParents	Sets the parent features for this macro feature.
	ISetSelections	Obsolete. Superseded by IMacroFeatureData::ISetSelections2
	ISetSelections2	Sets the selected objects for the macro feature.
	ReleaseSelectionAccess	Releases access to the selections associated with this macro feature.
	SetDoubleByName	Sets a double value by parameter name for the macro feature.
	SetEdgeUserId	Sets the user-defined IDs for the specified edge for the macro feature.
	SetFaceUserId	Sets user-defined IDs for the face for the macro feature.
	SetIntegerByName	Sets an integer value by parameter name.
	SetParameters	Sets the user-defined parameters.
	SetProgId	Sets the version-independent program ID that is valid for this COM feature.
	SetSelections	Obsolete. Superseded by IMacroFeatureData::SetSelections2
	SetSelections2	Sets the selected objects for the macro feature.
	SetStringByName	Sets a string value by parameter name.

[Top](#)

See Also

[IMacroFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertMacroFeature3 Method](#)
[IFeatureManager::InsertMacroFeature3 Method](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IMacroFeatureData Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IMacroFeatureData Interface

For a list of all members of this type, see [IMacroFeatureData members](#).

Public Properties

Name	Description
 CurrentConfiguration	Gets the macro feature configuration being rebuilt.
 EditBodies	Gets or sets the bodies to be modified by this macro feature.
 EditBody	Obsolete. Superseded by IMacroFeatureData::IGetEditBodies , IMacroFeatureData::ISetEditBodies , and IMacroFeatureData::EditBodies .
 EnableMultiBodyConsume	Gets or sets whether to replace the original edit body with multiple solid bodies created during regeneration of a multibody macro feature.
 FeatureTransform	Gets and sets the macro feature transform.
 IconFiles	Gets or sets the file names for the icons for this macro feature.
 MacroFileEmbedded	Gets whether the macro file is embedded in the model with the macro feature.
 MacroFileName	Gets or sets the path and file name for the macro for the macro feature.
 ModuleName	Gets or sets the name of a module in the macro for this macro feature.
 Parents	Gets or sets the parent features for this macro feature.
 PatternTransform	Gets the pattern transform.
 ProcedureName	Gets or sets a name of the procedure in the macro for this macro feature.
 PropertyManagerHandleMacroFileName	Gets or sets the path and file name for the macro file from or to the PropertyManager handle for this macro feature.
 PropertyManagerHandleModuleName	Gets or sets the name of the module in the macro file from or to the PropertyManager handle.
 PropertyManagerHandleProcedureName	Gets or sets the name of the procedure in the macro file from or to the PropertyManager handle.
 Provider	Gets or sets the error message to display in the What's Wrong dialog when a non-embedded macro feature fails to rebuild due to missing files.
 SecurityHandleMacroFileName	Gets or sets the name of the procedure in the macro file from or to the security handle.

	SecurityHandleModuleName	Gets and sets the name of the module in the macro file from or to the security handle.
	SecurityHandleProcedureName	Gets or sets the name of the procedure in the macro file from or to the security handle.

[Top](#)

See Also

[IMacroFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertMacroFeature3 Method](#)
[IFeatureManager::InsertMacroFeature3 Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

AccessSelections Method (IMacroFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : AccessSelections Method (IMacroFeatureData)

Gains access to the selections associated with this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections(
    ByVal TopDoc As System.Object, _
    ByVal Component As System.Object _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim TopDoc As System.Object
Dim Component As System.Object
Dim value As System.Boolean

value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(
    System.object TopDoc,
    System.object Component
)
```

C++/CLI

```
System.bool AccessSelections(
    & System.Object^ TopDoc,
    & System.Object^ Component
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc
 Top-level document (see **Remarks**)
Component
 Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections were successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::AccessSelections](#).

Example

[Cut Body in Half Using Macro Feature \(VBA\)](#)

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) if you modified the feature
- [IMacroFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::IAccessSelections Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CurrentConfiguration Property (IMacroFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : CurrentConfiguration Property (IMacroFeatureData)

Gets the macro feature configuration being rebuilt.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property CurrentConfiguration As Configuration

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As Configuration
```

```
value = instance.CurrentConfiguration
```

C#

```
Configuration CurrentConfiguration {get;}
```

C++/CLI

```
property Configuration^ CurrentConfiguration {  
    Configuration^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[Configuration](#) being rebuilt

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::CurrentConfiguration](#).

Example

[Cut Body in Half Using Macro Feature \(VBA\)](#)

See Also

Availability

SOLIDWORKS 2006 SP2, Revision Number 14.2

SOLIDWORKS API Help

[Send comments on this topic.](#)

EditBodies Property (IMacroFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : EditBodies Property (IMacroFeatureData)

Gets or sets the bodies to be modified by this macro feature.

.NET Syntax

Visual Basic (Declaration)

Property EditBodies As System.Object

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.Object
```

```
instance.EditBodies = value
```

```
value = instance.EditBodies
```

C#

```
System.object EditBodies {get; set;}
```

C++/CLI

```
property System.Object^ EditBodies {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of [bodies](#)

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::EditBodies](#).

Example

[Cut Body in Half Using Macro Feature \(VBA\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this property.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetEditBodiesCount Method](#)
[IMacroFeatureData::!GetEditBodies Method](#)
[IMacroFeatureData::!SetEditBodies Method](#)
[IMacroFeatureData::EnableMultiBodyConsume Method \(\)](#)

Availability

EditBody Property (IMacroFeatureData)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : EditBody Property (IMacroFeatureData)

Obsolete. Superseded by [IMacroFeatureData::IGetEditBodies](#), [IMacroFeatureData::ISetEditBodies](#), and [IMacroFeatureData::EditBodies](#).

.NET Syntax

Visual Basic (Declaration)

Property EditBody As Body2

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim value As Body2
```

```
instance.EditBody = value
```

```
value = instance.EditBody
```

C#

```
Body2 EditBody {get; set;}
```

C++/CLI

```
property Body2^ EditBody {
    Body2^ get();
    void set ( & Body2^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::EditBody](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)

EmbedMacroFile Method (IMacroFeatureData)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : EmbedMacroFile Method (IMacroFeatureData)

Sets whether to embed the macro file in the model with the macro feature.

.NET Syntax

Visual Basic (Declaration)

Function EmbedMacroFile() As System.Boolean

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim value As System.Boolean
```

```
value = instance.EmbedMacroFile()
```

C#

```
System.bool EmbedMacroFile()
```

C++/CLI

```
System.bool EmbedMacroFile();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True to embed the macro file in the model with the macro feature, false to not

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::EmbedMacroFile](#).

Remarks

Call [IMacroFeatureData::MacroFileEmbedded](#) to determine if the macro file is embedded with the macro feature.

If this property is set to false, you should specify a detailed error message to display in the What's Wrong dialog when SOLIDWORKS fails to find files during macro feature load or rebuild. Specify this error message using [IMacroFeatureData.Provider](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

EnableMultiBodyConsume Property (IMacroFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : EnableMultiBodyConsume Property (IMacroFeatureData)

Gets or sets whether to replace the original edit body with multiple solid bodies created during regeneration of a multibody macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Property EnableMultiBodyConsume As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.Boolean
```

```
instance.EnableMultiBodyConsume = value
```

```
value = instance.EnableMultiBodyConsume
```

C#

```
System.bool EnableMultiBodyConsume {get; set;}
```

C++/CLI

```
property System.bool EnableMultiBodyConsume {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to replace the original edit body with multiple solid bodies, false to not

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::EnableMultiBodyConsume](#).

Example

[Create Multibody Macro Feature \(VBA\)](#)
[Create Multibody Macro Feature \(VB.NET\)](#)
[Create Multibody Macro Feature \(C#\)](#)

Remarks

This method was designed to work specifically with macro features that generate multiple solid bodies. The [rebuild](#) function of a macro feature creates or regenerates the macro feature in the FeatureManager design tree. By default, if the rebuild function creates multiple solid bodies, it appends the new solid bodies to the original edit body in the Solid Bodies folder of the FeatureManager design tree.

Always set this property to true in the rebuild function when working with macro features involving multiple input or output bodies.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetEditBodiesCount Method \(\)](#)
[IMacroFeatureData::IGetEditBodies Method \(\)](#)
[IMacroFeatureData::EditBodies Property \(\)](#)

Availability

SOLIDWORKS 2013 SP05, Revision Number 21.5

SOLIDWORKS API Help

[Send comments on this topic.](#)

FeatureTransform Property (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : FeatureTransform Property (IMacroFeatureData)

Gets and sets the macro feature transform.

.NET Syntax

Visual Basic (Declaration)

Property FeatureTransform As MathTransform

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As MathTransform
```

```
instance.FeatureTransform = value
```

```
value = instance.FeatureTransform
```

C#

```
MathTransform FeatureTransform {get; set;}
```

C++/CLI

```
property MathTransform^ FeatureTransform {  
    MathTransform^ get();  
    void set ( & MathTransform^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[Math transform](#)

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::FeatureTransform](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this property.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetEditTargetTransform Method](#)
[IMacroFeatureData::PatternTransform Property](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetBaseName Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetBaseName Method (IMacroFeatureData)

Gets the name of the base feature for this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetBaseName() As System.String
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.String
```

```
value = instance.GetBaseName()
```

C#

```
System.string GetBaseName()
```

C++/CLI

```
System.String^ GetBaseName();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Name of the base feature

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetBaseName](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetDisplayDimensionCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetDisplayDimensionCount Method (IMacroFeatureData)

Gets the number of display dimensions for this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDisplayDimensionCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.Integer  
  
value = instance.GetDisplayDimensionCount()
```

C#

```
System.int GetDisplayDimensionCount()
```

C++/CLI

```
System.int GetDisplayDimensionCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of display dimensions

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetDisplayDimensionCount](#).

Remarks

Call this method before calling [IMacroFeatureData::GetDisplayDimensions](#) to determine the size of the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetDisplayDimensions Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

[SOLIDWORKS API Help](#)

[Send comments on this topic.](#)

GetDisplayDimensions Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetDisplayDimensions Method (IMacroFeatureData)

Gets the display dimensions for this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDisplayDimensions() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim value As System.Object

value = instance.GetDisplayDimensions()
```

C#

```
System.object GetDisplayDimensions()
```

C++/CLI

```
System.Object^ GetDisplayDimensions();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [display dimensions](#)

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetDisplayDimensions](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::IGetDisplayDimensions Method](#)
[IMacroFeatureData::GetDisplayDimensions Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetDoubleByName Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetDoubleByName Method (IMacroFeatureData)

Gets a double value by parameter name.

.NET Syntax

Visual Basic (Declaration)

```
Sub GetDoubleByName( _
    ByVal ParamName As System.String, _
    ByRef ParamValue As System.Double _
)
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim ParamName As System.String
Dim ParamValue As System.Double
```

```
instance.GetDoubleByName(ParamName, ParamValue)
```

C#

```
void GetDoubleByName(
    System.string ParamName,
```

```
    out System.double ParamValue
)
```

C++/CLI

```
void GetDoubleByName(
& System.String^ ParamName,
& [Out] System.double ParamValue
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ParamName
Name of the parameter
ParamValue
Double value

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetDoubleByName](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::SetDoubleByName Method](#)
[IMacroFeatureData::GetIntegerByName Method](#)
[IMacroFeatureData::GetParameterCount Method](#)
[IMacroFeatureData::GetParameters Method](#)
[IMacroFeatureData::IGetParameters Method](#)
[IMacroFeatureData::ISetParameters Method](#)
[IMacroFeatureData::SetIntegerByName Method](#)
[IMacroFeatureData::SetParameters Method](#)
[IMacroFeatureData::GetStringByName Method](#)
[IMacroFeatureData::SetStringByName Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEdgeIdType Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetEdgeIdType Method (IMacroFeatureData)

Gets the ID type of the specified edge for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEdgeIdType( _
    ByVal Edge As Edge _
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim Edge As Edge
Dim value As System.Integer

value = instance.GetEdgeIdType(Edge)
```

C#

```
System.int GetEdgeIdType(
    Edge Edge
)
```

C++/CLI

```
System.int GetEdgeIdType(  
& Edge^ Edge  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Edge
[Edge](#) in the feature

Return Value

ID type as defined in [swMacroFeatureEntityIdType_e](#)

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetEdgeIdType](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetEdgeUserId Method](#)
[IMacroFeatureData::GetEntitiesNeedUserId Method](#)
[IMacroFeatureData::GetEntitiesNeedUserIdCount Method](#)
[IMacroFeatureData::GetFaceIdType Method](#)
[IMacroFeatureData::GetFaceUserId Method](#)
[IMacroFeatureData::SetEdgeUserId Method](#)
[IMacroFeatureData::SetFaceUserId Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetEdgeUserId Method (IMacroFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetEdgeUserId Method (IMacroFeatureData)

Gets the user-defined IDs for the specified edge for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEdgeUserId( _  
    ByVal Edge As Edge, _  
    ByRef Id1 As System.Integer, _  
    ByRef Id2 As System.Integer _  
) As System.Boolean
```

Visual Basic (Usage)

```
Dim instance As IMacroFeatureData  
Dim Edge As Edge  
Dim Id1 As System.Integer  
Dim Id2 As System.Integer  
Dim value As System.Boolean  
  
value = instance.GetEdgeUserId(Edge, Id1, Id2)
```

C#



```
System.bool GetEdgeUserId(  
    Edge Edge,  
    out System.int Id1,  
    out System.int Id2  
)
```

C++/CLI

```
System.bool GetEdgeUserId(  
    & Edge^ Edge,  
    & [Out] System.int Id1,  
    & [Out] System.int Id2  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Edge
[Edge](#)
Id1
First ID
Id2
Second ID

Return Value

True if the IDs are valid, false if not

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetEdgeUserId](#).

Example

[Cut Body in Half Using Macro Feature \(VBA\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetEdgeIdType Method](#)
[IMacroFeatureData::GetEntitiesNeedUserId Method](#)
[IMacroFeatureData::GetEntitiesNeedUserIdCount Method](#)
[IMacroFeatureData::GetFacetIdType Method](#)
[IMacroFeatureData::GetFaceUserId Method](#)
[IMacroFeatureData::SetEdgeUserId Method](#)
[IMacroFeatureData::SetFaceUserId Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEditBodiesCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetEditBodiesCount Method (IMacroFeatureData)

Gets the number of bodies to be modified by this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEditBodiesCount() As System.Integer
```

```
Dim instance As IMacroFeatureData
Dim value As System.Integer

value = instance.GetEditBodiesCount()
```

C#

```
System.int GetEditBodiesCount()
```

C++/CLI

```
System.int GetEditBodiesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of bodies to be modified by this macro feature

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetEditBodiesCount](#).

Remarks

Call this method before calling [IMacroFeatureData::!GetEditBodies](#) to size the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::!SetEditBodies Method](#)
[IMacroFeatureData::!EditBodies Property](#)
[IMacroFeatureData::EnableMultiBodyConsume Method \(\)](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEditTargetTransform Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetEditTargetTransform Method (IMacroFeatureData)

Gets the transform of the component where the macro feature resides if at least one selection in the macro feature belongs to a different component.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEditTargetTransform() As MathTransform
```

Visual Basic (Usage)

```
Dim instance As IMacroFeatureData
Dim value As MathTransform

value = instance.GetEditTargetTransform()
```

C#

```
MathTransform GetEditTargetTransform()
```

C++/CLI

```
MathTransform^ GetEditTargetTransform();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Math transform](#) of the component where the macro feature resides if at least one selection in the macro feature belongs to a different component, or NULL if all of the selections in the macro feature belong to the component where the macro feature resides

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetEditTargetTransform](#).

Remarks

When [regenerating a macro feature](#) in a part that is a component in an assembly, you cannot get the component's transform where the macro feature resides because you cannot get the component using [IEntity::GetComponent](#) or [IEntity::IGetComponent2](#) in a part document. However, you may need the component's transform because references from other components to it often need to be transformed.

This method provides this transform. If there are no external references among the macro feature selections ([IMacroFeatureData::GetSelections3](#) or [IMacroFeatureData::IGetSelections3](#)), then this method returns NULL. If there are external references among the macro feature selections, then this method returns the transform of the component where the macro feature resides.

For example, if the macro feature includes a selection box in which the user can select a face, and the user selects a face on a different component, then this method can get the component's transform where the macro feature resides. However, if all of the selections in the macro feature belong to the component where the macro feature resides, then this method returns NULL because you probably will not need the transform. See also [Macro Features and Component Transforms](#).

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::FeatureTransform Property](#)
[IMacroFeatureData::PatternTransform Property](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEntitiesNeedUserId Method (IMacroFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetEntitiesNeedUserId Method (IMacroFeatureData)

Gets a list of faces and edges that need be assigned user IDs for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub GetEntitiesNeedUserId( _  
    ByVal Body As System.Object, _  
    ByRef Faces As System.Object, _  
    ByRef Edges As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim Body As System.Object  
Dim Faces As System.Object  
Dim Edges As System.Object  
  
instance.GetEntitiesNeedUserId(Body, Faces, Edges)
```

C#

```
void GetEntitiesNeedUserId(  
    System.object Body,  
    out System.object Faces,
```

```
    out System.Object Edges
)
```

C++/CLI

```
void GetEntitiesNeedUserId(
&    System.Object^ Body,
&    [Out] System.Object^ Faces,
&    [Out] System.Object^ Edges
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Body
[Body](#) containing the faces and edges
Faces

Array of [faces](#)

Edges
Array of [edges](#)

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetEntitiesNeedUserId](#).

Example

[Cut Body in Half Using Macro Feature \(VBA\)](#)

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetEdgeIdType Method](#)
[IMacroFeatureData::GetEdgeUserId Method](#)
[IMacroFeatureData::GetEntitiesNeedUserIdCount Method](#)
[IMacroFeatureData::GetFaceIdType Method](#)
[IMacroFeatureData::GetFaceUserId Method](#)
[IMacroFeatureData::SetEdgeUserId Method](#)
[IMacroFeatureData::SetFaceUserId Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEntitiesNeedUserIdCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetEntitiesNeedUserIdCount Method (IMacroFeatureData)

Gets the number of faces and edges that need to be assigned user IDs for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub GetEntitiesNeedUserIdCount( _
    ByVal Body As Body2, _
    ByRef FaceCount As System.Integer, _
    ByRef EdgeCount As System.Integer _
)
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim Body As Body2
Dim FaceCount As System.Integer
Dim EdgeCount As System.Integer

instance.GetEntitiesNeedUserIdCount(Body, FaceCount, EdgeCount)
```

C#

```
void GetEntitiesNeedUserIdCount(
    Body2 Body,
    out System.int FaceCount,
    out System.int EdgeCount
)
```

C++/CLI

```
void GetEntitiesNeedUserIdCount(
    & Body2^ Body,
    & [Out] System.int FaceCount,
    & [Out] System.int EdgeCount
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Body
[Body](#)
FaceCount
Number of faces
EdgeCount
Number of edges

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetEntitiesNeedUserIdCount](#).

Remarks

Call this method before calling [IMacroFeatureData::!GetEntitiesNeedUserId](#) to determine the size of the array for that method.
See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetEntitiesNeedUserId Method](#)
[IMacroFeatureData::GetFacelDType Method](#)
[IMacroFeatureData::GetFaceUserId Method](#)
[IMacroFeatureData::SetEdgeUserId Method](#)
[IMacroFeatureData::SetFaceUserId Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetFacelDType Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetFacelDType Method (IMacroFeatureData)

Gets the ID type from the face for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFaceIdType( _  
    ByVal Face As Face2 _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim Face As Face2  
Dim value As System.Integer  
  
value = instance.GetFaceIdType(Face)
```

C#

```
System.int GetFaceIdType(  
    Face2 Face  
)
```

C++/CLI

```
System.int GetFaceIdType(  
& Face2^ Face  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Face
[Face](#)

Return Value

ID type as defined in [swMacroFeatureEntityIdType_e](#)

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetFaceIdType](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetEdgeIdType Method](#)
[IMacroFeatureData::GetEdgeUserId Method](#)
[IMacroFeatureData::GetEntitiesNeedUserId Method](#)
[IMacroFeatureData::GetEntitiesNeedUserIdCount Method](#)
[IMacroFeatureData::GetFaceUserId Method](#)
[IMacroFeatureData::SetEdgeUserId Method](#)
[IMacroFeatureData::SetFaceUserId Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetFaceUserId Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetFaceUserId Method (IMacroFeatureData)

Gets the user-defined IDs for the specified face.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFaceUserId( _
    ByVal Face As Face2, _
    ByRef Id1 As System.Integer, _
    ByRef Id2 As System.Integer _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim Face As Face2
Dim Id1 As System.Integer
Dim Id2 As System.Integer
Dim value As System.Boolean

value = instance.GetFaceUserId(Face, Id1, Id2)
```

C#

```
System.bool GetFaceUserId(
    Face2 Face,
    out System.int Id1,
    out System.int Id2
)
```

C++/CLI

```
System.bool GetFaceUserId(
    & Face2^ Face,
    & [Out] System.int Id1,
    & [Out] System.int Id2
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Face

[Face](#)

Id1

First ID

Id2

Second ID

Return Value

True if the IDs are valid, false if not

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetFaceUserId](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)

[IMacroFeatureData Members](#)

[IMacroFeatureData::GetEdgeIdType Method](#)

[IMacroFeatureData::GetEdgeUserId Method](#)

[IMacroFeatureData::GetEntitiesNeedUserIdCount Method](#)

[IMacroFeatureData::GetEntitiesNeedUserIdCount Method](#)

[IMacroFeatureData::GetFaceIdType Method](#)

[IMacroFeatureData::SetEdgeUserId Method](#)

[IMacroFeatureData::SetFaceUserId Method](#)

Availability

GetIconFileCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetIconFileCount Method (IMacroFeatureData)

Gets the number of the files for the icons for this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetIconFileCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.Integer  
  
value = instance.GetIconFileCount()
```

C#

```
System.int GetIconFileCount()
```

C++/CLI

```
System.int GetIconFileCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of files for the icons

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetIconFileCount](#).

Remarks

Call this method before calling [IMacroFeatureData::IGetIconFiles](#) to determine the size of the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::IGetIconFiles Method](#)
[IMacroFeatureData::ISetIconFiles Method](#)
[IMacroFeatureData::IconFiles Property](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

GetIntegerByName Method (IMacroFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetIntegerByName Method (IMacroFeatureData)

Gets an integer value by parameter name.

.NET Syntax

Visual Basic (Declaration)

```
Sub GetIntegerByName(  
    ByVal ParamName As System.String, _
```

```
ByRef ParamValue As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim ParamName As System.String  
Dim ParamValue As System.Integer  
  
instance.GetIntegerByName(ParamName, ParamValue)
```

C#

```
void GetIntegerByName(  
    System.string ParamName,  
    out System.int ParamValue  
)
```

C++/CLI

```
void GetIntegerByName(  
& System.String^ ParamName,  
& [Out] System.int ParamValue  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ParamName
Name of the parameter
ParamValue
Integer value

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetIntegerByName](#).

Example

[Cut Body in Half Using Macro Feature \(VBA\)](#)

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetDoubleByName Method](#)
[IMacroFeatureData::GetParameterCount Method](#)
[IMacroFeatureData::GetParameters Method](#)
[IMacroFeatureData::IGetParameters Method](#)
[IMacroFeatureData::ISetParameters Method](#)
[IMacroFeatureData::SetDoubleByName Method](#)
[IMacroFeatureData::SetIntegerByName Method](#)
[IMacroFeatureData::SetParameters Method](#)
[IMacroFeatureData::GetStringByName Method](#)
[IMacroFeatureData::SetStringByName Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetModuleCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetModuleCount Method (IMacroFeatureData)

Gets the number of modules for the macro feature.

.NET Syntax

Visual Basic (Declaration)

Function GetModuleCount() As System.Integer

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.Integer
```

```
value = instance.GetModuleCount()
```

C#

```
System.int GetModuleCount()
```

C++/CLI

```
System.int GetModuleCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of modules

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetModuleCount](#).

Remarks

Call this method before calling [IMacroFeatureData::IGetModuleNames](#) to determine the size of the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetModuleNames Method](#)
[IMacroFeatureData::GetProcedureCount Method](#)
[IMacroFeatureData::GetProcedureNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::IGetProcedureNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::ModuleName Property](#)
[IMacroFeatureData::PropertyManagerHandleMacroFileName Property](#)
[IMacroFeatureData::PropertyManagerHandleModuleName Property](#)
[IMacroFeatureData::PropertyManagerHandleProcedureName Property](#)
[IMacroFeatureData::SecurityHandleMacroFileName Property](#)
[IMacroFeatureData::SecurityHandleModuleName Property](#)
[IMacroFeatureData::SecurityHandleProcedureName Property](#)
[IMacroFeatureData::MacroFileName Property](#)
[IMacroFeatureData::ProcedureName Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetModuleNames Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetModuleNames Method (IMacroFeatureData)

Gets the names of the modules in the macro for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetModuleNames() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim value As System.Object

value = instance.GetModuleNames()
```

C#

```
System.Object GetModuleNames()
```

C++/CLI

```
System.Object^ GetModuleNames();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of strings of the module names

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetModuleNames](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetModuleCount Method](#)
[IMacroFeatureData::GetProcedureCount Method](#)
[IMacroFeatureData::GetProcedureNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::!GetModuleNames Method](#)
[IMacroFeatureData::!GetProcedureNames Method](#)
[IMacroFeatureData::!GetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::!GetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::ModuleName Property](#)
[IMacroFeatureData::ProcedureName Property](#)
[IMacroFeatureData::PropertyManagerHandleMacroFileName Property](#)
[IMacroFeatureData::PropertyManagerHandleMacroFileName Property](#)
[IMacroFeatureData::PropertyManagerHandleModuleName Property](#)
[IMacroFeatureData::PropertyManagerHandleProcedureName Property](#)
[IMacroFeatureData::SecurityHandleMacroFileName Property](#)
[IMacroFeatureData::SecurityHandleModuleName Property](#)
[IMacroFeatureData::SecurityHandleProcedureName Property](#)
[IMacroFeatureData::MacroFileName Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetParameterCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetParameterCount Method (IMacroFeatureData)

Gets the number of user-defined parameters.

.NET Syntax

Visual Basic (Declaration)

```
Function GetParameterCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim value As System.Integer

value = instance.GetParameterCount()
```

C#

```
System.int GetParameterCount()
```

C++/CLI

```
System.int GetParameterCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of user-defined parameters

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetParameterCount](#).

Remarks

Call this method before calling [IMacroFeatureData::IGetParameters](#) to determine the size of the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetDoubleByName Method](#)
[IMacroFeatureData::GetIntegerByName Method](#)
[IMacroFeatureData::GetParameters Method](#)
[IMacroFeatureData::!SetParameters Method](#)
[IMacroFeatureData::SetDoubleByName Method](#)
[IMacroFeatureData::SetIntegerByName Method](#)
[IMacroFeatureData::SetParameters Method](#)
[IMacroFeatureData::GetStringByName Method](#)
[IMacroFeatureData::SetStringByName Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetParameters Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetParameters Method (IMacroFeatureData)

Gets the user-defined parameters.

.NET Syntax

Visual Basic (Declaration)

```
Sub GetParameters( _  
    ByRef ParamNames As System.Object, _  
    ByRef ParamTypes As System.Object, _  
    ByRef ParamValues As System.Object _  
)
```

Visual Basic (Usage)

```
Dim instance As IMacroFeatureData  
Dim ParamNames As System.Object  
Dim ParamTypes As System.Object  
Dim ParamValues As System.Object  
  
instance.GetParameters(ParamNames, ParamTypes, ParamValues)
```

C#

```
void GetParameters(  
    out System.object ParamNames,  
    out System.object ParamTypes,
```



```
    out System.Object ParamValues
)
```

C++/CLI

```
void GetParameters(
& [Out] System.Object^ ParamNames,
& [Out] System.Object^ ParamTypes,
& [Out] System.Object^ ParamValues
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ParamNames

Array of parameter names

ParamTypes

Array of parameter data types as defined in [swMacroFeatureParamType_e](#)

ParamValues

Array of the parameter values

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetParameters](#).

See Also

[IMacroFeatureData Interface](#)

[IMacroFeatureData Members](#)

[IMacroFeatureData::GetDoubleByName Method](#)

[IMacroFeatureData::GetIntegerByName Method](#)

[IMacroFeatureData::GetParameterCount Method](#)

[IMacroFeatureData::GetStringByName Method](#)

[IMacroFeatureData::IGetParameters Method](#)

[IMacroFeatureData::ISetParameters Method](#)

[IMacroFeatureData::SetDoubleByName Method](#)

[IMacroFeatureData::SetIntegerByName Method](#)

[IMacroFeatureData::SetStringByName Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetParentsCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetParentsCount Method (IMacroFeatureData)

Gets the number of parent features for this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetParentsCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
```

```
Dim value As System.Integer
```

```
value = instance.GetParentsCount()
```

C#

```
System.int GetParentsCount()
```

C++/CLI

```
System.int GetParentsCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of parent features for this macro feature

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetParentsCount](#).

Remarks

Call this method before using [IMacroFeatureData::IGetParents](#) to determine the size of the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::IGetParents Method](#)
[IMacroFeatureData::ISetParents Method](#)
[IMacroFeatureData::Parents Property](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetProcedureCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetProcedureCount Method (IMacroFeatureData)

Gets the number of procedures in the specified module in the macro for this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetProcedureCount( _  
    ByVal ModuleName As System.String _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim ModuleName As System.String  
Dim value As System.Integer  
  
value = instance.GetProcedureCount(ModuleName)
```

C#

```
System.int GetProcedureCount(  
    System.string ModuleName  
)
```

C++/CLI

```
System.int GetProcedureCount(  
& System.String^ ModuleName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ModuleName
Name of module

Return Value

Number of procedures in module ModuleName

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetProcedureCount](#).

Remarks

Call this method before calling [IMacroFeatureData::iGetProcedureNames](#) to determine the size of the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetModuleCount Method](#)
[IMacroFeatureData::GetModuleNames Method](#)
[IMacroFeatureData::GetProcedureNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::iGetModuleNames Method](#)
[IMacroFeatureData::iGetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::iGetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::ModuleName Property](#)
[IMacroFeatureData::ProcedureName Property](#)
[IMacroFeatureData::PropertyManagerHandleMacroFileName Property](#)
[IMacroFeatureData::PropertyManagerHandleModuleName Property](#)
[IMacroFeatureData::PropertyManagerHandleProcedureName Property](#)
[IMacroFeatureData::SecurityHandleMacroFileName Property](#)
[IMacroFeatureData::SecurityHandleModuleName Property](#)
[IMacroFeatureData::SecurityHandleProcedureName Property](#)
[IMacroFeatureData::MacroFileName Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetProcedureNames Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetProcedureNames Method (IMacroFeatureData)

Gets the names of the procedures in the specified module for the macro for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetProcedureNames( _  
    ByVal ModuleName As System.String _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim ModuleName As System.String  
Dim value As System.Object  
  
value = instance.GetProcedureNames(ModuleName)
```

C#

```
System.object GetProcedureNames(  
    System.string ModuleName  
)
```

C++/CLI

```
System.Object^ GetProcedureNames(  
& System.String^ ModuleName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ModuleName
Name of module

Return Value

Array of procedure names in module ModuleName

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetProcedureNames](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetModuleCount Method](#)
[IMacroFeatureData::GetModuleNames Method](#)
[IMacroFeatureData::GetProcedureCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::IGetModuleNames Method](#)
[IMacroFeatureData::IGetProcedureNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::ModuleName Property](#)
[IMacroFeatureData::ProcedureName Property](#)
[IMacroFeatureData::PropertyManagerHandleMacroFileName Property](#)
[IMacroFeatureData::PropertyManagerHandleModuleName Property](#)
[IMacroFeatureData::PropertyManagerHandleProcedureName Property](#)
[IMacroFeatureData::SecurityHandleMacroFileName Property](#)
[IMacroFeatureData::SecurityHandleModuleName Property](#)
[IMacroFeatureData::SecurityHandleProcedureName Property](#)
[IMacroFeatureData::MacroFileName Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetProgId Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetProgId Method (IMacroFeatureData)

Gets the version-independent program ID that is valid for this COM feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetProgId() As System.String
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.String  
  
value = instance.GetProgId()
```

C#

```
System.string GetProgId()
```

C++/CLI

```
System.String^ GetProgId();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Name of the program ID for the component that implements the COM feature handler

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetProgid](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::IsCOMFeature Method](#)
[IMacroFeatureData::SetProgid Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetPropertyManagerHandleModuleCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetPropertyManagerHandleModuleCount Method (IMacroFeatureData)

Gets the number of modules in the macro from the PropertyManager handle for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPropertyManagerHandleModuleCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.Integer
```

```
value = instance.GetPropertyManagerHandleModuleCount()
```

C#

```
System.int GetPropertyManagerHandleModuleCount()
```

C++/CLI

```
System.int GetPropertyManagerHandleModuleCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of modules

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetPropertyManagerHandleModuleCount](#).

Remarks

Call this method before calling [IMacroFeatureData::GetPropertyManagerHandleModuleNames](#) to determine the size of the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetModuleCount Method](#)
[IMacroFeatureData::GetModuleNames Method](#)
[IMacroFeatureData::GetProcedureCount Method](#)
[IMacroFeatureData::GetProcedureNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::IGetModuleNames Method](#)
[IMacroFeatureData::IGetProcedureNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::ModuleName Property](#)
[IMacroFeatureData::ProcedureName Property](#)
[IMacroFeatureData::PropertyManagerHandleMacroFileName Property](#)
[IMacroFeatureData::PropertyManagerHandleModuleName Property](#)

[IMacroFeatureData::PropertyManagerHandleProcedureName Property](#)
[IMacroFeatureData::SecurityHandleMacroFileName Property](#)
[IMacroFeatureData::SecurityHandleModuleName Property](#)
[IMacroFeatureData::SecurityHandleProcedureName Property](#)
[IMacroFeatureData::MacroFileName Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetPropertyManagerHandleModuleNames Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetPropertyManagerHandleModuleNames Method (IMacroFeatureData)

Gets the names of the modules in the macro from the PropertyManager handle for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPropertyManagerHandleModuleNames() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.Object  
  
value = instance.GetPropertyManagerHandleModuleNames()
```

C#

```
System.object GetPropertyManagerHandleModuleNames()
```

C++/CLI

```
System.Object^ GetPropertyManagerHandleModuleNames();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of module names

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetPropertyManagerHandleModuleNames](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetModuleCount Method](#)
[IMacroFeatureData::GetModuleNames Method](#)
[IMacroFeatureData::GetProcedureCount Method](#)
[IMacroFeatureData::GetProcedureNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::IGetModuleNames Method](#)
[IMacroFeatureData::IGetProcedureNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::ProcedureName Property](#)
[IMacroFeatureData::ModuleName Property](#)
[IMacroFeatureData::PropertyManagerHandleMacroFileName Property](#)
[IMacroFeatureData::PropertyManagerHandleModuleName Property](#)
[IMacroFeatureData::PropertyManagerHandleProcedureName Property](#)
[IMacroFeatureData::SecurityHandleMacroFileName Property](#)
[IMacroFeatureData::SecurityHandleModuleName Property](#)
[IMacroFeatureData::SecurityHandleProcedureName Property](#)
[IMacroFeatureData::MacroFileName Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

GetPropertyManagerHandleProcedureCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetPropertyManagerHandleProcedureCount Method (IMacroFeatureData)

Gets the number of procedures in the specified module in the macro from the PropertyManager handle for this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPropertyManagerHandleProcedureCount( _
    ByVal ModuleName As System.String _
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData
Dim ModuleName As System.String
Dim value As System.Integer

value = instance.GetPropertyManagerHandleProcedureCount(ModuleName)
```

C#

```
System.int GetPropertyManagerHandleProcedureCount(
    System.string ModuleName
)
```

C++/CLI

```
System.int GetPropertyManagerHandleProcedureCount(
    & System.String^ ModuleName
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ModuleName

Name of module

Return Value

Number of procedures in module ModuleName

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetPropertyManagerHandleProcedureCount](#).

Remarks

Call this method before calling [IMacroFeatureData::IGetProcedureNames](#) to determine the size of the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetModuleCount Method](#)
[IMacroFeatureData::GetModuleNames Method](#)
[IMacroFeatureData::GetProcedureCount Method](#)
[IMacroFeatureData::GetProcedureNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::IGetModuleNames Method](#)
[IMacroFeatureData::IGetProcedureNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::ModuleName Property](#)
[IMacroFeatureData::ProcedureName Property](#)
[IMacroFeatureData::PropertyManagerHandleMacroFileName Property](#)
[IMacroFeatureData::PropertyManagerHandleModuleName Property](#)
[IMacroFeatureData::PropertyManagerHandleProcedureName Property](#)
[IMacroFeatureData::SecurityHandleMacroFileName Property](#)
[IMacroFeatureData::SecurityHandleModuleName Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetPropertyManagerHandleProcedureNames Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetPropertyManagerHandleProcedureNames Method (IMacroFeatureData)

Gets the names of the procedures in the specified module in the macro from the PropertyManager handle for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPropertyManagerHandleProcedureNames( _  
    ByVal ModuleName As System.String _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim ModuleName As System.String  
Dim value As System.Object  
  
value = instance.GetPropertyManagerHandleProcedureNames(ModuleName)
```

C#

```
System.object GetPropertyManagerHandleProcedureNames(  
    System.string ModuleName  
)
```

C++/CLI

```
System.Object^ GetPropertyManagerHandleProcedureNames(  
& System.String^ ModuleName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ModuleName

Name of the module

Return Value

Array of procedure names

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetPropertyManagerHandleProcedureNames](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetModuleCount Method](#)
[IMacroFeatureData::GetModuleNames Method](#)
[IMacroFeatureData::GetProcedureCount Method](#)
[IMacroFeatureData::GetProcedureNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleCount Method](#)
[IMacroFeatureData::GetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::GetPropertyManagerHandleProcedureCount Method](#)
[IMacroFeatureData::IGetModuleNames Method](#)
[IMacroFeatureData::IGetProcedureNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleModuleNames Method](#)
[IMacroFeatureData::IGetPropertyManagerHandleProcedureNames Method](#)
[IMacroFeatureData::ModuleName Property](#)
[IMacroFeatureData::ProcedureName Property](#)
[IMacroFeatureData::PropertyManagerHandleMacroFileName Property](#)

[IMacroFeatureData::PropertyManagerHandleModuleName Property](#)
[IMacroFeatureData::PropertyManagerHandleProcedureName Property](#)
[IMacroFeatureData::SecurityHandleMacroFileName Property](#)
[IMacroFeatureData::SecurityHandleModuleName Property](#)
[IMacroFeatureData::SecurityHandleProcedureName Property](#)
[IMacroFeatureData::MacroFileName Property](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelectionCount Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetSelectionCount Method (IMacroFeatureData)

Gets the number of selected objects for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSelectionCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.Integer  
  
value = instance.GetSelectionCount()
```

C#

```
System.int GetSelectionCount()
```

C++/CLI

```
System.int GetSelectionCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of selected objects

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetSelectionCount](#).

Remarks

Call this method before calling [IMacroFeatureData::IGetSelections3](#) to determine the size of the array for that method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::IGetSelections2 Method](#)
[IMacroFeatureData::SetSelections2 Method](#)
[IMacroFeatureData::GetSelections3 Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSelections Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetSelections Method (IMacroFeatureData)

Obsolete. Superseded by [IMacroFeatureData::GetSelections3](#).

 .NET Syntax

Visual Basic (Declaration)

```
Sub GetSelections( _  
    ByRef Objects As System.Object, _  
    ByRef ObjectTypes As System.Object, _  
    ByRef SelMarks As System.Object _  
)
```

Visual Basic (Usage) 

```
Dim instance As IMacroFeatureData  
Dim Objects As System.Object  
Dim ObjectTypes As System.Object  
Dim SelMarks As System.Object  
  
instance.GetSelections(Objects, ObjectTypes, SelMarks)
```

C#

```
void GetSelections(  
    out System.object Objects,  
    out System.object ObjectTypes,  
    out System.object SelMarks  
)
```

C++/CLI

```
void GetSelections(  
& [Out] System.Object^ Objects,  
& [Out] System.Object^ ObjectTypes,  
& [Out] System.Object^ SelMarks  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

- Objects*
- ObjectTypes*
- SelMarks*

 Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetSelections](#).

 See Also

- [IMacroFeatureData Interface](#)
- [IMacroFeatureData Members](#)

GetSelections2 Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetSelections2 Method (IMacroFeatureData)

Obsolete. Superseded by [IMacroFeatureData::GetSelections3](#).

 .NET Syntax

Visual Basic (Declaration)

```
Sub GetSelections2( _  
    ByRef Objects As System.Object, _
```

```

ByRef ObjectTypes As System.Object, _
ByRef SelMarks As System.Object, _
ByRef DrViews As System.Object _
)

```

Visual Basic (Usage)



```

Dim instance As IMacroFeatureData
Dim Objects As System.Object
Dim ObjectTypes As System.Object
Dim SelMarks As System.Object
Dim DrViews As System.Object

instance.GetSelections2(Objects, ObjectTypes, SelMarks, DrViews)

```

C#

```

void GetSelections2(
    out System.object Objects,
    out System.object ObjectTypes,
    out System.object SelMarks,
    out System.object DrViews
)

```

C++/CLI

```

void GetSelections2(
    & [Out] System.Object^ Objects,
    & [Out] System.Object^ ObjectTypes,
    & [Out] System.Object^ SelMarks,
    & [Out] System.Object^ DrViews
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Objects

ObjectTypes

SelMarks

DrViews

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetSelections2](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetSelections3 Method (IMacroFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetSelections3 Method (IMacroFeatureData)

Gets the selected objects for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```

Sub GetSelections3( _
    ByRef Objects As System.Object, _
    ByRef ObjectTypes As System.Object, _
    ByRef SelMarks As System.Object, _
    ByRef DrViews As System.Object, _
)

```

```
ByRef ComponentXForms As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim Objects As System.Object  
Dim ObjectTypes As System.Object  
Dim SelMarks As System.Object  
Dim DrViews As System.Object  
Dim ComponentXForms As System.Object
```

```
instance.GetSelections3(Objects, ObjectTypes, SelMarks, DrViews, ComponentXForms)
```

C#

```
void GetSelections3(  
    out System.object Objects,  
    out System.object ObjectTypes,  
    out System.object SelMarks,  
    out System.object DrViews,  
    out System.object ComponentXForms  
)
```

C++/CLI

```
void GetSelections3(  
& [Out] System.Object^ Objects,  
& [Out] System.Object^ ObjectTypes,  
& [Out] System.Object^ SelMarks,  
& [Out] System.Object^ DrViews,  
& [Out] System.Object^ ComponentXForms  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Objects

Array of selected objects

ObjectTypes

Array of selected object types as defined in [swSelectType_e](#)

SelMarks

Array of marks for the selected objects

DrViews

Array of [drawing views](#)

ComponentXForms

Array of [transforms](#) for the selections' components

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetSelections3](#).

Example

[Cut Body in Half Using Macro Feature \(VBA\)](#)

Remarks

When a macro feature is inserted in-context and an entity on a different component is selected, you may need to know that component's transform.

If the assembly is the active document, then you can use [IEntity::GetComponent](#) or [IComponent2::Transform2](#) to get the component's transform

However, if the part for the component is open for editing and a [macro feature is being edited](#), then you must use [IMacroFeatureData::GetSelections3](#) to get the component's transform. This method returns the transform and the selection. If the selection belongs to the same part as the macro feature, then NULL is returned. See also [Macro Features and Component Transforms](#).

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetSelectionCount Method](#)
[IMacroFeatureData::!GetSelections3 Method](#)
[IMacroFeatureData::!SetSelections2 Method](#)
[IMacroFeatureData::SetSelections2 Method](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetStringByName Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : GetStringByName Method (IMacroFeatureData)

Gets a string value by the name of the parameter for the macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub GetStringByName(  
    ByVal ParamName As System.String, _  
    ByRef ParamValue As System.String _  
)
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim ParamName As System.String  
Dim ParamValue As System.String  
  
instance.GetStringByName(ParamName, ParamValue)
```

C#

```
void GetStringByName(  
    System.string ParamName,  
    out System.string ParamValue  
)
```

C++/CLI

```
void GetStringByName(  
& System.String^ ParamName,  
& [Out] System.String^ ParamValue  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ParamName
Name of the parameter

ParamValue
String value

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::GetStringByName](#).

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetDoubleByName Method](#)
[IMacroFeatureData::GetIntegerByName Method](#)
[IMacroFeatureData::GetParameterCount Method](#)

[IMacroFeatureData::GetParameters Method](#)
[IMacroFeatureData::IGetParameters Method](#)
[IMacroFeatureData::SetDoubleByName Method](#)
[IMacroFeatureData::SetIntegerByName Method](#)
[IMacroFeatureData::SetStringByName Method](#)

 Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

IAccessSelections Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : IAccessSelections Method (IMacroFeatureData)

Gains access to the selections associated with this macro feature.

 .NET Syntax

Visual Basic (Declaration)

```
Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim TopDoc As ModelDoc2  
Dim Component As Component2  
Dim value As System.Boolean  
  
value = instance.IAccessSelections(TopDoc, Component)
```

C#

```
System.bool IAccessSelections(  
    ModelDoc2 TopDoc,  
    Component2 Component  
)
```

C++/CLI

```
System.bool IAccessSelections(  
& ModelDoc2^ TopDoc,  
& Component2^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc
Top-level document (see **Remarks**)
Component
Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections were successfully accessed, false if not

 Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::IAccessSelections](#).

 Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::IModifyDefinition2](#) if you modified the feature
- [IMacroFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::AccessSelections Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IAddDisplayDimensions Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : IAddDisplayDimensions Method (IMacroFeatureData)

Adds the specified display dimensions to this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub IAddDisplayDimensions( _  
    ByVal DimCount As System.Integer, _  
    ByRef DimTypes As System.Integer, _  
    ByRef DimValues As System.Double _  
)
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim DimCount As System.Integer  
Dim DimTypes As System.Integer  
Dim DimValues As System.Double  
  
instance.IAddDisplayDimensions(DimCount, DimTypes, DimValues)
```

C#

```
void IAddDisplayDimensions(  
    System.int DimCount,  
    ref System.int DimTypes,  
    ref System.double DimValues  
)
```

C++/CLI

```
void IAddDisplayDimensions(  
& System.int DimCount,  
& System.int% DimTypes,  
& System.double% DimValues  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

DimCount
Number of display dimensions
DimTypes

- in-process, unmanaged C++: Pointer to an array of display dimension types as defined [swDimensionType_e](#)
- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

DimValues

- in-process, unmanaged C++: Pointer to an array of display dimension values
- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)

Availability

SOLIDWORKS 2013 FCS, Revision Number 21.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IconFiles Property (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : IconFiles Property (IMacroFeatureData)

Gets or sets the file names for the icons for this macro feature.

.NET Syntax

Visual Basic (Declaration)

Property IconFiles As System.Object

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim value As System.Object
```

```
instance.IconFiles = value
```

```
value = instance.IconFiles
```

C#

```
System.Object IconFiles {get; set;}
```

C++/CLI

```
property System.Object^ IconFiles {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of the file names for the icons (see **Remarks**)

Visual Basic for Applications (VBA) Syntax

See [MacroFeatureData::IconFiles](#).

Remarks

The array of the file names for the icons can contain either three or nine strings.

Number of strings in array	Types of images in this order	Image format and sizes
Three	1. Regular 2. Suppressed 3. Highlighted	• Windows bitmap (*.bmp) format • 16 pixels wide X 18 pixels high
Nine	1. Regular small 2. Suppressed small 3. Highlighted small 4. Regular medium 5. Suppressed medium 6. Highlighted medium 7. Regular large 8. Suppressed large 9. Highlighted large	• Windows bitmap (*.bmp) format • Recommended sizes are: • Small: 20 pixels wide X 20 pixels high • Medium: 32 pixels wide X 32 pixels high • Large: 40 pixels wide X 40 pixels high

NOTES:

- This size array is only valid for macro features created in parts, assemblies, and drawings in SOLIDWORKS 2017 and later.
- SOLIDWORKS displays the appropriate images based on the current DPI setting of the display device.

You can specify either the full path name or just the file name for the strings; for example, **c:\bitmaps\icon1.bmp** or **icon1.bmp**.

If you change the bitmaps after inserting them with a macro feature into a SOLIDWORKS document, then the new bitmaps are not displayed until you exit and restart SOLIDWORKS.

See [Accessing Selections that Define Features](#) for additional details on using this property.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetIconFileCount Method](#)
[IMacroFeatureData::GetIconFiles Method](#)
[IMacroFeatureData::SetIconFiles Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetDisplayDimensions Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : IGetDisplayDimensions Method (IMacroFeatureData)

Gets the display dimensions for this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub IGetDisplayDimensions( _  
    ByVal DimCount As System.Integer, _  
    ByRef Dims As DisplayDimension _  
)
```

Visual Basic (Usage)



```
Dim instance As IMacroFeatureData  
Dim DimCount As System.Integer  
Dim Dims As DisplayDimension  
  
instance.IGetDisplayDimensions(DimCount, Dims)
```

C#

```
void IGetDisplayDimensions(  
    System.int DimCount,  
    out DisplayDimension Dims  
)
```

C++/CLI

```
void IGetDisplayDimensions(  
&    System.int DimCount,  
&    [Out] DisplayDimension^ Dims  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

DimCount

Number of display dimensions

Dims

- in-process, unmanaged C++: Pointer to an array of [display dimensions](#)

• VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

Before calling this method, call [IMacroFeatureData::GetDisplayDimensionCount](#) to determine the size of the array.

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::GetDisplayDimensions Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetEditBodies Method (IMacroFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IMacroFeatureData Interface](#) : IGetEditBodies Method (IMacroFeatureData)

Gets the bodies to be modified by this macro feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub IGetEditBodies( _  
    ByVal BodiesCount As System.Integer, _  
    ByRef PBodies As Body2 _  
)
```

Visual Basic (Usage)

```
Dim instance As IMacroFeatureData  
Dim BodiesCount As System.Integer  
Dim PBodies As Body2  
  
instance.IGetEditBodies(BodiesCount, PBodies)
```

C#

```
void IGetEditBodies(  
    System.int BodiesCount,  
    out Body2 PBodies  
)
```

C++/CLI

```
void IGetEditBodies(  
& System.int BodiesCount,  
& [Out] Body2^ PBodies  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

BodiesCount

Number of bodies to be modified by this macro feature

PBodies

- in-process, unmanaged C++: Pointer to an array of [bodies](#) to be modified by this macro feature

• VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

Before calling this method, call [IMacroFeatureData::GetEditBodiesCount](#) to determine the size the array.

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[IMacroFeatureData Interface](#)
[IMacroFeatureData Members](#)
[IMacroFeatureData::ISetEditBodies Method](#)
[IMacroFeatureData::EditBodies Property](#)
[IMacroFeatureData::EnableMultiBodyConsume Method\(\)](#)

