

SOLIDWORKS API (NET VBA C#) — Reference (209/337): IModelViewManager

SOLIDWORKS API Documentation (converted from CHM)

IModelViewManager (Type)

IModelViewManager Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IModelViewManager Interface

Allows access to the model view.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IModelViewManager
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
```

C#

```
public interface IModelViewManager
```

C++/CLI

```
public interface class IModelViewManager
```

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager](#).

Example

- [Create Section View in Model \(C#\)](#)
- [Create Section View in Model \(VB.NET\)](#)
- [Create Section View in Model \(VBA\)](#)
- [Set Viewports \(C#\)](#)
- [Set Viewports \(VB.NET\)](#)
- [Set Viewports \(VBA\)](#)
- [Add .NET Controls to SOLIDWORKS using an Add-in \(C#\)](#)
- [Add .NET Controls to SOLIDWORKS using an Add-in \(VB.NET\)](#)

Accessors

[IModelDoc2::ModelViewManager](#)

Access Diagram

[ModelViewManager](#)

See Also

- [IModelViewManager Members](#)
- [SolidWorks.Interop.sldworks Namespace](#)
- [IModelView Interface](#)
- [IManipulator Interface](#)
- [ISectionViewData Interface](#)
- [IFeatMgrView Interface](#)

IModelViewManager Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IModelViewManager Interface

The following tables list the members exposed by [IModelViewManager](#).

Public Properties

Name	Description
 ActiveFeatureManagerTabIndex	Gets or sets the index of the active tab in the Manager Pane.
 Document	Gets the document to which this model view belongs.
 FeatureManagerTabsVisible	Gets or sets whether all of the tabs in the Manager Pane are visible.
 LinkedViews	Gets or sets whether linking of viewports is enabled in this document.
 ViewportDisplay	Sets the model's viewport arrangement.

[Top](#)

Public Methods

Name	Description
 ActivateControlTab	Selects a control tab on the model view to be the active tab.
 ActivateModelTab	Selects a control tab on the model view.
 AddControl	Adds a tab to this model view using the specified ActiveX control.
 AddControl2	Obsolete. Superseded by IModelViewManager::AddControl3
 AddControl3	Adds a tab to this model view that supports tab traversal using the specified ActiveX control.
 AddSnapShot	Creates a snapshot with the specified name of an assembly.
 CreateFeatureMgrControl	Obsolete. Superseded by IModelViewManager::CreateFeatureMgrControl2
 CreateFeatureMgrControl2	Obsolete. Superseded by IModelViewManager::CreateFeatureMgrControl3
 CreateFeatureMgrControl3	Obsolete. Superseded by IModelViewManager::CreateFeatureMgrControl4
 CreateFeatureMgrControl4	Creates a new FeatureManager design tree view containing the specified ActiveX control with a tab that displays the specified scaleable icon.
 CreateFeatureMgrView	Obsolete. Superseded by IModelViewManager::CreateFeatureMgrView2
 CreateFeatureMgrView2	Creates a new view (tab) in this FeatureManager design tree.
 CreateFeatureMgrWindowFromHandle	Obsolete. Superseded by IModelViewManager::CreateFeatureMgrWindowFromHandlex64. This method is unsafe to use with 64-bit SOLIDWORKS, i.e. all versions since SOLIDWORKS 2016. The 32-bit integer returned may be too small to contain the 64-bit window handle/pointer, and will be truncated silently. A critical exception will occur sometime later, when the truncated handle/pointer is used. Creates a new view in the FeatureManager design tree using the specified .NET tab control.
 CreateFeatureMgrWindowFromHandlex64	On 64-bit machines, creates a new view in the FeatureManager design tree using the specified .NET tab control.
 CreateManipulator	Creates a manipulator, which is similar to the triad in the SOLIDWORKS Design user interface.
 CreateSectionView	Creates a section view in parts and assemblies.
 CreateSectionViewData	Creates an empty ISectionViewData object whose properties you set before creating a section view in a part or an assembly .
 DeleteControlTab	Deletes the specified control tab.
 DeleteSnapShot	Deletes the specified snapshot from an assembly.
 DisplayWindowFromHandle	Obsolete. Superseded by IModelViewManager::DisplayWindowFromHandlex64. This method is unsafe to use with 64-bit SOLIDWORKS, i.e. all versions since SOLIDWORKS 2016. The 32-bit integer returned may be too small to contain the 64-bit window handle/pointer, and will be truncated silently. A critical exception will occur sometime later, when the truncated handle/pointer is used. Displays a .NET control in this model view.
 DisplayWindowFromHandlex64	Displays a .NET control in this model view on 64-bit machines.
 GetConfigurationManagerTabIndex	Gets the index of the ConfigurationManager tab in the Manager Pane.
 GetControl	Gets the control associated with this model view.
 GetDimXpertManagerTabIndex	Gets the index of the DimXpertManager tab in the Manager Pane.
 GetDisplayManagerTabIndex	Gets the index of the DisplayManager tab in the Manager Pane.
 GetFeatureManagerTabs	Gets the tabs from right to left in the Manager Pane.

	GetFeatureManagerTreeTabIndex	Gets the index of the FeatureManager design tree tab in the Manager Pane.
	GetFeatureMgrViewHWnd	Obsolete. Superseded by IModelViewManager::GetFeatureMgrViewHWndx64. This method is unsafe to use with 64-bit SOLIDWORKS, i.e. all versions since SOLIDWORKS 2016. The 32-bit integer returned may be too small to contain the 64-bit window handle/pointer, and will be truncated silently. A critical exception will occur sometime later, when the truncated handle/pointer is used. Gets the window handle for the specified FeatureManager design tree view.
	GetFeatureMgrViewHWndx64	Gets the window handle for the specified FeatureManager design tree view in 64-bit applications.
	GetPropertyManagerTabIndex	Gets the index of the PropertyManager tab in the Manager Pane.
	GetSectionViewData	Gets access to the data of the specified section view.
	GetSnapShot	Gets the specified snapshot of an assembly.
	GetSnapShots	Gets the snapshots of an assembly.
	IGetControl	Gets the control associated with this model view.
	IsControlTabActive	Gets whether the specified control is active.
	IsModelTabActive	Gets whether the control on this model view is active.
	RemoveSectionView	Removes a section view from a part and assembly.

[Top](#)

See Also

[IModelViewManager Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelView Interface](#)
[IManipulator Interface](#)
[ISectionViewData Interface](#)
[IFeatMgrView Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IModelViewManager Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IModelViewManager Interface

For a list of all members of this type, see [IModelViewManager members](#).

Public Methods

Name	Description
	ActivateControlTab Selects a control tab on the model view to be the active tab.
	ActivateModelTab Selects a control tab on the model view.
	AddControl Adds a tab to this model view using the specified ActiveX control.
	AddControl2 Obsolete. Superseded by IModelViewManager::AddControl3.
	AddControl3 Adds a tab to this model view that supports tab traversal using the specified ActiveX control.
	AddSnapShot Creates a snapshot with the specified name of an assembly.
	CreateFeatureMgrControl Obsolete. Superseded by IModelViewManager::CreateFeatureMgrControl2.
	CreateFeatureMgrControl2 Obsolete. Superseded by IModelViewManager::CreateFeatureMgrControl3.
	CreateFeatureMgrControl3 Obsolete. Superseded by IModelViewManager::CreateFeatureMgrControl4.
	CreateFeatureMgrControl4 Creates a new FeatureManager design tree view containing the specified ActiveX control with a tab that displays the specified scaleable icon.
	CreateFeatureMgrView Obsolete. Superseded by IModelViewManager::CreateFeatureMgrView2.
	CreateFeatureMgrView2 Creates a new view (tab) in this FeatureManager design tree.
	CreateFeatureMgrWindowFromHandle Obsolete. Superseded by IModelViewManager::CreateFeatureMgrWindowFromHandlex64. This method is unsafe to use with 64-bit SOLIDWORKS, i.e. all versions since SOLIDWORKS 2016. The 32-bit integer returned may be too small to contain the 64-bit window handle/pointer, and will be truncated silently. A critical exception will occur sometime later, when the truncated handle/pointer is used.

Creates a new view in the FeatureManager design tree using the specified .NET tab control.

	CreateFeatureMgrWindowFromHandlex64	On 64-bit machines, creates a new view in the FeatureManager design tree using the specified .NET tab control.
	CreateManipulator	Creates a manipulator, which is similar to the triad in the SOLIDWORKS Design user interface.
	CreateSectionView	Creates a section view in parts and assemblies.
	CreateSectionViewData	Creates an empty ISectionViewData object whose properties you set before creating a section view in a part or an assembly .
	DeleteControlTab	Deletes the specified control tab.
	DeleteSnapShot	Deletes the specified snapshot from an assembly.
	DisplayWindowFromHandle	Obsolete. Superseded by IModelViewManager::DisplayWindowFromHandlex64. This method is unsafe to use with 64-bit SOLIDWORKS, i.e. all versions since SOLIDWORKS 2016. The 32-bit integer returned may be too small to contain the 64-bit window handle/pointer, and will be truncated silently. A critical exception will occur sometime later, when the truncated handle/pointer is used. Displays a .NET control in this model view.
	DisplayWindowFromHandlex64	Displays a .NET control in this model view on 64-bit machines.
	GetConfigurationManagerTabIndex	Gets the index of the ConfigurationManager tab in the Manager Pane.
	GetControl	Gets the control associated with this model view.
	GetDimXpertManagerTabIndex	Gets the index of the DimXpertManager tab in the Manager Pane.
	GetDisplayManagerTabIndex	Gets the index of the DisplayManager tab in the Manager Pane.
	GetFeatureManagerTabs	Gets the tabs from right to left in the Manager Pane.
	GetFeatureManagerTreeTabIndex	Gets the index of the FeatureManager design tree tab in the Manager Pane.
	GetFeatureMgrViewHWnd	Obsolete. Superseded by IModelViewManager::GetFeatureMgrViewHWndx64. This method is unsafe to use with 64-bit SOLIDWORKS, i.e. all versions since SOLIDWORKS 2016. The 32-bit integer returned may be too small to contain the 64-bit window handle/pointer, and will be truncated silently. A critical exception will occur sometime later, when the truncated handle/pointer is used. Gets the window handle for the specified FeatureManager design tree view.
	GetFeatureMgrViewHWndx64	Gets the window handle for the specified FeatureManager design tree view in 64-bit applications.
	GetPropertyManagerTabIndex	Gets the index of the PropertyManager tab in the Manager Pane.
	GetSectionViewData	Gets access to the data of the specified section view.
	GetSnapShot	Gets the specified snapshot of an assembly.
	GetSnapShots	Gets the snapshots of an assembly.
	IGetControl	Gets the control associated with this model view.
	IsControlTabActive	Gets whether the specified control is active.
	IsModelTabActive	Gets whether the control on this model view is active.
	RemoveSectionView	Removes a section view from a part and assembly.

[Top](#)

See Also

[IModelViewManager Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelView Interface](#)
[IManipulator Interface](#)
[ISectionViewData Interface](#)
[IFeatMgrView Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IModelViewManager Interface Properties

[See Also](#)

 [SolidWorks.Interop.sldworks Namespace](#) : [IModelViewManager Interface](#)

For a list of all members of this type, see [IModelViewManager members](#).

Public Properties

Name	Description
 ActiveFeatureManagerTabIndex	Gets or sets the index of the active tab in the Manager Pane.
 Document	Gets the document to which this model view belongs.
 FeatureManagerTabsVisible	Gets or sets whether all of the tabs in the Manager Pane are visible.
 LinkedViews	Gets or sets whether linking of viewports is enabled in this document.
 ViewportDisplay	Sets the model's viewport arrangement.

[Top](#)

See Also

[IModelViewManager Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelView Interface](#)
[IManipulator Interface](#)
[ISectionViewData Interface](#)
[IFeatMgrView Interface](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ActivateControlTab Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : ActivateControlTab Method (IModelViewManager)

Selects a control tab on the model view to be the active tab.

.NET Syntax

Visual Basic (Declaration)

```
Function ActivateControlTab( _  
    ByVal Name As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim Name As System.String  
Dim value As System.Boolean  
  
value = instance.ActivateControlTab(Name)
```

C#

```
System.bool ActivateControlTab(  
    System.string Name  
)
```

C++/CLI

```
System.bool ActivateControlTab(  
& System.String^ Name  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name

Name of control tab

Return Value

True if the selected control tab is active, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::ActivateControlTab](#).

Example

[Add ActiveX Tabs to Model View \(C#\)](#)
[Add ActiveX Tabs to Model View \(VB.NET\)](#)
[Add ActiveX Tabs to Model View \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::ActivateModelTab Method](#)
[IModelViewManager::AddControl3 Method](#)
[IModelViewManager::DeleteControlTab Method](#)
[IModelViewManager::GetControl Method](#)
[IModelViewManager::IGetControl Method](#)
[IModelViewManager::IsControlTabActive Method](#)
[IModelViewManager::IsModelTabActive Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ActivateModelTab Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : ActivateModelTab Method (IModelViewManager)

Selects a control tab on the model view.

.NET Syntax

Visual Basic (Declaration)

```
Function ActivateModelTab() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim value As System.Boolean  
  
value = instance.ActivateModelTab()
```

C#

```
System.bool ActivateModelTab()
```

C++/CLI

```
System.bool ActivateModelTab();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if the control tab on the model view is selected, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::ActivateModelTab](#).

Example

[Add ActiveX Tabs to Model View \(C#\)](#)
[Add ActiveX Tabs to Model View \(VB.NET\)](#)
[Add ActiveX Tabs to Model View \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)

[IModelViewManager::ActivateControlTab Method](#)
[IModelViewManager::AddControl3 Method](#)
[IModelViewManager::DeleteControlTab Method](#)
[IModelViewManager::GetControl Method](#)
[IModelViewManager::!GetControl Method](#)
[IModelViewManager::IsControlTabActive Method](#)
[IModelViewManager::IsModelTabActive Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ActiveFeatureManagerTabIndex Property (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : ActiveFeatureManagerTabIndex Property (IModelViewManager)

Gets or sets the index of the active tab in the Manager Pane.

.NET Syntax

Visual Basic (Declaration)

Property ActiveFeatureManagerTabIndex As System.Integer

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim value As System.Integer

instance.ActiveFeatureManagerTabIndex = value

value = instance.ActiveFeatureManagerTabIndex
```

C#

```
System.int ActiveFeatureManagerTabIndex {get; set;}
```

C++/CLI

```
property System.int ActiveFeatureManagerTabIndex {
    System.int get();
    void set ( & System.int value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Index of the active tab in the Manager Pane

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::ActiveFeatureManagerTabIndex](#).

Example

[Change Active Tab in Manager Pane \(C#\)](#)
[Change Active Tab in Manager Pane \(VB.NET\)](#)
[Change Active Tab in Manager Pane \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::FeatureManagerTabsVisible Property \(\)](#)
[IModelViewManager::GetConfigurationManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDimXpertManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDisplayManagerTabIndex Method \(\)](#)
[IModelViewManager::GetFeatureManagerTabs Method \(\)](#)
[IModelViewManager::GetFeatureManagerTreeTabIndex Method \(\)](#)
[IModelViewManager::GetPropertyManagerTabIndex Method \(\)](#)
[DAssemblyDocEvents_FeatureManagerTabActivatedNotifyEventHandler Delegate \(IModelViewManager\)](#)
[DAssemblyDocEvents_FeatureManagerTabActivatedPreNotifyEventHandler Delegate \(IModelViewManager\)](#)
[DDrawingDocEvents_FeatureManagerTabActivatedNotifyEventHandler Delegate \(IModelViewManager\)](#)
[DDrawingDocEvents_FeatureManagerTabActivatedPreNotifyEventHandler Delegate \(IModelViewManager\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

AddControl Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : AddControl Method (IModelViewManager)

Adds a tab to this model view using the specified ActiveX control.

.NET Syntax

Visual Basic (Declaration)

```
Function AddControl( _  
    ByVal Name As System.String, _  
    ByVal ControlName As System.String, _  
    ByVal BstrLicKey As System.String _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim Name As System.String  
Dim ControlName As System.String  
Dim BstrLicKey As System.String  
Dim value As System.Object  
  
value = instance.AddControl(Name, ControlName, BstrLicKey)
```

C#

```
System.Object AddControl(  
    System.string Name,  
    System.string ControlName,  
    System.string BstrLicKey  
)
```

C++/CLI

```
System.Object^ AddControl(  
& System.String^ Name,  
& System.String^ ControlName,  
& System.String^ BstrLicKey  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name

User-defined label that appears on the tab

ControlName

Name or class ID for the ActiveX control

BstrLicKey

Optional license key; this data is needed to create ActiveX controls that require a runtime license key; if the ActiveX control supports licensing, then provide a license key for the creation of the ActiveX control; default value is NULL

Return Value

Pointer to the new ActiveX control

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::AddControl](#).

Example

[Add ActiveX Tabs to Model View \(C#\)](#)
[Add ActiveX Tabs to Model View \(VB.NET\)](#)
[Add ActiveX Tabs to Model View \(VBA\)](#)

Remarks

If your ActiveX control needs tab traversal support, then use [IModelViewManager::AddControl3](#).

This method sets the class ID and license key information for the ActiveX control when the API PropertyManager page is shown and the ActiveX control is created. The controlName argument can be either the name of the control (ProgID) or the class ID (CLSID), for example, "MSCAL.calendar" or "{8E27C92B-1264-101C-8A2F-040224009C02}". Both provide the calendar protocol. You can obtain these strings using a combination of the Microsoft OLE/COM Object Viewer and the registry editor.

For example:

```
' ProgID
bRet = m_pActiveXControl.SetClass("MSCAL.Calendar", "")
bRet = m_pActiveXControl2.SetClass("MSComctlLib.ListViewCtrl", "")

' CLSID
bRet = m_pActiveXControl.SetClass("{8E27C92B-1264-101C-8A2F-040224009C02}", "")
bRet = m_pActiveXControl2.SetClass("{BDD1F04B-858B-11D1-B16A-00C0F0283628}", "")
```

To delete a tab created by this method, use [IModelViewManager::DeleteControlTab](#).

See also [Keystrokes and Accelerator Keys in ActiveX Modeless Dialogs and PropertyManager Pages](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::ActivateControlTab Method](#)
[IModelViewManager::ActivateModelTab Method](#)
[IModelViewManager::DeleteControlTab Method](#)
[IModelViewManager::GetControl Method](#)
[IModelViewManager::IGetControl Method](#)
[IModelViewManager::IsControlTabActive Method](#)
[IModelViewManager::IsModelTabActive Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

AddControl2 Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : AddControl2 Method (IModelViewManager)

Obsolete. Superseded by [IModelViewManager::AddControl3](#).

.NET Syntax

Visual Basic (Declaration)

```
Function AddControl2( _
    ByVal Name As System.String, _
    ByVal ControlName As System.String, _
    ByVal BstrLicKey As System.String _
) As System.Object
```

Visual Basic (Usage)

```
Dim instance As IModelViewManager
Dim Name As System.String
Dim ControlName As System.String
```



```
Dim BstrLicKey As System.String
Dim value As System.Object

value = instance.AddControl2(Name, ControlName, BstrLicKey)
```

C#

```
System.object AddControl2(
    System.string Name,
    System.string ControlName,
    System.string BstrLicKey
)
```

C++/CLI

```
System.Object^ AddControl2(
    & System.String^ Name,
    & System.String^ ControlName,
    & System.String^ BstrLicKey
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name

ControlName

BstrLicKey

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::AddControl2](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

AddControl3 Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : AddControl3 Method (IModelViewManager)

Adds a tab to this model view that supports tab traversal using the specified ActiveX control.

.NET Syntax

Visual Basic (Declaration)

```
Function AddControl3( _
    ByVal Name As System.String, _
    ByVal ControlName As System.String, _
    ByVal BstrLicKey As System.String, _
    ByVal SplitWindow As System.Boolean _
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim Name As System.String
Dim ControlName As System.String
Dim BstrLicKey As System.String
Dim SplitWindow As System.Boolean
Dim value As System.Object
```

```
value = instance.AddControl3(Name, ControlName, BstrLicKey, SplitWindow)
```

C#

```
System.object AddControl3(
    System.string Name,
    System.string ControlName,
    System.string BstrLicKey,
    System.bool SplitWindow
)
```

C++/CLI

```
System.Object^ AddControl3(
    & System.String^ Name,
    & System.String^ ControlName,
    & System.String^ BstrLicKey,
    & System.bool SplitWindow
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name

User-defined label that appears on the tab

ControlName

Name or class ID for the ActiveX control

BstrLicKey

Optional license key; this data is needed to create ActiveX controls that require a runtime license key; if the ActiveX control supports licensing, then provide a license key for the creation of the ActiveX control; default value is NULL

SplitWindow

True to add a splitter window, false to not

Return Value

Pointer to the new ActiveX control

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::AddControl3](#).

Remarks

If your ActiveX control does not need tab traversal support, then use [IModelViewManager::AddControl](#).

This method sets the class ID and license key information for the ActiveX control when the API PropertyManager page is shown and the ActiveX control is created. The controlName argument can be either the name of the control (ProgID) or the class ID (CLSID), for example, "MSCAL.calendar" or "{8E27C92B-1264-101C-8A2F-040224009C02}". Both provide the calendar protocol. You can obtain these strings using a combination of the Microsoft OLE/COM Object Viewer and the registry editor.

For example:

```
' ProgID
bRet = m_pActiveXControl.SetClass("MSCAL.Calendar", "")
bRet = m_pActiveXControl2.SetClass("MSComctlLib.ListViewCtrl", "")

' CLSID
bRet = m_pActiveXControl.SetClass("{8E27C92B-1264-101C-8A2F-040224009C02}", "")
bRet = m_pActiveXControl2.SetClass("{BDD1F04B-858B-11D1-B16A-00C0F0283628}", "")
```

Two or more tabs cannot be added with the same name.

To delete a tab created by this method, use [IModelViewManager::DeleteControlTab](#). Each use of IModelViewManager::AddControl3 must use a corresponding IModelViewManager::DeleteControlTab before exiting your macro or application.

See also [Keystrokes and Accelerator Keys in ActiveX Modeless Dialogs and PropertyManager Pages](#).

See Also

[IModelViewManager Interface](#)

[IModelViewManager Members](#)

[IModelViewManager::ActivateControlTab Method](#)

[IModelViewManager::ActivateModelTab Method](#)

[IModelViewManager::GetControl Method](#)

[IModelViewManager::GetControl Method](#)
[IModelViewManager::IsControlTabActive Method](#)
[IModelViewManager::IsModelTabActive Method](#)
[IModelViewManager::DeleteControlTab Method](#)
[IModelViewManager::CreateFeatureMgrView2 Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

AddSnapShot Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : AddSnapShot Method (IModelViewManager)

Creates a snapshot with the specified name of an assembly.

.NET Syntax

Visual Basic (Declaration)

```
Function AddSnapShot( _  
    ByVal SnapShotName As System.String _  
) As Snapshot
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim SnapShotName As System.String  
Dim value As Snapshot  
  
value = instance.AddSnapShot(SnapShotName)
```

C#

```
Snapshot AddSnapShot(  
    System.string SnapShotName  
)
```

C++/CLI

```
Snapshot^ AddSnapShot(  
& System.String^ SnapShotName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

SnapShotName

- Name of the snapshot
- OR -
- "" to give a default name of "Snapn"
- OR -
- "?" to open the Name Snapshot dialog box

Return Value

[ISnapShot](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::AddSnapShot](#).

Example

[Open Assembly in Large Design Review Mode \(VBA\)](#)
[Open Assembly in Large Design Review Mode \(VB.NET\)](#)
[Open Assembly in Large Design Review Mode \(C#\)](#)

Remarks

This method is valid only for assemblies.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::DeleteSnapshot Method](#)
[IModelViewManager::GetSnapshot Method](#)
[IModelViewManager::GetSnapshots Method](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateFeatureMgrControl Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateFeatureMgrControl Method (IModelViewManager)

Obsolete. Superseded by [IModelViewManager::CreateFeatureMgrControl2](#)

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrControl( _  
    ByVal PPicture As System.Object, _  
    ByVal Class As System.String, _  
    ByVal LicKey As System.String, _  
    ByVal ToolTip As System.String, _  
    ByVal WhichPane As System.Integer _  
) As FeatMgrView
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim PPicture As System.Object  
Dim Class As System.String  
Dim LicKey As System.String  
Dim ToolTip As System.String  
Dim WhichPane As System.Integer  
Dim value As FeatMgrView  
  
value = instance.CreateFeatureMgrControl(PPicture, Class, LicKey, ToolTip, WhichPane)
```

C#

```
FeatMgrView CreateFeatureMgrControl(  
    System.object PPicture,  
    System.string Class,  
    System.string LicKey,  
    System.string ToolTip,  
    System.int WhichPane  
)
```

C++/CLI

```
FeatMgrView^ CreateFeatureMgrControl(  
& System.Object^ PPicture,  
& System.String^ Class,  
& System.String^ LicKey,  
& System.String^ ToolTip,  
& System.int WhichPane  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PPicture

Pointer to the bitmap that you want to use for the tab

Class

Class ID for the ActiveX control

LicKey

License key for the ActiveX control

ToolTip

Text for the ToolTip

WhichPane

Pane to use as defined in [swFeatMgrPane_e](#)

Return Value

Pointer to the new [tab](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateFeatureMgrControl](#).

Remarks

This method is not supported in applications written in .NET languages.

The user can click the tab to activate an ActiveX control.

This method references the IPictureDisp interface. Use [IModelViewManager::CreateFeatureMgrControl2](#) to specify the fully qualified path to the bitmap file on disk. Use [IModelViewManager::CreateFeatureMgrControl3](#) if tab traversal support is needed and specify a fully qualified path to the bitmap file on disk.

This method sets the class ID and license key information for the ActiveX control when the API PropertyManager page is shown and the ActiveX control is created. The Class argument can be either the name of the control (ProgID) or the class ID (CLSID), for example, "MSCAL.calendar" or "{8E27C92B-1264-101C-8A2F-040224009C02}". Both provide the calendar protocol. You can obtain these strings using a combination of the Microsoft OLE/COM Object Viewer and the registry editor.

For example:

```
' ProgID
bRet = m_pActiveXControl.SetClass("MSCAL.Calendar", "")
bRet = m_pActiveXControl2.SetClass("MSComctlLib.ListViewCtrl", "")

' CLSID
bRet = m_pActiveXControl.SetClass("{8E27C92B-1264-101C-8A2F-040224009C02}", "")
bRet = m_pActiveXControl2.SetClass("{BDD1F04B-858B-11D1-B16A-00C0F0283628}", "")
```

See also [Keystrokes and Accelerator Keys in ActiveX Modeless Dialogs and PropertyManager Pages](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)

Availability

SOLIDWORKS 2003 SP1, Revision Number 11.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateFeatureMgrControl2 Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateFeatureMgrControl2 Method (IModelViewManager)

Obsolete. Superseded by [IModelViewManager::CreateFeatureMgrControl3](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrControl2( _
    ByVal BitMapFile As System.String, _
    ByVal Class As System.String, _
    ByVal LicKey As System.String, _
```

```

ByVal ToolTip As System.String, _
ByVal WhichPane As System.Integer _
) As FeatMgrView

```

Visual Basic (Usage)



```

Dim instance As IModelViewManager
Dim BitMapFile As System.String
Dim Class As System.String
Dim LicKey As System.String
Dim ToolTip As System.String
Dim WhichPane As System.Integer
Dim value As FeatMgrView

value = instance.CreateFeatureMgrControl2(BitMapFile, Class, LicKey, ToolTip, WhichPane)

```

C#

```

FeatMgrView CreateFeatureMgrControl2(
    System.string BitMapFile,
    System.string Class,
    System.string LicKey,
    System.string ToolTip,
    System.int WhichPane
)

```

C++/CLI

```

FeatMgrView^ CreateFeatureMgrControl2(
    & System.String^ BitMapFile,
    & System.String^ Class,
    & System.String^ LicKey,
    & System.String^ ToolTip,
    & System.int WhichPane
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

BitMapFile

Fully qualified path to the bitmap file that you want to use for the tab

Class

Class ID for the ActiveX control

LicKey

License key for the ActiveX control

ToolTip

Text for the ToolTip

WhichPane

Pane to use as defined in [swFeatMgrPane_e](#)

Return Value

Pointer to the new [tab](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateFeatureMgrControl2](#).

Example

[Add ActiveX Tabs to FeatureManager Design Tree \(C#\)](#)
[Add ActiveX Tabs to FeatureManager Design Tree \(VB.NET\)](#)
[Add ActiveX Tabs to FeatureManager Design Tree \(VBA\)](#)
[Split FeatureManager Design Tree and Position Splitter \(C#\)](#)
[Split FeatureManager Design Tree and Position Splitter \(VB.NET\)](#)
[Split FeatureManager Design Tree and Position Splitter \(VBA\)](#)

Remarks

This method lets you add a tab for a registered ActiveX control to the FeatureManager design tree. A user can click the tab to activate the Active control.

To add a tab to the FeatureManager design tree, specify `swFeatMgrPane_e.FeatMgrPaneBottom` for WhichPane. To add a tab to a FeatureManager design tree that has been split, specify `swFeatMgrPane_e.swFeatMgrPaneTop` and `swFeatMgrPane_e.swFeatMgrPaneBottom` respectively, for WhichPane. See [IModelDoc2::FeatureManagerSplitterPosition](#) for details on splitting and positioning the split panel bar on a split FeatureManager design tree.

To delete a tab created by this method, use [IFeatMgrView::DeleteView](#).

Class can be either the name of the registered control (ProgID) or its class ID (CLSID), for example, "MSCAL.calendar" or "{8E27C92B-1264-101C-8A2F-040224009C02}". You must obtain these strings by searching for the registered ActiveX control in the registry editor. The ActiveX control library names displayed in the Object Browser may not be the same as the ActiveX control names in the registry. Do not use the Object Browser to specify Class.

See also [Keystrokes and Accelerator Keys in ActiveX Modeless Dialogs and PropertyManager Pages](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::CreateFeatureMgrView2 Method](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateFeatureMgrControl3 Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateFeatureMgrControl3 Method (IModelViewManager)

Obsolete. Superseded by [IModelViewManager::CreateFeatureMgrControl4](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrControl3( _  
    ByVal BitMapFile As System.String, _  
    ByVal Class As System.String, _  
    ByVal LicKey As System.String, _  
    ByVal ToolTip As System.String, _  
    ByVal WhichPane As System.Integer _  
    ) As FeatMgrView
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim BitMapFile As System.String  
Dim Class As System.String  
Dim LicKey As System.String  
Dim ToolTip As System.String  
Dim WhichPane As System.Integer  
Dim value As FeatMgrView
```

```
value = instance.CreateFeatureMgrControl3(BitMapFile, Class, LicKey, ToolTip, WhichPane)
```

C#

```
FeatMgrView CreateFeatureMgrControl3(  
    System.string BitMapFile,  
    System.string Class,  
    System.string LicKey,  
    System.string ToolTip,  
    System.int WhichPane  
)
```

C++/CLI

```
FeatMgrView^ CreateFeatureMgrControl3(  
& System.String^ BitMapFile,  
& System.String^ Class,
```

```
& System.String^ LicKey,  
& System.String^ ToolTip,  
& System.int WhichPane  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

BitmapFile

Fully qualified path to the bitmap file that you want to use for the tab

Class

Class ID for the ActiveX control

LicKey

License key for the ActiveX control

ToolTip

Text for the ToolTip

WhichPane

Pane to use as defined in [swFeatMgrPane_e](#)

Return Value

Pointer to the new [tab](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateFeatureMgrControl3](#).

Remarks

This method lets you add a tab for a registered ActiveX control to the FeatureManager design tree. A user can click the tab to activate the Active control.

To add a tab to the FeatureManager design tree, specify `swFeatMgrPane_e.FeatMgrPaneBottom` for `WhichPane`. To add a tab to a FeatureManager design tree that has been split, specify `swFeatMgrPane_e.swFeatMgrPaneTop` and `swFeatMgrPane_e.swFeatMgrPaneBottom` respectively, for `WhichPane`. See [IModelDoc2::FeatureManagerSplitterPosition](#) for details on splitting and positioning the split panel bar on a spl FeatureManager design tree.

To delete a tab created by this method, use [IFeatMgrView::DeleteView](#).

Class can be either the name of the registered control (ProgID) or its class ID (CLSID), for example, "MSCAL.calendar" or "{8E27C92B-1264-101C-8A2F-040224009C02}". You must obtain these strings by searching for the registered ActiveX control in the registry editor. The ActiveX control library names displayed in the Object Browser may not be the same as the ActiveX control names in the registry. Do not use the Object Browser to specify Class.

See also [Keystrokes and Accelerator Keys in ActiveX Modeless Dialogs and PropertyManager Pages](#).

See Also

[IModelViewManager Interface](#)

[IModelViewManager Members](#)

[IModelViewManager::CreateFeatureMgrView2 Method](#)

[IModelViewManager::AddControl3 Method](#)

Availability

SOLIDWORKS 2005 SP1, Revision Number 13.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateFeatureMgrControl4 Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateFeatureMgrControl4 Method (IModelViewManager)

Creates a new FeatureManager design tree view containing the specified ActiveX control with a tab that displays the specified scaleable icon.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrControl4( _  
    ByVal BitmapFileNames As System.Object, _  
    ByVal Class As System.String, _
```

```

    ByVal LicKey As System.String, _
    ByVal ToolTip As System.String, _
    ByVal WhichPane As System.Integer _
) As FeatMgrView

```

Visual Basic (Usage)



```

Dim instance As IModelViewManager
Dim BitMapFileNames As System.Object
Dim Class As System.String
Dim LicKey As System.String
Dim ToolTip As System.String
Dim WhichPane As System.Integer
Dim value As FeatMgrView

value = instance.CreateFeatureMgrControl4(BitMapFileNames, Class, LicKey, ToolTip, WhichPane)

```

C#

```

FeatMgrView CreateFeatureMgrControl4(
    System.object BitMapFileNames,
    System.string Class,
    System.string LicKey,
    System.string ToolTip,
    System.int WhichPane
)

```

C++/CLI

```

FeatMgrView^ CreateFeatureMgrControl4(
    & System.Object^ BitMapFileNames,
    & System.String^ Class,
    & System.String^ LicKey,
    & System.String^ ToolTip,
    & System.int WhichPane
)

```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

BitMapFileNames

Array of fully qualified paths to three bitmap files, one for each size (small, medium, and large), to be used for the tab icon in different screen resolutions

Class

CLSID or ProgID for the ActiveX control (see **Remarks**)

LicKey

License key for the ActiveX control; empty string if unknown

ToolTip

Text to display when hovering over the tab icon

WhichPane

Pane where to add the tab as defined in [swFeatMgrPane_e](#) (see **Remarks**)

Return Value

Pointer to the new [tab](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateFeatureMgrControl4](#).

Example

[Add ActiveX Tab to FeatureManager Design Tree \(VBA\)](#)
[Add ActiveX Tab to FeatureManager Design Tree \(VB.NET\)](#)
[Add ActiveX Tab to FeatureManager Design Tree \(C#\)](#)

Remarks

To:

- Add a tab to the FeatureManager design tree, specify WhichPane with swFeatMgrPane_e.FeatMgrPaneBottom.
- Add a tab to a split FeatureManager design tree, specify WhichPane with either swFeatMgrPane_e.swFeatMgrPaneTop or swFeatMgrPane_e.swFeatMgrPaneBottom. See [IModelDoc2::FeatureManagerSplitterPosition](#) for details on splitting and positioning the split panel bar in the FeatureManager design tree.
- Delete the tab created by this method, use [IFeatMgrView::DeleteView](#).

Specify Class with either the ProgID or the CLSID of the registered ActiveX control. You can obtain these strings by searching for the registered ActiveX control in the registry editor.

For example, **RichEditCtrl.ocx** resides in **c:\Program files\SOLIDWORKS Corp\SOLIDWORKS\slidUtils**. It is registered during the SOLIDWORKS installation. When you search for **RichEditCtrl.ocx** in the registry, you find ProgID = GTSWRICHEDITCTRL.RichEditCtrlCtrl.1 and CLSID = {7632C33C-A935-48FF-84D9-F0F173EF543D}. Use either the registry's ActiveX ProgID or CLSID to specify Class. The ActiveX control library names displayed in the Object Browser may not be the same as the ActiveX control names in the registry. Do not use the Object Browser to specify Class.

See also [Keystrokes and Accelerator Keys in ActiveX Modeless Dialogs and PropertyManager Pages](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::CreateFeatureMgrView2 Method \(\)](#)
[IModelViewManager::AddControl3 Method \(\)](#)

Availability

SOLIDWORKS 2020 FCS, Revision Number 28.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateFeatureMgrView Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateFeatureMgrView Method (IModelViewManager)

Obsolete. Superseded by [IModelViewManager::CreateFeatureMgrView2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrView( _
    ByVal PPicture As System.Object, _
    ByVal ToolTip As System.String, _
    ByVal WhichPane As System.Integer _
) As FeatMgrView
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim PPicture As System.Object
Dim ToolTip As System.String
Dim WhichPane As System.Integer
Dim value As FeatMgrView

value = instance.CreateFeatureMgrView(PPicture, ToolTip, WhichPane)
```

C#

```
FeatMgrView CreateFeatureMgrView(
    System.object PPicture,
    System.string ToolTip,
    System.int WhichPane
)
```

C++/CLI

```
FeatMgrView^ CreateFeatureMgrView(
    & System.Object^ PPicture,
    & System.String^ ToolTip,
    & System.int WhichPane
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PPicture
ToolTip
WhichPane

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateFeatureMgrView](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateFeatureMgrView2 Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateFeatureMgrView2 Method (IModelViewManager)

Creates a new view (tab) in this FeatureManager design tree.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrView2( _  
    ByVal BitMapFile As System.String, _  
    ByVal ToolTip As System.String, _  
    ByVal WhichPane As System.Integer _  
) As FeatMgrView
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim BitMapFile As System.String  
Dim ToolTip As System.String  
Dim WhichPane As System.Integer  
Dim value As FeatMgrView  
  
value = instance.CreateFeatureMgrView2(BitMapFile, ToolTip, WhichPane)
```

C#

```
FeatMgrView CreateFeatureMgrView2(  
    System.string BitMapFile,  
    System.string ToolTip,  
    System.int WhichPane  
)
```

C++/CLI

```
FeatMgrView^ CreateFeatureMgrView2(  
& System.String^ BitMapFile,  
& System.String^ ToolTip,  
& System.int WhichPane  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

BitMapFile
Bitmap file that you want to use for the tab

ToolTip
Text for the ToolTip

WhichPane
Pane to use as defined in [swFeatMgrPane_e](#)

Return Value

Pointer to the new [tab](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateFeatureMgrView2](#).

Remarks

This method provides the ability to place your newly created Feature Manager tab on either the top or bottom pane. The pane may or may not be visible. However, the tab is added to the specified pane.

Under certain conditions, for example while the **Surface, Extend** command is active in the user interface, SOLIDWORKS locks the bottom pane and does not allow the activation of any other tab. If your application needs the ability to activate your new tab at all times, consider adding it either to the top pane or to both panes. If you add it to the top pane only, it may not be apparent to the user until the top pane is made visible.

If you receive a non-NULL return value, you can use [IFeatMgrView::GetFeatMgrViewWnd](#) or [IFeatureMgrView::GetFeatMgrViewWndx64](#) to get the new view handle. Because the view created is empty, you can use the new view handle in combination with standard MFC calls to draw, as desired, into the view.

The FeatureManager design tree view added to this document is not persistent. In other words, the FeatureManager design tree view is not stored with this document and must be recreated upon reloading the document.

This method automatically sets up to receive [FeatMgrView ActivateNotify](#) and [DeactivateNotify](#) events. On the appropriate notification, you can call [IModelDoc2::DeleteFeatureMgrView](#) or [IModelDocExtension::DeleteFeatureMgrViewx64](#) to clean up and delete your view.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::CreateFeatureMgrControl Method](#)
[IModelViewManager::CreateFeatureMgrControl2 Method](#)
[IModelViewManager::CreateFeatureMgrControl3 Method](#)

Availability

SOLIDWORKS 2003 SP1, Revision Number 11.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateFeatureMgrWindowFromHandle Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : [CreateFeatureMgrWindowFromHandle Method \(IModelViewManager\)](#)

Obsolete. Superseded by [IModelViewManager::CreateFeatureMgrWindowFromHandlex64](#).

This method is unsafe to use with 64-bit SOLIDWORKS, i.e. all versions since SOLIDWORKS 2016.

The 32-bit integer returned may be too small to contain the 64-bit window handle/pointer, and will be truncated silently. A critical exception will occur sometime later, when the truncated handle/pointer is used.

Creates a new view in the FeatureManager design tree using the specified .NET tab control.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrWindowFromHandle( _  
    ByVal BitMapFile As System.String, _  
    ByVal WindowHandle As System.Integer, _  
    ByVal ToolTip As System.String, _  
    ByVal WhichPane As System.Integer _  
) As FeatMgrView
```

Visual Basic (Usage)

```
Dim instance As IModelViewManager  
Dim BitMapFile As System.String  
Dim WindowHandle As System.Integer  
Dim ToolTip As System.String  
Dim WhichPane As System.Integer  
Dim value As FeatMgrView
```



```
value = instance.CreateFeatureMgrWindowFromHandle(BitmapFile, WindowHandle, ToolTip, WhichPane)
```

C#

```
FeatMgrView CreateFeatureMgrWindowFromHandle(  
    System.string BitMapFile,  
    System.int WindowHandle,  
    System.string ToolTip,  
    System.int WhichPane  
)
```

C++/CLI

```
FeatMgrView^ CreateFeatureMgrWindowFromHandle(  
& System.String^ BitMapFile,  
& System.int WindowHandle,  
& System.String^ ToolTip,  
& System.int WhichPane  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

BitMapFile

Fully qualified path to the bitmap file that you want to use for the control

WindowHandle

Handle of the .NET tab control

ToolTip

Text for the ToolTip

WhichPane

Pane to use as defined in [swFeatMgrPane_e](#)

Return Value

[IFeatMgrView](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateFeatureMgrWindowFromHandle](#).

Remarks

All applications are required to be compatible with SOLIDWORKS x64. You must replace all calls to 32-bit only APIs with calls to their 64-bit safe counterparts.

See [Eliminating 32-bit only API use](#) for more information.

See Also

[IModelViewManager Interface](#)

[IModelViewManager Members](#)

[IModelViewManager::DisplayWindowFromHandle Method](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateFeatureMgrWindowFromHandlex64 Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateFeatureMgrWindowFromHandlex64 Method (IModelViewManager)

On 64-bit machines, creates a new view in the FeatureManager design tree using the specified .NET tab control.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateFeatureMgrWindowFromHandlex64( _  
    ByVal BitMapFile As System.String, _
```

```
ByVal WindowHandle As System.Long, _  
ByVal ToolTip As System.String, _  
ByVal WhichPane As System.Integer _  
) As FeatMgrView
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim BitMapFile As System.String  
Dim WindowHandle As System.Long  
Dim ToolTip As System.String  
Dim WhichPane As System.Integer  
Dim value As FeatMgrView
```

```
value = instance.CreateFeatureMgrWindowFromHandlex64(BitMapFile, WindowHandle, ToolTip, WhichPane)
```

C#

```
FeatMgrView CreateFeatureMgrWindowFromHandlex64(  
    System.string BitMapFile,  
    System.long WindowHandle,  
    System.string ToolTip,  
    System.int WhichPane  
)
```

C++/CLI

```
FeatMgrView^ CreateFeatureMgrWindowFromHandlex64(  
& System.String^ BitMapFile,  
& System.int64 WindowHandle,  
& System.String^ ToolTip,  
& System.int WhichPane  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

BitMapFile

Fully qualified path to the bitmap file that you want to use for the control

WindowHandle

Handle of the .NET tab control

ToolTip

Text for the ToolTip

WhichPane

Pane to use as defined in [swFeatMgrPane_e](#)

Return Value

[IFeatMgrView](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateFeatureMgrWindowFromHandlex64](#).

Example

[Add .NET Controls to SOLIDWORKS using an Add-in \(C#\)](#)

[Add .NET Controls to SOLIDWORKS using an Add-in \(VB.NET\)](#)

Remarks

This method is only available through early binding and with 64-bit versions of the SOLIDWORKS Design software.

See Also

[IModelViewManager Interface](#)

[IModelViewManager Members](#)

[IModelViewManager::DisplayWindowFromHandlex64 Method](#)

[IModelViewManager::CreateFeatureMgrWindowFromHandle Method](#)

Availability

CreateManipulator Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateManipulator Method (IModelViewManager)

Creates a manipulator, which is similar to the triad in the SOLIDWORKS Design user interface.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateManipulator( _
    ByVal Type As System.Integer, _
    ByVal PHandler As System.Object _
) As Manipulator
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim Type As System.Integer
Dim PHandler As System.Object
Dim value As Manipulator

value = instance.CreateManipulator(Type, PHandler)
```

C#

```
Manipulator CreateManipulator(
    System.int Type,
    System.object PHandler
)
```

C++/CLI

```
Manipulator^ CreateManipulator(
    & System.int Type,
    & System.Object^ PHandler
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Type

Type of manipulator to create as defined by [swManipulatorType_e](#)

PHandler

Manipulator handler object

Return Value

[Manipulator](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateManipulator](#).

Example

[Create Triad Manipulator \(VBA\)](#)
[Create Triad Manipulator \(VB.NET\)](#)
[Create Triad Manipulator \(C#\)](#)
[Create Drag Arrow Manipulator \(C#\)](#)
[Create Drag Arrow Manipulator \(VB.NET\)](#)
[Create Drag Arrow Manipulator \(VBA\)](#)

Remarks

If you move a manipulator far away from the model and then zoom-to-fit the model, the manipulator is not seen because it is not included in the clipping region.

See [Manipulators](#) for details.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

CreateSectionView Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateSectionView Method (IModelViewManager)

Creates a section view in parts and assemblies.

.NET Syntax

Visual Basic (Declaration)

```
Function CreateSectionView( _  
    ByVal SectionData As SectionViewData _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim SectionData As SectionViewData  
Dim value As System.Boolean  
  
value = instance.CreateSectionView(SectionData)
```

C#

```
System.bool CreateSectionView(  
    SectionViewData SectionData  
)
```

C++/CLI

```
System.bool CreateSectionView(  
& SectionViewData^ SectionData  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

SectionData
[Section view data](#)

Return Value

True if the section view is created, false if not ([see Remarks](#))

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateSectionView](#).

Example

[Create Section View in Model \(C#\)](#)
[Create Section View in Model \(VB.NET\)](#)
[Create Section View in Model \(VBA\)](#)

Remarks

To create a section view in a part or assembly:

1. Use [IModelViewManager::CreateSectionViewData](#) to create the SectionViewData object.
2. Set the properties of [ISectionViewData](#).
3. Use [IModelViewManager::CreateSectionView](#) to create the section view. This method only returns whether it successfully created the section view. It does not return whether it created valid section bodies. Set [ISectionViewData::Redraw](#) to true to have [IModelViewManager::CreateSectionView](#) validate and return a status for section bodies instead of section views.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetSectionViewData Method](#)
[IModelViewManager::RemoveSectionView Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

CreateSectionViewData Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : CreateSectionViewData Method (IModelViewManager)

Creates an empty [ISectionViewData](#) object whose properties you set before [creating a section view in a part or an assembly](#).

.NET Syntax

Visual Basic (Declaration)

```
Function CreateSectionViewData() As SectionViewData
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim value As SectionViewData  
  
value = instance.CreateSectionViewData()
```

C#

```
SectionViewData CreateSectionViewData()
```

C++/CLI

```
SectionViewData^ CreateSectionViewData();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Section view data](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::CreateSectionViewData](#).

Example

[Create Section View in Model \(C#\)](#)
[Create Section View in Model \(VB.NET\)](#)
[Create Section View in Model \(VBA\)](#)

Remarks

To create a section view in a part or assembly:

1. Use this method to create the SectionViewData object.
2. Set the properties of [ISectionViewData](#).
3. Use [IModelViewManager::CreateSectionView](#) to create the section view. [IModelViewManager::CreateSectionView](#) only returns whether it successfully created the section view. It does not return whether it created valid section bodies. Set [ISectionViewData::Redraw](#) to true to have [IModelViewManager::CreateSectionView](#) validate and return a status for section bodies.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetSectionViewData Method](#)
[IModelViewManager::RemoveSectionView Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

DeleteControlTab Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : DeleteControlTab Method (IModelViewManager)

Deletes the specified control tab.

.NET Syntax

Visual Basic (Declaration)

```
Function DeleteControlTab( _  
    ByVal Name As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim Name As System.String  
Dim value As System.Boolean  
  
value = instance.DeleteControlTab(Name)
```

C#

```
System.bool DeleteControlTab(  
    System.string Name  
)
```

C++/CLI

```
System.bool DeleteControlTab(  
& System.String^ Name  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name

Name of control tab

Return Value

True if control tab is deleted, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::DeleteControlTab](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::ActivateControlTab Method](#)
[IModelViewManager::ActivateModelTab Method](#)
[IModelViewManager::GetControl Method](#)
[IModelViewManager::!GetControl Method](#)
[IModelViewManager::IsControlTabActive Method](#)
[IModelViewManager::IsModelTabActive Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

DeleteSnapShot Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : DeleteSnapShot Method (IModelViewManager)

Deletes the specified snapshot from an assembly.

.NET Syntax

Visual Basic (Declaration)

```
Function DeleteSnapShot( _  
    ByVal SnapShotName As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim SnapshotName As System.String  
Dim value As System.Boolean  
  
value = instance.DeleteSnapShot(SnapShotName)
```

C#

```
System.bool DeleteSnapShot(  
    System.string SnapShotName  
)
```

C++/CLI

```
System.bool DeleteSnapShot(  
& System.String^ SnapShotName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

SnapShotName
Name of snapshot to delete

Return Value

True if successful, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::DeleteSnapShot](#).

Remarks

This method is valid only for assemblies.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::AddSnapShot Method](#)
[IModelViewManager::GetSnapShot Method](#)
[IModelViewManager::GetSnapShots Method](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

DisplayWindowFromHandle Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : DisplayWindowFromHandle Method (IModelViewManager)

Obsolete. Superseded by [IModelViewManager::DisplayWindowFromHandlex64](#).

This method is unsafe to use with 64-bit SOLIDWORKS, i.e. all versions since SOLIDWORKS 2016.

The 32-bit integer returned may be too small to contain the 64-bit window handle/pointer, and will be truncated silently. A critical exception will occur sometime later, when the truncated handle/pointer is used.

Displays a .NET control in this model view.

.NET Syntax

Visual Basic (Declaration)

```
Function DisplayWindowFromHandle( _
    ByVal Name As System.String, _
    ByVal WindowHandle As System.Integer, _
    ByVal SplitWindow As System.Boolean _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim Name As System.String
Dim WindowHandle As System.Integer
Dim SplitWindow As System.Boolean
Dim value As System.Boolean

value = instance.DisplayWindowFromHandle(Name, WindowHandle, SplitWindow)
```

C#

```
System.bool DisplayWindowFromHandle(
    System.string Name,
    System.int WindowHandle,
    System.bool SplitWindow
)
```

C++/CLI

```
System.bool DisplayWindowFromHandle(
    & System.String^ Name,
    & System.int WindowHandle,
    & System.bool SplitWindow
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name
User-defined label that appears on the tab

WindowHandle
Handle of the .NET control

SplitWindow
True to add a splitter window, false to not

Return Value

True if .NET control is created, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::DisplayWindowFromHandle](#).

Remarks

All applications are required to be compatible with SOLIDWORKS x64. You must replace all calls to 32-bit only APIs with calls to their 64-bit safe counterparts.

See [Eliminating 32-bit only API use](#) for more information.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::CreateFeatureMgrWindowFromHandle Method](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

DisplayWindowFromHandlex64 Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : DisplayWindowFromHandlex64 Method (IModelViewManager)

Displays a .NET control in this model view on 64-bit machines.

.NET Syntax

Visual Basic (Declaration)

```
Function DisplayWindowFromHandlex64( _  
    ByVal Name As System.String, _  
    ByVal WindowHandle As System.Long, _  
    ByVal SplitWindow As System.Boolean _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim Name As System.String  
Dim WindowHandle As System.Long  
Dim SplitWindow As System.Boolean  
Dim value As System.Boolean  
  
value = instance.DisplayWindowFromHandlex64(Name, WindowHandle, SplitWindow)
```

C#

```
System.bool DisplayWindowFromHandlex64(  
    System.string Name,  
    System.long WindowHandle,  
    System.bool SplitWindow  
)
```

C++/CLI

```
System.bool DisplayWindowFromHandlex64(  
& System.String^ Name,  
& System.int64 WindowHandle,  
& System.bool SplitWindow  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name
User-defined label that appears on the tab
WindowHandle
64-bit handle of the .NET control
SplitWindow
True to add a splitter window, false to not

Return Value

True if .NET control is created, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::DisplayWindowFromHandle64](#).

Example

[Add .NET Controls to SOLIDWORKS using an Add-in \(C#\)](#)
[Add .NET Controls to SOLIDWORKS using an Add-in \(VB.NET\)](#)

Remarks

This method is only available through early binding and with 64-bit versions of the SOLIDWORKS software.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::CreateFeatureMgrWindowFromHandle64 Method](#)

Availability

SOLIDWORKS 2011 FCS, Revision Number 19.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Document Property (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : Document Property (IModelViewManager)

Gets the document to which this model view belongs.

.NET Syntax

Visual Basic (Declaration)

ReadOnly Property Document As ModelDoc2

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim value As ModelDoc2
```

```
value = instance.Document
```

C#

```
ModelDoc2 Document {get;}
```

C++/CLI

```
property ModelDoc2^ Document {  
    ModelDoc2^ get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

[Document](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::Document](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)

Availability

FeatureManagerTabsVisible Property (IModelViewManager)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : FeatureManagerTabsVisible Property (IModelViewManager)

Gets or sets whether all of the tabs in the Manager Pane are visible.

.NET Syntax

Visual Basic (Declaration)

Property FeatureManagerTabsVisible As System.Boolean

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim value As System.Boolean

instance.FeatureManagerTabsVisible = value

value = instance.FeatureManagerTabsVisible
```

C#

```
System.bool FeatureManagerTabsVisible {get; set;}
```

C++/CLI

```
property System.bool FeatureManagerTabsVisible {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).**Property Value**

True if all of the tabs in the Manager Pane are visible, false if none of the tabs in the Manager Pane are visible

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::FeatureManagerTabsVisible](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelDocExtension::HideFeatureManager Method \(\)](#)
[IModelViewManager::GetConfigurationManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDimXpertManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDisplayManagerTabIndex Method \(\)](#)
[IModelViewManager::GetFeatureManagerTabs Method \(\)](#)
[IModelViewManager::GetFeatureManagerTreeTabIndex Method \(\)](#)
[IModelViewManager::GetPropertyManagerTabIndex Method \(\)](#)
[IModelViewManager::ActiveFeatureManagerTabIndex Property \(\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

GetConfigurationManagerTabIndex Method (IModelViewManager)

[See Also](#) [Example](#)[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetConfigurationManagerTabIndex Method (IModelViewManager)

Gets the index of the ConfigurationManager tab in the Manager Pane.

.NET Syntax

Visual Basic (Declaration)

```
Function GetConfigurationManagerTabIndex() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim value As System.Integer

value = instance.GetConfigurationManagerTabIndex()
```

C#

```
System.int GetConfigurationManagerTabIndex()
```

C++/CLI

```
System.int GetConfigurationManagerTabIndex();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

2 if in the Manager Pane; -1 if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetConfigurationManagerTabIndex](#).

Example

[Change Active Tab in Manager Pane \(C#\)](#)
[Change Active Tab in Manager Pane \(VB.NET\)](#)
[Change Active Tab in Manager Pane \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetDimXpertManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDisplayManagerTabIndex Method \(\)](#)
[IModelViewManager::GetFeatureManagerTabs Method \(\)](#)
[IModelViewManager::GetFeatureManagerTreeTabIndex Method \(\)](#)
[IModelViewManager::GetPropertyManagerTabIndex Method \(\)](#)
[IModelViewManager::ActiveFeatureManagerTabIndex Property \(\)](#)
[IModelViewManager::FeatureManagerTabsVisible Property \(\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetControl Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetControl Method (IModelViewManager)

Gets the control associated with this model view.

.NET Syntax

Visual Basic (Declaration)

```
Function GetControl( _  
    ByVal Name As System.String _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim Name As System.String
Dim value As System.Object
```

```
value = instance.GetControl(Name)
```

C#

```
System.object GetControl(  
    System.string Name  
)
```

C++/CLI

```
System.Object^ GetControl(  
& System.String^ Name  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name
Name of the control

Return Value

Control object

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetControl](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::IGetControl Method](#)
[IModelViewManager::ActivateControlTab Method](#)
[IModelViewManager::ActivateModelTab Method](#)
[IModelViewManager::AddControl3 Method](#)
[IModelViewManager::AddControl Method](#)
[IModelViewManager::DeleteControlTab Method](#)
[IModelViewManager::IsControlTabActive Method](#)
[IModelViewManager::IsModelTabActive Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetDimXpertManagerTabIndex Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetDimXpertManagerTabIndex Method (IModelViewManager)

Gets the index of the DimXpertManager tab in the Manager Pane.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDimXpertManagerTabIndex() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim value As System.Integer
```

```
value = instance.GetDimXpertManagerTabIndex()
```

C#

```
System.int GetDimXpertManagerTabIndex()
```

C++/CLI

```
System.int GetDimXpertManagerTabIndex();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

3 if in the Manager Pane; -1 if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetDimXpertManagerTabIndex](#).

Example

[Change Active Tab in Manager Pane \(C#\)](#)
[Change Active Tab in Manager Pane \(VB.NET\)](#)
[Change Active Tab in Manager Pane \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetConfigurationManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDisplayManagerTabIndex Method \(\)](#)
[IModelViewManager::GetFeatureManagerTabs Method \(\)](#)
[IModelViewManager::GetFeatureManagerTreeTabIndex Method \(\)](#)
[IModelViewManager::GetPropertyManagerTabIndex Method \(\)](#)
[IModelViewManager::ActiveFeatureManagerTabIndex Property \(\)](#)
[IModelViewManager::FeatureManagerTabsVisible Property \(\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetDisplayManagerTabIndex Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetDisplayManagerTabIndex Method (IModelViewManager)

Gets the index of the DisplayManager tab in the Manager Pane.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDisplayManagerTabIndex() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim value As System.Integer
```

```
value = instance.GetDisplayManagerTabIndex()
```

C#

```
System.int GetDisplayManagerTabIndex()
```

C++/CLI

```
System.int GetDisplayManagerTabIndex();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

4 if in Manager Pane; -1 if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetDisplayManagerTabIndex](#).

Example

[Change Active Tab in Manager Pane \(C#\)](#)
[Change Active Tab in Manager Pane \(VB.NET\)](#)
[Change Active Tab in Manager Pane \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetConfigurationManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDimXpertManagerTabIndex Method \(\)](#)
[IModelViewManager::GetFeatureManagerTabs Method \(\)](#)
[IModelViewManager::GetFeatureManagerTreeTabIndex Method \(\)](#)
[IModelViewManager::GetPropertyManagerTabIndex Method \(\)](#)
[IModelViewManager::ActiveFeatureManagerTabIndex Property \(\)](#)
[IModelViewManager::FeatureManagerTabsVisible Property \(\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetFeatureManagerTabs Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetFeatureManagerTabs Method (IModelViewManager)

Gets the tabs from right to left in the Manager Pane.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFeatureManagerTabs() As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim value As System.Object  
  
value = instance.GetFeatureManagerTabs()
```

C#

```
System.object GetFeatureManagerTabs()
```

C++/CLI

```
System.Object^ GetFeatureManagerTabs();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Tabs from right to left in the Manager Pane

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetFeatureManagerTabs](#).

Example

[Change Active Tab in Manager Pane \(C#\)](#)
[Change Active Tab in Manager Pane \(VB.NET\)](#)
[Change Active Tab in Manager Pane \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetConfigurationManagerTabIndex Method \(\)](#)

[IModelViewManager::GetDimXpertManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDisplayManagerTabIndex Method \(\)](#)
[IModelViewManager::GetFeatureManagerTreeTabIndex Method \(\)](#)
[IModelViewManager::GetPropertyManagerTabIndex Method \(\)](#)
[IModelViewManager::ActiveFeatureManagerTabIndex Property \(\)](#)
[IModelViewManager::FeatureManagerTabsVisible Property \(\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetFeatureManagerTreeTabIndex Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetFeatureManagerTreeTabIndex Method (IModelViewManager)

Gets the index of the FeatureManager design tree tab in the Manager Pane.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFeatureManagerTreeTabIndex() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim value As System.Integer
```

```
value = instance.GetFeatureManagerTreeTabIndex()
```

C#

```
System.int GetFeatureManagerTreeTabIndex()
```

C++/CLI

```
System.int GetFeatureManagerTreeTabIndex();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

0

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetFeatureManagerTreeTabIndex](#).

Example

[Change Active Tab in Manager Pane \(C#\)](#)
[Change Active Tab in Manager Pane \(VB.NET\)](#)
[Change Active Tab in Manager Pane \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetConfigurationManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDimXpertManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDisplayManagerTabIndex Method \(\)](#)
[IModelViewManager::GetFeatureManagerTabs Method \(\)](#)
[IModelViewManager::GetPropertyManagerTabIndex Method \(\)](#)
[IModelViewManager::ActiveFeatureManagerTabIndex Property \(\)](#)
[IModelViewManager::FeatureManagerTabsVisible Property \(\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetFeatureMgrViewHWnd Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : [GetFeatureMgrViewHWnd](#) Method (IModelViewManager)

Obsolete. Superseded by [IModelViewManager::GetFeatureMgrViewHWndx64](#).

This method is unsafe to use with 64-bit SOLIDWORKS, i.e. all versions since SOLIDWORKS 2016.

The 32-bit integer returned may be too small to contain the 64-bit window handle/pointer, and will be truncated silently. A critical exception will occur sometime later, when the truncated handle/pointer is used.

Gets the window handle for the specified FeatureManager design tree view.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFeatureMgrViewHWnd( _  
    ByVal FeatMgrViewPane As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim FeatMgrViewPane As System.Integer  
Dim value As System.Integer  
  
value = instance.GetFeatureMgrViewHWnd(FeatMgrViewPane)
```

C#

```
System.int GetFeatureMgrViewHWnd(  
    System.int FeatMgrViewPane  
)
```

C++/CLI

```
System.int GetFeatureMgrViewHWnd(  
& System.int FeatMgrViewPane  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

FeatMgrViewPane

FeatureManager design tree view as defined by [swFeatMgrPane_e](#)

Return Value

Window handle for the specified FeatMgrViewPane

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetFeatureMgrViewHWnd](#).

Remarks

All applications are required to be compatible with SOLIDWORKS x64. You must replace all calls to 32-bit only APIs with calls to their 64-bit safe counterparts.

See [Eliminating 32-bit only API use](#) for more information.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IFeatMgrView Interface](#)

Availability

GetFeatureMgrViewHWndx64 Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetFeatureMgrViewHWndx64 Method (IModelViewManager)

Gets the window handle for the specified FeatureManager design tree view in 64-bit applications.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFeatureMgrViewHWndx64( _  
    ByVal FeatMgrViewPane As System.Integer _  
) As System.Long
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim FeatMgrViewPane As System.Integer  
Dim value As System.Long
```

```
value = instance.GetFeatureMgrViewHWndx64(FeatMgrViewPane)
```

C#

```
System.long GetFeatureMgrViewHWndx64(  
    System.int FeatMgrViewPane  
)
```

C++/CLI

```
System.int64 GetFeatureMgrViewHWndx64(  
&    System.int FeatMgrViewPane  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

FeatMgrViewPane

FeatureManager design tree view as defined by [swFeatMgrPane_e](#)

Return Value

Window handle for the specified FeatMgrViewPane

Remarks

This method is only available through early binding and with 64-bit versions of the SOLIDWORKS Design software.

See Also

[IModelViewManager Interface](#)

[IModelViewManager Members](#)

[IFeatMgrView Interface](#)

[IModelViewManager::GetFeatureMgrViewHWnd Method](#)

Availability

SOLIDWORKS 2006 SP2, Revision Number 14.2

GetPropertyManagerTabIndex Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetPropertyManagerTabIndex Method (IModelViewManager)

Gets the index of the PropertyManager tab in the Manager Pane.

.NET Syntax

Visual Basic (Declaration)

```
Function GetPropertyManagerTabIndex() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim value As System.Integer

value = instance.GetPropertyManagerTabIndex()
```

C#

```
System.int GetPropertyManagerTabIndex()
```

C++/CLI

```
System.int GetPropertyManagerTabIndex();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

1

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetPropertyManagerTabIndex](#).

Example

[Change Active Tab in Manager Pane \(C#\)](#)
[Change Active Tab in Manager Pane \(VB.NET\)](#)
[Change Active Tab in Manager Pane \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetConfigurationManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDimXpertManagerTabIndex Method \(\)](#)
[IModelViewManager::GetDisplayManagerTabIndex Method \(\)](#)
[IModelViewManager::GetFeatureManagerTabs Method \(\)](#)
[IModelViewManager::GetFeatureManagerTreeTabIndex Method \(\)](#)
[IModelViewManager::ActiveFeatureManagerTabIndex Property \(\)](#)
[IModelViewManager::FeatureManagerTabsVisible Property \(\)](#)

Availability

SOLIDWORKS 2017 FCS, Revision Number 25.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSectionViewData Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetSectionViewData Method (IModelViewManager)

Gets access to the data of the specified section view.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSectionViewData( _
    ByVal ViewName As System.String _
) As SectionViewData
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim ViewName As System.String
Dim value As SectionViewData
```

```
value = instance.GetSectionViewData(ViewName)
```

C#

```
SectionViewData GetSectionViewData(  
    System.string ViewName  
)
```

C++/CLI

```
SectionViewData^ GetSectionViewData(  
& System.String^ ViewName  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ViewName

Name of the section view or an empty string for the active section view

Return Value

[Section view data](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetSectionViewData](#).

Example

[Get Section View Data \(C#\)](#)
[Get Section View Data \(VB.NET\)](#)
[Get Section View Data \(VBA\)](#)

Remarks

If the specified string refers to a non-existent section view or a view that is not sectioned, then this method returns Nothing or null.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::CreateSectionView Method](#)
[IModelViewManager::CreateSectionViewData Method](#)
[IModelViewManager::RemoveSectionView Method](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSnapShot Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetSnapShot Method (IModelViewManager)

Gets the specified snapshot of an assembly.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSnapShot( _  
    ByVal SnapshotName As System.String _  
) As Snapshot
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim SnapshotName As System.String
Dim value As Snapshot

value = instance.GetSnapshot(SnapshotName)
```

C#

```
Snapshot GetSnapshot(
    System.string SnapshotName
)
```

C++/CLI

```
Snapshot^ GetSnapshot(
    & System.String^ SnapshotName
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

SnapshotName
Name of snapshot to get

Return Value

[ISnapshot](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetSnapshot](#).

Remarks

This method is valid only for assemblies.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::AddSnapshot Method](#)
[IModelViewManager::DeleteSnapshot Method](#)
[IModelViewManager::GetSnapshots Method](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSnapshots Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : GetSnapshots Method (IModelViewManager)

Gets the snapshots of an assembly.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSnapshots() As System.Object
```

Visual Basic (Usage)

```
Dim instance As IModelViewManager
Dim value As System.Object

value = instance.GetSnapshots()
```



C#

```
System.object GetSnapShots()
```

C++/CLI

```
System.Object^ GetSnapShots();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Array of [ISnapShots](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::GetSnapShots](#).

Example

[Open Assembly in Large Design Review Mode \(VBA\)](#)
[Open Assembly in Large Design Review Mode \(VB.NET\)](#)
[Open Assembly in Large Design Review Mode \(C#\)](#)

Remarks

This method is valid only for assemblies.

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::AddSnapShot Method](#)
[IModelViewManager::DeleteSnapShot Method](#)
[IModelViewManager::GetSnapShot Method](#)

Availability

SOLIDWORKS 2012 FCS, Revision Number 20.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetControl Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : IGetControl Method (IModelViewManager)

Gets the control associated with this model view.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetControl( _  
    ByVal Name As System.String _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim Name As System.String  
Dim value As System.Object  
  
value = instance.IGetControl(Name)
```

C#

```
System.object IGetControl(  
    System.string Name  
)
```

C++/CLI

```
System.Object^ IGetControl(  
& System.String^ Name  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name
Name of the control

Return Value

Control object

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::IGetControl](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetControl Method](#)
[IModelViewManager::ActivateControlTab Method](#)
[IModelViewManager::ActivateModelTab Method](#)
[IModelViewManager::AddControl Method](#)
[IModelViewManager::AddControl3 Method](#)
[IModelViewManager::DeleteControlTab Method](#)
[IModelViewManager::IsControlTabActive Method](#)
[IModelViewManager::IsModelTabActive Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IsControlTabActive Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : IsControlTabActive Method (IModelViewManager)

Gets whether the specified control is active.

.NET Syntax

Visual Basic (Declaration)

```
Function IsControlTabActive( _  
    ByVal Name As System.String _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim Name As System.String  
Dim value As System.Boolean  
  
value = instance.IsControlTabActive(Name)
```

C#

```
System.bool IsControlTabActive(  
    System.string Name  
)
```

C++/CLI

```
System.bool IsControlTabActive(  
& System.String^ Name  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Name
Name of control tab

Return Value

True if control tab is active, false if not

 Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::IsControlTabActive](#).

 Example

[Add ActiveX Tabs to Model View \(C#\)](#)
[Add Active Tabs to Model View \(VB.NET\)](#)
[Add ActiveX Tabs to Model View \(VBA\)](#)

 See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::GetControl Method](#)
[IModelViewManager::ActivateControlTab Method](#)
[IModelViewManager::ActivateModelTab Method](#)
[IModelViewManager::AddControl Method](#)
[IModelViewManager::AddControl3 Method](#)
[IModelViewManager::DeleteControlTab Method](#)
[IModelViewManager::IsModelTabActive Method](#)
[IModelViewManager::GetControl Method](#)

 Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IsModelTabActive Method (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : IsModelTabActive Method (IModelViewManager)

Gets whether the control on this model view is active.

 .NET Syntax

Visual Basic (Declaration)

```
Function IsModelTabActive() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
Dim value As System.Boolean  
  
value = instance.IsModelTabActive()
```

C#

```
System.bool IsModelTabActive()
```

C++/CLI

```
System.bool IsModelTabActive();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if the control tab on this model view is active, false if not

 Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::IsModelTabActive](#).

Example

[Add ActiveX Tabs to Model View \(C#\)](#)
[Add ActiveX Tabs to Model View \(VB.NET\)](#)
[Add ActiveX Tabs to Model View \(VBA\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::ActivateControlTab Method](#)
[IModelViewManager::ActivateModelTab Method](#)
[IModelViewManager::DeleteControlTab Method](#)
[IModelViewManager::GetControl Method](#)
[IModelViewManager::IGetControl Method](#)
[IModelViewManager::IsControlTabActive Method](#)

Availability

SOLIDWORKS 2003 FCS, Revision Number 11.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

LinkedViews Property (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : LinkedViews Property (IModelViewManager)

Gets or sets whether linking of viewports is enabled in this document.

.NET Syntax

Visual Basic (Declaration)

Property LinkedViews As System.Boolean

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim value As System.Boolean
```

```
instance.LinkedViews = value
```

```
value = instance.LinkedViews
```

C#

```
System.bool LinkedViews {get; set;}
```

C++/CLI

```
property System.bool LinkedViews {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True if linking of viewports is enabled in this document, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::LinkedViews](#).

Example

[Set Viewports \(VB.NET\)](#)
[Set Viewports \(VBA\)](#)
[Set Viewports \(C#\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelView::Linked Property](#)
[IModelViewManager::ViewportDisplay Property](#)

Availability

SOLIDWORKS 2006 FCS, Revision Number 14.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

RemoveSectionView Method (IModelViewManager)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : RemoveSectionView Method (IModelViewManager)

Removes a section view from a part and assembly.

.NET Syntax

Visual Basic (Declaration)

```
Function RemoveSectionView() As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IModelViewManager
Dim value As System.Boolean

value = instance.RemoveSectionView()
```

C#

```
System.bool RemoveSectionView()
```

C++/CLI

```
System.bool RemoveSectionView();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

True if the section view is removed, false if not

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager.RemoveSectionView](#).

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::CreateSectionView Method](#)
[IModelViewManager::CreateSectionViewData Method](#)
[IModelViewManager::GetSectionViewData Method](#)
[ISectionViewData Interface](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ViewportDisplay Property (IModelViewManager)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IModelViewManager Interface](#) : ViewportDisplay Property (IModelViewManager)

Sets the model's viewport arrangement.

.NET Syntax

Visual Basic (Declaration)

WriteOnly Property ViewportDisplay As System.Integer

Visual Basic (Usage)



```
Dim instance As IModelViewManager  
instance.ViewportDisplay = value
```

C#

```
System.int ViewportDisplay {set;}
```

C++/CLI

```
property System.int ViewportDisplay {  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Viewport arrangement as defined by [swViewportDisplay_e](#)

Visual Basic for Applications (VBA) Syntax

See [ModelViewManager::ViewportDisplay](#).

Example

[Set Viewports \(VB.NET\)](#)
[Set Viewports \(VBA\)](#)
[Set Viewports \(C#\)](#)

See Also

[IModelViewManager Interface](#)
[IModelViewManager Members](#)
[IModelViewManager::LinkedViews Property](#)
[IModelView::Linked Property](#)

Availability

SOLIDWORKS 2010 FCS, Revision Number 18.0