

SOLIDWORKS API (.NET VBA C#) — Reference (245/337): ISaveTo3DExperienceOptions ISaveTo3DExperienceOptions

SOLIDWORKS API Documentation (converted from CHM)

ISafeArrayUtility (Type)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISafeArrayUtility Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISafeArrayUtility Interface

Access the ISafeArrayUtility interface, which can:

- get an unpacked array of native SOLIDWORKS Dispatch-based objects of the same data type and return a packed Variant SafeArray to use in methods that requires passing a packed Variant SafeArray.
- get a packed Variant SafeArray and return an unpacked array of native SOLIDWORKS Dispatch-based objects of the same data type.
- get a Variant SafeArray and return the number of SafeArray objects in the Variant SafeArray and their data type.
- get and put a value in a Variant SafeArray of the same data type.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISafeArrayUtility
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
```

C#

```
public interface ISafeArrayUtility
```

C++/CLI

```
public interface class ISafeArrayUtility
```

Example

[Get Names of Configurations Using Variant \(C++\)](#)
[Get Object's Persistent Reference ID \(C++\)](#)
[Get Spline Points \(C++\)](#)
[Get Scale Factor of Each Model View \(C++\)](#)

Remarks

The ISafeArrayUtility interface replaces the SOLIDWORKS SafeArray template class, which you might have used in earlier versions of SOLIDWORKS to instantiate SafeArrays for methods requiring Variant arrays in your C++ projects.

This ISafeArrayUtility interface's methods are only compatible with raw pointers and BSTRs; this interface's methods are not compatible with smart pointers (i.e., reference counted) or the Active Template Library (ATL) class CComBSTR. For example:

```
IDispatch* pDisp1; //This works  
IDispatchPtr pDisp2 //This does not work  
CComPtr<IDispatch> pDisp3 //This does not work  
BSTR fileName1 //This works  
CComBSTR fileName2 //This does not work
```

Accessors

[ISldWorks::GetSafeArrayUtility](#)

Access Diagram

[SafeArrayUtility](#)

See Also

[ISafeArrayUtility Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISafeArrayUtility Interface Members

[See Also](#) [Methods](#)

[SolidWorks.Interop.sldworks Namespace](#) : ISafeArrayUtility Interface

The following tables list the members exposed by [ISafeArrayUtility](#).

 Public Methods

Name	Description
 GetBoolean	Gets the specified Boolean value in a Variant SafeArray of Boolean values.
 GetBstr	Gets the specified BSTR in a Variant SafeArray of BSTRs.
 GetByte	Gets the specified byte value in a Variant SafeArray of byte values.
 GetDispatch	Gets the specified Dispatch object in a Variant SafeArray of Dispatch objects.
 GetDouble	Gets the specified double value in a Variant SafeArray of double values.
 GetInfo	Gets the number of elements in a Variant SafeArray and their data type.
 GetLong	Gets the specified long value in a Variant SafeArray of long values.
 GetLongLong	Gets the specified long long value in a Variant SafeArray of long long values.
 GetShort	Gets the specified short value in a Variant SafeArray of short values.
 GetUNKNOWN	Gets the specified UNKNOWN object in a Variant SafeArray of UNKNOWN objects.
 PackVariant	Packs the specified native SOLIDWORKS Dispatch-based objects of the same data type into a Variant SafeArray and returns that packed Variant SafeArray to use in methods requiring passing a packed Variant SafeArray.
 PutBoolean	Adds the specified Boolean value to a Variant SafeArray of Boolean values.
 PutBstr	Adds the specified BSTR to a Variant SafeArray of BSTRs.
 PutByte	Adds the specified byte value to a Variant SafeArray of byte values.
 PutDispatch	Adds the specified Dispatch object to a Variant SafeArray of Dispatch objects.
 PutDouble	Adds the specified double value to a Variant SafeArray of double values.
 PutLong	Adds the specified long value to a Variant SafeArray of long values.
 PutLongLong	Adds the specified long long value to a Variant SafeArray of long long values.
 PutShort	Adds the specified short value to a Variant SafeArray of short values.
 PutUNKNOWN	Adds the specified UNKNOWN object to a Variant SafeArray of UNKNOWN objects.
 UnPackVariant	Unpacks the specified packed Variant SafeArray to native SOLIDWORKS Dispatch-based objects of the same data type.

[Top](#)

 See Also

[ISafeArrayUtility Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISafeArrayUtility Interface Methods

[See Also](#)

[SolidWorks.Interop.sldworks Namespace](#) : ISafeArrayUtility Interface

For a list of all members of this type, see [ISafeArrayUtility members](#).

 Public Methods

Name	Description
 GetBoolean	Gets the specified Boolean value in a Variant SafeArray of Boolean values.
 GetBstr	Gets the specified BSTR in a Variant SafeArray of BSTRs.
 GetByte	Gets the specified byte value in a Variant SafeArray of byte values.
 GetDispatch	Gets the specified Dispatch object in a Variant SafeArray of Dispatch objects.
 GetDouble	Gets the specified double value in a Variant SafeArray of double values.
 GetInfo	Gets the number of elements in a Variant SafeArray and their data type.

	
	GetLong Gets the specified long value in a Variant SafeArray of long values.
	GetLongLong Gets the specified long long value in a Variant SafeArray of long long values.
	GetShort Gets the specified short value in a Variant SafeArray of short values.
	GetUNKNOWN Gets the specified UNKNOWN object in a Variant SafeArray of UNKNOWN objects.
	PackVariant Packs the specified native SOLIDWORKS Dispatch-based objects of the same data type into a Variant SafeArray and returns that packed Variant SafeArray to use in methods requiring passing a packed Variant SafeArray.
	PutBoolean Adds the specified Boolean value to a Variant SafeArray of Boolean values.
	PutBstr Adds the specified BSTR to a Variant SafeArray of BSTRs.
	PutByte Adds the specified byte value to a Variant SafeArray of byte values.
	PutDispatch Adds the specified Dispatch object to a Variant SafeArray of Dispatch objects.
	PutDouble Adds the specified double value to a Variant SafeArray of double values.
	PutLong Adds the specified long value to a Variant SafeArray of long values.
	PutLongLong Adds the specified long long value to a Variant SafeArray of long long values.
	PutShort Adds the specified short value to a Variant SafeArray of short values.
	PutUNKNOWN Adds the specified UNKNOWN object to a Variant SafeArray of UNKNOWN objects.
	UnPackVariant Unpacks the specified packed Variant SafeArray to native SOLIDWORKS Dispatch-based objects of the same data type.

[Top](#)

See Also

[ISafeArrayUtility Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetBoolean Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetBoolean Method (ISafeArrayUtility)

Gets the specified Boolean value in a Variant SafeArray of Boolean values.

.NET Syntax

Visual Basic (Declaration)

```
Function GetBoolean( _  
    ByVal VariantArray As System.Object, _  
    ByVal Index As System.Integer _  
) As System.Boolean
```

Visual Basic (Usage)

```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Index As System.Integer  
Dim value As System.Boolean  
  
value = instance.GetBoolean(VariantArray, Index)
```

C#

```
System.bool GetBoolean(  
    System.object VariantArray,  
    System.int Index  
)
```

C++/CLI

```
System.bool GetBoolean(  
& System.Object^ VariantArray,
```

```
& System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of Boolean values
Index
Index of Boolean value

Return Value

Boolean value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PutBoolean Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetBstr Method (ISafeArrayUtility)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetBstr Method (ISafeArrayUtility)

Gets the specified BSTR in a Variant SafeArray of BSTRs.

.NET Syntax

Visual Basic (Declaration)

```
Function GetBstr( _  
    ByVal VariantArray As System.Object, _  
    ByVal Index As System.Integer _  
) As System.String
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Index As System.Integer  
Dim value As System.String  
  
value = instance.GetBstr(VariantArray, Index)
```

C#

```
System.string GetBstr(  
    System.object VariantArray,  
    System.int Index  
)
```

C++/CLI

```
System.String^ GetBstr(  
& System.Object^ VariantArray,  
& System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of BSTRs
Index
Index of BSTR

Return Value

 Example[Get Names of Configurations Using Variant \(C++\)](#) Remarks See Also[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PutBstr Method \(\)](#) Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetByte Method (ISafeArrayUtility)

[See Also](#) [Example](#)[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetByte Method (ISafeArrayUtility)

Gets the specified byte value in a Variant SafeArray of byte values.

 .NET Syntax

Visual Basic (Declaration)

```
Function GetByte( _
    ByVal VariantArray As System.Object, _
    ByVal Index As System.Integer _
) As System.Byte
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
Dim VariantArray As System.Object
Dim Index As System.Integer
Dim value As System.Byte

value = instance.GetByte(VariantArray, Index)
```

C#

```
System.byte GetByte(
    System.object VariantArray,
    System.int Index
)
```

C++/CLI

```
System.byte GetByte(
    & System.Object^ VariantArray,
    & System.int Index
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of byte values
Index
Index of byte value

Return Value

Byte value

Example

[Get Object's Persistent Reference ID \(C++\)](#)

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PutByte Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetDispatch Method (ISafeArrayUtility)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetDispatch Method (ISafeArrayUtility)

Gets the specified Dispatch object in a Variant SafeArray of Dispatch objects.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDispatch( _  
    ByVal VariantArray As System.Object, _  
    ByVal Index As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Index As System.Integer  
Dim value As System.Object  
  
value = instance.GetDispatch(VariantArray, Index)
```

C#

```
System.object GetDispatch(  
    System.object VariantArray,  
    System.int Index  
)
```

C++/CLI

```
System.Object^ GetDispatch(  
& System.Object^ VariantArray,  
& System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of Dispatch objects
Index
Index of Dispatch object

Return Value

Dispatch object

Example

[Get Scale Factor of Each Model View \(C++\)](#)

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PutDispatch Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetDouble Method (ISafeArrayUtility)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetDouble Method (ISafeArrayUtility)

Gets the specified double value in a Variant SafeArray of double values.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDouble( _  
    ByVal VariantArray As System.Object, _  
    ByVal Index As System.Integer _  
) As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Index As System.Integer  
Dim value As System.Double  
  
value = instance.GetDouble(VariantArray, Index)
```

C#

```
System.double GetDouble(  
    System.object VariantArray,  
    System.int Index  
)
```

C++/CLI

```
System.double GetDouble(  
& System.Object^ VariantArray,  
& System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of double values
Index
Index of double value

Return Value

Double value

Example

[Get Spline Points \(C++\)](#)

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PutDouble Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetInfo Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetInfo Method (ISafeArrayUtility)

Gets the number of elements in a Variant SafeArray and their data type.

.NET Syntax

Visual Basic (Declaration)

```
Sub GetInfo( _  
    ByVal VariantArray As System.Object, _  
    ByRef Count As System.Integer, _  
    ByRef Type As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Count As System.Integer  
Dim Type As System.Integer  
  
instance.GetInfo(VariantArray, Count, Type)
```

C#

```
void GetInfo(  
    System.object VariantArray,  
    out System.int Count,  
    out System.int Type  
)
```

C++/CLI

```
void GetInfo(  
& System.Object^ VariantArray,  
& [Out] System.int Count,  
& [Out] System.int Type  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray
Count
Number of elements in VariantArray
Type
Data type of elements in VariantArray as defined in [swSafeArrayType_e](#)

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PackVariant Method \(\)](#)
[ISafeArrayUtility::UnPackVariant Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetLong Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetLong Method (ISafeArrayUtility)

Gets the specified long value in a Variant SafeArray of long values.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLong( _  
    ByVal VariantArray As System.Object, _  
    ByVal Index As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Index As System.Integer  
Dim value As System.Integer  
  
value = instance.GetLong(VariantArray, Index)
```

C#

```
System.int GetLong(  
    System.object VariantArray,  
    System.int Index  
)
```

C++/CLI

```
System.int GetLong(  
& System.Object^ VariantArray,  
& System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of long values
Index
Index of a long value

Return Value

Long value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PutLong Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetLongLong Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetLongLong Method (ISafeArrayUtility)

Gets the specified long long value in a Variant SafeArray of long long values.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLongLong( _  
    ByVal VariantArray As System.Object, _  
    ByVal Index As System.Integer _  
) As System.Long
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Index As System.Integer  
Dim value As System.Long  
  
value = instance.GetLongLong(VariantArray, Index)
```

C#

```
System.long GetLongLong(  
    System.object VariantArray,  
    System.int Index  
)
```

C++/CLI

```
System.int64 GetLongLong(  
& System.Object^ VariantArray,  
& System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of long long values
Index
Index of long long value

Return Value

Long long value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PutLongLong Method\(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetShort Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetShort Method (ISafeArrayUtility)

Gets the specified short value in a Variant SafeArray of short values.

.NET Syntax

Visual Basic (Declaration)

```
Function GetShort( _  
    ByVal VariantArray As System.Object, _  
    ByVal Index As System.Integer _  
) As System.Short
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
Dim VariantArray As System.Object
Dim Index As System.Integer
Dim value As System.Short

value = instance.GetShort(VariantArray, Index)
```

C#

```
System.short GetShort(
    System.object VariantArray,
    System.int Index
)
```

C++/CLI

```
System.short GetShort(
    & System.Object^ VariantArray,
    & System.int Index
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of short values
Index
Index of short value

Return Value

Short value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PutShort Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetUNKNOWN Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : GetUNKNOWN Method (ISafeArrayUtility)

Gets the specified UNKNOWN object in a Variant SafeArray of UNKNOWN objects.

.NET Syntax

Visual Basic (Declaration)

```
Function GetUNKNOWN( _
    ByVal VariantArray As System.Object, _
    ByVal Index As System.Integer _
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
Dim VariantArray As System.Object
Dim Index As System.Integer
Dim value As System.Object

value = instance.GetUNKNOWN(VariantArray, Index)
```

C#

```
System.object GetUNKNOWN(  
    System.object VariantArray,  
    System.int Index  
)
```

C++/CLI

```
System.Object^ GetUNKNOWN(  
& System.Object^ VariantArray,  
& System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of UNKNOWN objects
Index
Index of UNKNOWN object

Return Value

UNKNOWN object

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::PutUNKNOWN Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PackVariant Method (ISafeArrayUtility)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PackVariant Method (ISafeArrayUtility)

Packs the specified native SOLIDWORKS Dispatch-based objects of the same data type into a Variant SafeArray and returns that packed Variant SafeArray to use in methods requiring passing a packed Variant SafeArray.

.NET Syntax

Visual Basic (Declaration)

```
Sub PackVariant( _  
    ByRef VariantArray As System.Object, _  
    ByVal Count As System.Integer, _  
    ByVal Type As System.Integer, _  
    ByRef Data As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Count As System.Integer  
Dim Type As System.Integer  
Dim Data As System.Integer
```

```
instance.PackVariant(VariantArray, Count, Type, Data)
```

C#

```
void PackVariant(  
    out System.object VariantArray,  
    System.int Count,  
    System.int Type,
```

```
    ref System.int Data
)
```

C++/CLI

```
void PackVariant(
& [Out] System.Object^ VariantArray,
& System.int Count,
& System.int Type,
& System.int% Data
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Packed Variant SafeArray
Count
Number of native SOLIDWORKS Dispatch-based objects of Type
Type
Data type as defined in [swSafeArrayType_e](#)
Data
Native SOLIDWORKS Dispatch-based objects of Type

Example

[Get Scale Factor of Each Model View \(C++\)](#)

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetInfo Method \(\)](#)
[ISafeArrayUtility::UnPackVariant Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

PutBoolean Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PutBoolean Method (ISafeArrayUtility)

Adds the specified Boolean value to a Variant SafeArray of Boolean values.

.NET Syntax

Visual Basic (Declaration)

```
Sub PutBoolean( _
    ByRef VariantArray As System.Object, _
    ByVal Index As System.Integer, _
    ByVal Value As System.Boolean _
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
Dim VariantArray As System.Object
Dim Index As System.Integer
Dim Value As System.Boolean
```

```
instance.PutBoolean(VariantArray, Index, Value)
```

C#

```
void PutBoolean(
    out System.object VariantArray,
    System.int Index,
```

```
        System.bool Value
    )
```

C++/CLI

```
void PutBoolean(
    & [Out] System.Object^ VariantArray,
    & System.int Index,
    & System.bool Value
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of Boolean values
Index
Index of Boolean value
Value
Boolean value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetBoolean Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

PutBstr Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PutBstr Method (ISafeArrayUtility)

Adds the specified BSTR to a Variant SafeArray of BSTRs.

Visual Basic Syntax

Visual Basic (Declaration)

```
Sub PutBstr( _
    ByRef VariantArray As System.Object, _
    ByVal Index As System.Integer, _
    ByVal Value As System.String _
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
Dim VariantArray As System.Object
Dim Index As System.Integer
Dim Value As System.String

instance.PutBstr(VariantArray, Index, Value)
```

C#

```
void PutBstr(
    out System.object VariantArray,
    System.int Index,
    System.string Value
)
```

C++/CLI

```
void PutBstr(
    & [Out] System.Object^ VariantArray,
    & System.int Index,
```

```
& System.String^ Value
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of BSTRs
Index
Index of BSTR
Value
BSTR

Remarks

Be aware that calling `ISafeArrayUtility::PutBstr` within a loop that inserts a BSTR repeatedly declared on the stack results in an array of pointers to the same BSTR; i.e., all elements of the SafeArray are the same, which is most likely not your intention. For example, you should avoid using code similar to the following:

```
for (ULONG ulIndex = 0L; ulIndex < ulSize; ulIndex++)
{
    CString testString;
    testString.Format(_T('Index = %d'), ulIndex);
    CComBSTR bstrTemp = testString;
    HRESULT hres = iSAUtil->PutBstr(&vPacked, ulIndex, bstrTemp);

    bstrArray[ulIndex] = bstrTemp;
}
```

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetBstr Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PutByte Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PutByte Method (ISafeArrayUtility)

Adds the specified byte value to a Variant SafeArray of byte values.

Visual Basic Syntax

Visual Basic (Declaration)

```
Sub PutByte( _
    ByRef VariantArray As System.Object, _
    ByVal Index As System.Integer, _
    ByVal Value As System.Byte _
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
Dim VariantArray As System.Object
Dim Index As System.Integer
Dim Value As System.Byte
```

```
instance.PutByte(VariantArray, Index, Value)
```

C#

```
void PutByte(
    out System.object VariantArray,
    System.int Index,
```

```
        System.byte Value
    )
```

C++/CLI

```
void PutByte(
    & [Out] System.Object^ VariantArray,
    & System.int Index,
    & System.byte Value
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of byte values
Index
Index of byte value
Value
Byte value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetByte Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

PutDispatch Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PutDispatch Method (ISafeArrayUtility)

Adds the specified Dispatch object to a Variant SafeArray of Dispatch objects.

Visual Basic Syntax

Visual Basic (Declaration)

```
Sub PutDispatch( _
    ByRef VariantArray As System.Object, _
    ByVal Index As System.Integer, _
    ByVal Value As System.Object _
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
Dim VariantArray As System.Object
Dim Index As System.Integer
Dim Value As System.Object

instance.PutDispatch(VariantArray, Index, Value)
```

C#

```
void PutDispatch(
    out System.object VariantArray,
    System.int Index,
    System.object Value
)
```

C++/CLI

```
void PutDispatch(
    & [Out] System.Object^ VariantArray,
    & System.int Index,
```

```
& System.Object^ Value
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of Dispatch objects
Index
Index of Dispatch object
Value
Dispatch object

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetDispatch Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

PutDouble Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PutDouble Method (ISafeArrayUtility)

Adds the specified double value to a Variant SafeArray of double values.

.NET Syntax

Visual Basic (Declaration)

```
Sub PutDouble( _
    ByRef VariantArray As System.Object, _
    ByVal Index As System.Integer, _
    ByVal Value As System.Double _
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
Dim VariantArray As System.Object
Dim Index As System.Integer
Dim Value As System.Double

instance.PutDouble(VariantArray, Index, Value)
```

C#

```
void PutDouble(
    out System.object VariantArray,
    System.int Index,
    System.double Value
)
```

C++/CLI

```
void PutDouble(
    & [Out] System.Object^ VariantArray,
    & System.int Index,
    & System.double Value
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of double values
Index
Index of double value

Value
Double value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetDouble Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PutLong Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PutLong Method (ISafeArrayUtility)

Adds the specified long value to a Variant SafeArray of long values.

.NET Syntax

Visual Basic (Declaration)

```
Sub PutLong( _  
    ByRef VariantArray As System.Object, _  
    ByVal Index As System.Integer, _  
    ByVal Value As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Index As System.Integer  
Dim Value As System.Integer  
  
instance.PutLong(VariantArray, Index, Value)
```

C#

```
void PutLong(  
    out System.object VariantArray,  
    System.int Index,  
    System.int Value  
)
```

C++/CLI

```
void PutLong(  
& [Out] System.Object^ VariantArray,  
& System.int Index,  
& System.int Value  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of long values
Index
Index of long value
Value
Long value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetLong Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PutLongLong Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PutLongLong Method (ISafeArrayUtility)

Adds the specified long long value to a Variant SafeArray of long long values.

Visual Basic Syntax

Visual Basic (Declaration)

```
Sub PutLongLong( _  
    ByRef VariantArray As System.Object, _  
    ByVal Index As System.Integer, _  
    ByVal Value As System.Long _  
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Index As System.Integer  
Dim Value As System.Long  
  
instance.PutLongLong(VariantArray, Index, Value)
```

C#

```
void PutLongLong(  
    out System.object VariantArray,  
    System.int Index,  
    System.long Value  
)
```

C++/CLI

```
void PutLongLong(  
& [Out] System.Object^ VariantArray,  
& System.int Index,  
& System.int64 Value  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of long long values
Index
Index of long long value
Value
Long long value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetLongLong Method\(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PutShort Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PutShort Method (ISafeArrayUtility)

Adds the specified short value to a Variant SafeArray of short values.

.NET Syntax

Visual Basic (Declaration)

```
Sub PutShort( _  
    ByRef VariantArray As System.Object, _  
    ByVal Index As System.Integer, _  
    ByVal Value As System.Short _  
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Index As System.Integer  
Dim Value As System.Short  
  
instance.PutShort(VariantArray, Index, Value)
```

C#

```
void PutShort(  
    out System.object VariantArray,  
    System.int Index,  
    System.short Value  
)
```

C++/CLI

```
void PutShort(  
& [Out] System.Object^ VariantArray,  
& System.int Index,  
& System.short Value  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of short values
Index
Index of short value
Value
Short value

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetShort Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PutUNKNOWN Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : PutUNKNOWN Method (ISafeArrayUtility)

Adds the specified UNKNOWN object to a Variant SafeArray of UNKNOWN objects.

.NET Syntax

Visual Basic (Declaration)

```
Sub PutUNKNOWN( _
    ByRef VariantArray As System.Object, _
    ByVal Index As System.Integer, _
    ByVal Value As System.Object _
)
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility
Dim VariantArray As System.Object
Dim Index As System.Integer
Dim Value As System.Object

instance.PutUNKNOWN(VariantArray, Index, Value)
```

C#

```
void PutUNKNOWN(
    out System.object VariantArray,
    System.int Index,
    System.object Value
)
```

C++/CLI

```
void PutUNKNOWN(
    & [Out] System.Object^ VariantArray,
    & System.int Index,
    & System.Object^ Value
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray of UNKNOWN objects
Index
Index of UNKNOWN object
Value
UNKNOWN object

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetUNKNOWN Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

UnPackVariant Method (ISafeArrayUtility)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISafeArrayUtility Interface](#) : UnPackVariant Method (ISafeArrayUtility)

Unpacks the specified packed Variant SafeArray to native SOLIDWORKS Dispatch-based objects of the same data type.

.NET Syntax

Visual Basic (Declaration)

```
Function UnPackVariant( _
    ByVal VariantArray As System.Object, _
    ByVal Count As System.Integer _
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISafeArrayUtility  
Dim VariantArray As System.Object  
Dim Count As System.Integer  
Dim value As System.Integer  
  
value = instance.UnPackVariant(VariantArray, Count)
```

C#

```
System.int UnPackVariant(  
    System.object VariantArray,  
    System.int Count  
)
```

C++/CLI

```
System.int UnPackVariant(  
& System.Object^ VariantArray,  
& System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

VariantArray
Variant SafeArray
Count
Number of native SOLIDWORKS Dispatch-based objects of the same data type

Return Value

Native SOLIDWORKS Dispatch-based objects of the same data type

See Also

[ISafeArrayUtility Interface](#)
[ISafeArrayUtility Members](#)
[ISafeArrayUtility::GetInfo Method \(\)](#)
[ISafeArrayUtility::PackVariant Method \(\)](#)

Availability

SOLIDWORKS 2015 FCS, Revision Number 23.0

ISaveBodyFeatureData (Type)

ISaveBodyFeatureData Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISaveBodyFeatureData Interface

Allows access to a Save Bodies feature.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISaveBodyFeatureData
```

Visual Basic (Usage)

```
Dim instance As ISaveBodyFeatureData
```

C#

```
public interface ISaveBodyFeatureData
```

C++/CLI

```
public interface class ISaveBodyFeatureData
```

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData](#).

Remarks

Accessors

[IFeature::GetDefinition](#) and [IFeature::!GetDefinition](#)

Access Diagram

[SaveBodyFeatureData](#)

See Also

[ISaveBodyFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::CreateSaveBodyFeature Method](#)

ISaveBodyFeatureData Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISaveBodyFeatureData Interface

For a list of all members of this type, see [ISaveBodyFeatureData members](#).

Public Methods

Name	Description
AccessSelections	Gains access to the selections that define this Save Bodies feature.
AddSaveBodies	Adds the specified bodies to the Save Bodies feature and saves them as part documents on disk.
GetSaveBodies	Gets the save bodies in this Save Bodies feature.

		
	GetSaveBodiesCount	Gets the number of save bodies in this Save Bodies feature.
	ReleaseSelectionAccess	Releases access to the selections that define this Save Bodies feature.
	RemoveSaveBodies	Removes the specified bodies from this Save Bodies feature.

[Top](#)

See Also

[ISaveBodyFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::CreateSaveBodyFeature Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISaveBodyFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)

 [SolidWorks.Interop.sldworks Namespace](#) : ISaveBodyFeatureData Interface

The following tables list the members exposed by [ISaveBodyFeatureData](#).

Public Properties

Name	Description
 AssemblyPath	Gets or sets the path and filename of the assembly (*.sldasm) of save bodies.
 ConsumeBody	Gets or sets whether to consume all bodies in the original part.
 CopyCustomProperties	Gets or sets whether to copy custom properties to the new parts.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Gains access to the selections that define this Save Bodies feature.
 AddSaveBodies	Adds the specified bodies to the Save Bodies feature and saves them as part documents on disk.
 GetSaveBodies	Gets the save bodies in this Save Bodies feature.
 GetSaveBodiesCount	Gets the number of save bodies in this Save Bodies feature.
 ReleaseSelectionAccess	Releases access to the selections that define this Save Bodies feature.
 RemoveSaveBodies	Removes the specified bodies from this Save Bodies feature.

[Top](#)

See Also

[ISaveBodyFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::CreateSaveBodyFeature Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISaveBodyFeatureData Interface Properties

[See Also](#)

 [SolidWorks.Interop.sldworks Namespace](#) : ISaveBodyFeatureData Interface

For a list of all members of this type, see [ISaveBodyFeatureData members](#).

Public Properties

Name	Description
 AssemblyPath	Gets or sets the path and filename of the assembly (*.sldasm) of save bodies.
 ConsumeBody	Gets or sets whether to consume all bodies in the original part.
 CopyCustomProperties	Gets or sets whether to copy custom properties to the new parts.

[Top](#)

See Also

[ISaveBodyFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::CreateSaveBodyFeature Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

AccessSelections Method (ISaveBodyFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISaveBodyFeatureData Interface](#) : AccessSelections Method (ISaveBodyFeatureData)

Gains access to the selections that define this Save Bodies feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISaveBodyFeatureData  
Dim TopDoc As ModelDoc2  
Dim Component As Component2  
Dim value As System.Boolean  
  
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(  
    ModelDoc2 TopDoc,  
    Component2 Component  
)
```

C++/CLI

```
System.bool AccessSelections(  
& ModelDoc2^ TopDoc,  
& Component2^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Top-level document (see **Remarks**)

Component

Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections were successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData::AccessSelections](#).

Example

[Get Number of Bodies in Save Bodies Feature \(VBA\)](#)

Remarks

To modify a feature in a...

Then...

Part

- TopDoc argument is the [IModelDoc2](#) for the part

	Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [ISaveBodyFeatureData::ReleaseSelectionAccess](#) if you did not

See Also

[ISaveBodyFeatureData Interface](#)
[ISaveBodyFeatureData Members](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

AddSaveBodies Method (ISaveBodyFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISaveBodyFeatureData Interface](#) : AddSaveBodies Method (ISaveBodyFeatureData)

Adds the specified bodies to the Save Bodies feature and saves them as part documents on disk.

.NET Syntax

Visual Basic (Declaration)

```
Function AddSaveBodies( _
    ByVal Bodies As System.Object, _
    ByVal FilePaths As System.Object _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISaveBodyFeatureData
Dim Bodies As System.Object
Dim FilePaths As System.Object
Dim value As System.Boolean

value = instance.AddSaveBodies(Bodies, FilePaths)
```

C#

```
System.bool AddSaveBodies(
    System.object Bodies,
    System.object FilePaths
)
```

C++/CLI

```
System.bool AddSaveBodies(
    & System.Object^ Bodies,
    & System.Object^ FilePaths
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Bodies
Array of bodies to add to the Save Bodies feature
FilePaths
Array of path and filenames of part documents to which to save Bodies

Return Value

True if the bodies are added to the Save Bodies feature and saved as part documents on disk, false if not

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData::AddSaveBodies](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[ISaveBodyFeatureData Interface](#)
[ISaveBodyFeatureData Members](#)
[ISaveBodyFeatureData::GetSaveBodies Method](#)
[ISaveBodyFeatureData::RemoveSaveBodies Method](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

AssemblyPath Property (ISaveBodyFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISaveBodyFeatureData Interface](#) : AssemblyPath Property (ISaveBodyFeatureData)

Gets or sets the path and filename of the assembly (*.sldasm) of save bodies.

.NET Syntax

Visual Basic (Declaration)

```
Property AssemblyPath As System.String
```

Visual Basic (Usage)



```
Dim instance As ISaveBodyFeatureData  
Dim value As System.String
```

```
instance.AssemblyPath = value  
value = instance.AssemblyPath
```

C#

```
System.string AssemblyPath {get; set;}
```

C++/CLI

```
property System.String^ AssemblyPath {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Path and filename of the assembly (*.sldasm) of save bodies

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData::AssemblyPath](#).

See Also

[ISaveBodyFeatureData Interface](#)
[ISaveBodyFeatureData Members](#)

Availability

ConsumeBody Property (ISaveBodyFeatureData)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [ISaveBodyFeatureData Interface](#) : ConsumeBody Property (ISaveBodyFeatureData)

Gets or sets whether to consume all bodies in the original part.

.NET Syntax

Visual Basic (Declaration)

Property ConsumeBody As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISaveBodyFeatureData
Dim value As System.Boolean

instance.ConsumeBody = value

value = instance.ConsumeBody
```

C#

```
System.bool ConsumeBody {get; set;}
```

C++/CLI

```
property System.bool ConsumeBody {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

See [Remarks](#)

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData::ConsumeBody](#).

Remarks

For VBA, .NET:

True to consume all bodies in the original part, false to not.

For C++:

VARIANT_TRUE (-1) to consume all bodies in the original part, VARIANT_FALSE (0) to not.

See Also

[ISaveBodyFeatureData Interface](#)
[ISaveBodyFeatureData Members](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

CopyCustomProperties Property (ISaveBodyFeatureData)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [ISaveBodyFeatureData Interface](#) : CopyCustomProperties Property (ISaveBodyFeatureData)

Gets or sets whether to copy custom properties to the new parts.

.NET Syntax

Visual Basic (Declaration)

```
Property CopyCustomProperties As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISaveBodyFeatureData  
Dim value As System.Boolean
```

```
instance.CopyCustomProperties = value
```

```
value = instance.CopyCustomProperties
```

C#

```
System.bool CopyCustomProperties {get; set;}
```

C++/CLI

```
property System.bool CopyCustomProperties {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

See [Remarks](#)

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData::CopyCustomProperties](#).

Remarks

For VBA, .NET:

True to copy custom properties to the new parts, false to not.

For C++:

VARIANT_TRUE (-1) to copy custom properties to the new parts, VARIANT_FALSE (0) to not.

See Also

[ISaveBodyFeatureData Interface](#)
[ISaveBodyFeatureData Members](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSaveBodies Method (ISaveBodyFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISaveBodyFeatureData Interface](#) : GetSaveBodies Method (ISaveBodyFeatureData)

Gets the save bodies in this Save Bodies feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub GetSaveBodies(  
    ByRef Bodies As System.Object, _  
    ByRef FilePaths As System.Object, _
```

```
ByRef Flags As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As ISaveBodyFeatureData  
Dim Bodies As System.Object  
Dim FilePaths As System.Object  
Dim Flags As System.Object  
  
instance.GetSaveBodies(Bodies, FilePaths, Flags)
```

C#

```
void GetSaveBodies(  
    out System.object Bodies,  
    out System.object FilePaths,  
    out System.object Flags  
)
```

C++/CLI

```
void GetSaveBodies(  
& [Out] System.Object^ Bodies,  
& [Out] System.Object^ FilePaths,  
& [Out] System.Object^ Flags  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Bodies

Array of save bodies

FilePaths

Array of paths and filenames for the part documents of Bodies

Flags

Array of booleans indicating whether each corresponding save body is consumed; true if removed from the original part, false if not

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData::GetSaveBodies](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[ISaveBodyFeatureData Interface](#)

[ISaveBodyFeatureData Members](#)

[ISaveBodyFeatureData::GetSaveBodiesCount Method](#)

[ISaveBodyFeatureData::AddSaveBodies Method](#)

[ISaveBodyFeatureData::RemoveSaveBodies Method](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetSaveBodiesCount Method (ISaveBodyFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISaveBodyFeatureData Interface](#) : GetSaveBodiesCount Method (ISaveBodyFeatureData)

Gets the number of save bodies in this Save Bodies feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetSaveBodiesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISaveBodyFeatureData  
Dim value As System.Integer
```

```
value = instance.GetSaveBodiesCount()
```

C#

```
System.int GetSaveBodiesCount()
```

C++/CLI

```
System.int GetSaveBodiesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of save bodies in this Save Bodies feature

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData::GetSaveBodiesCount](#).

Example

[Get Number of Bodies in Save Body Feature \(VBA\)](#)

See Also

[ISaveBodyFeatureData Interface](#)
[ISaveBodyFeatureData Members](#)
[ISaveBodyFeatureData::GetSaveBodies Method](#)

Availability

SOLIDWORKS 2009 FCS, Release Number 17.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

ReleaseSelectionAccess Method (ISaveBodyFeatureData)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISaveBodyFeatureData Interface](#) : ReleaseSelectionAccess Method (ISaveBodyFeatureData)

Releases access to the selections that define this Save Bodies feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ReleaseSelectionAccess()
```

Visual Basic (Usage)



```
Dim instance As ISaveBodyFeatureData
```

```
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData::ReleaseSelectionAccess](#).

Example

[Get Number of Bodies in Save Bodies Feature \(VBA\)](#)

Remarks

[ISaveBodiesFeatureData::AccessSelections](#) puts the model in a rollback state to allow access to the selections that define the feature.

Use this method to restore the rollback state if you did not modify the feature, or use [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you did modify the feature.

See Also

[ISaveBodyFeatureData Interface](#)
[ISaveBodyFeatureData Members](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

RemoveSaveBodies Method (ISaveBodyFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISaveBodyFeatureData Interface](#) : RemoveSaveBodies Method (ISaveBodyFeatureData)

Removes the specified bodies from this Save Bodies feature.

.NET Syntax

Visual Basic (Declaration)

```
Function RemoveSaveBodies(  
    ByVal Bodies As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISaveBodyFeatureData  
Dim Bodies As System.Object  
Dim value As System.Boolean  
  
value = instance.RemoveSaveBodies(Bodies)
```

C#

```
System.bool RemoveSaveBodies(  
    System.object Bodies  
)
```

C++/CLI

```
System.bool RemoveSaveBodies(  
    & System.Object^ Bodies  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Bodies
Array of bodies to remove from this Save Bodies feature

Return Value

True if the bodies are removed from this Save Bodies feature, false if not

Visual Basic for Applications (VBA) Syntax

See [SaveBodyFeatureData::RemoveSaveBodies](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details on using this method.

See Also

[ISaveBodyFeatureData Interface](#)
[ISaveBodyFeatureData Members](#)
[ISaveBodyFeatureData::AddSaveBodies Method](#)
[ISaveBodyFeatureData::GetSaveBodies Method](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

ISaveTo3DExperienceOptions (Type)

ISaveTo3DExperienceOptions Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISaveTo3DExperienceOptions Interface

Allows access to options for saving a document in [SOLIDWORKS Design connected to the 3DEXPERIENCE platform](#).

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISaveTo3DExperienceOptions
```

Visual Basic (Usage)



```
Dim instance As ISaveTo3DExperienceOptions
```

C#

```
public interface ISaveTo3DExperienceOptions
```

C++/CLI

```
public interface class ISaveTo3DExperienceOptions
```

Visual Basic for Applications (VBA) Syntax

See [SaveTo3DExperienceOptions](#).

Example

See the [IPLMObjectSpecification](#) examples.

Accessors

[ISldWorks::GetSaveTo3DExperienceOptions](#)

Access Diagram

[SaveTo3DExperienceOptions](#)

See Also

[ISaveTo3DExperienceOptions Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

ISaveTo3DExperienceOptions Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISaveTo3DExperienceOptions Interface

For a list of all members of this type, see [ISaveTo3DExperienceOptions members](#).

Public Methods

Name	Description
 SetRevisionComments	Sets the specified revision comments when saving a document in SOLIDWORKS Design connected to the 3DEXPERIENCE platform .

[Top](#)

See Also

[ISaveTo3DExperienceOptions Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISaveTo3DExperienceOptions Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISaveTo3DExperienceOptions Interface

The following tables list the members exposed by [ISaveTo3DExperienceOptions](#).

Public Properties

Name	Description
 FileName	Gets or sets the specified file name when saving a document in SOLIDWORKS Design connected to the 3DEXPERIENCE platform .

[Top](#)

Public Methods

Name	Description
 SetRevisionComments	Sets the specified revision comments when saving a document in SOLIDWORKS Design connected to the 3DEXPERIENCE platform .

[Top](#)

See Also

[ISaveTo3DExperienceOptions Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISaveTo3DExperienceOptions Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISaveTo3DExperienceOptions Interface

For a list of all members of this type, see [ISaveTo3DExperienceOptions members](#).

Public Properties

Name	Description
 FileName	Gets or sets the specified file name when saving a document in SOLIDWORKS Design connected to the 3DEXPERIENCE platform .

[Top](#)

See Also

[ISaveTo3DExperienceOptions Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

FileName Property (ISaveTo3DExperienceOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISaveTo3DExperienceOptions Interface](#) : FileName Property (ISaveTo3DExperienceOptions)

Gets or sets the specified file name when saving a document in [SOLIDWORKS Design connected to the 3DEXPERIENCE platform](#).

.NET Syntax

Visual Basic (Declaration)

Property FileName As System.String

Visual Basic (Usage)



```
Dim instance As ISaveTo3DExperienceOptions  
Dim value As System.String
```

```
instance.FileName = value  
value = instance.FileName
```

C#

```
System.string FileName {get; set;}
```

C++/CLI

```
property System.String^ FileName {  
    System.String^ get();  
    void set ( & System.String^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

File name

Visual Basic for Applications (VBA) Syntax

See [SaveTo3DExperienceOptions::FileName](#).

Example

See the [IPLMObjectSpecification](#) examples.

See Also

[ISaveTo3DExperienceOptions Interface](#)
[ISaveTo3DExperienceOptions Members](#)

Availability

SOLIDWORKS 2020 SP3.1, Revision Number 28.3.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

SetRevisionComments Method (ISaveTo3DExperienceOptions)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISaveTo3DExperienceOptions Interface](#) : SetRevisionComments Method (ISaveTo3DExperienceOptions)

Sets the specified revision comments when saving a document in [SOLIDWORKS Design connected to the 3DEXPERIENCE platform](#).

.NET Syntax

Visual Basic (Declaration)

```
Function SetRevisionComments(  
    ByVal RevisionComments As System.String _  
) As System.Boolean
```

Visual Basic (Usage)

```
Dim instance As ISaveTo3DExperienceOptions  
Dim RevisionComments As System.String  
Dim value As System.Boolean
```

```
value = instance.SetRevisionComments(RevisionComments)
```

C#

```
System.bool SetRevisionComments(  
    System.string RevisionComments  
)
```

C++/CLI



```
System.bool SetRevisionComments(  
& System.String^ RevisionComments  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

RevisionComments
Save comments

Return Value

True if the document saved successfully, false if not

Visual Basic for Applications (VBA) Syntax

See [SaveTo3DExperienceOptions::SetRevisionComments](#).

Example

See the [IPLMObjectSpecification](#) examples.

See Also

[ISaveTo3DExperienceOptions Interface](#)
[ISaveTo3DExperienceOptions Members](#)

Availability

SOLIDWORKS 2020 SP3.1, Revision Number 28.3.1