

SOLIDWORKS API (.NET VBA C#) — Reference (255/337): IShellFeatureData-ISilhouetteEdge

SOLIDWORKS API Documentation (converted from CHM)

IShellFeatureData (Type)

IShellFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IShellFeatureData Interface

Allows access to a shell feature.
NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface IShellFeatureData
```

Visual Basic (Usage)



```
Dim instance As IShellFeatureData
```

C#

```
public interface IShellFeatureData
```

C++/CLI

```
public interface class IShellFeatureData
```

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData](#).

Example

[Create Shell Feature \(VBA\)](#)
[Create Shell Feature \(VB.NET\)](#)
[Create Shell Feature \(C#\)](#)

Accessors

[IFeature::GetDefinition](#) and [IFeature::IGetDefinition](#)

Access Diagram

[ShellFeatureData](#)

See Also

[IShellFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertFeatureShell Method](#)

IShellFeatureData Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IShellFeatureData Interface

For a list of all members of this type, see [IShellFeatureData members](#).

Public Methods

Name	Description
 AccessSelections	Gains access to the selections that define this shell feature.
 GetMultipleThicknessAtIndex	Gets the thickness of the shell at the specified index in this shell feature.

 GetMultipleThicknessFacesCount	Gets the number of faces with multiple thickness in this shell feature.
 IAccessSelections	Gains access to the selections that define this shell feature.
 IGetFacesRemoved	Gets the faces removed in this shell feature.
 IGetMultipleThicknessFaces	Gets the multiple-thickness faces in this shell feature.
 ISetFacesRemoved	Sets the faces to remove in this shell feature.
 ISetMultipleThicknessFaces	Sets the multiple-thickness faces in this shell feature.
 ReleaseSelectionAccess	Releases access to the selections used to define this shell feature.
 SetMultipleThicknessAtIndex	Sets the thickness of the shell at this index in this shell feature.

[Top](#)

See Also

[IShellFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertFeatureShell Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IShellFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)

[SolidWorks.Interop.sldworks Namespace](#) : IShellFeatureData Interface

The following tables list the members exposed by [IShellFeatureData](#).

Public Properties

Name	Description
 Direction	Gets and sets the direction of this shell feature.
 FacesRemoved	Gets the faces removed and sets the faces to remove in this shell feature.
 FacesRemovedCount	Gets the number of faces removed in this shell feature.
 MultipleThicknessFaces	Gets and sets the multiple-thickness faces in this shell feature.
 Thickness	Gets and sets the overall thickness of the shell feature.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Gains access to the selections that define this shell feature.
 GetMultipleThicknessAtIndex	Gets the thickness of the shell at the specified index in this shell feature.
 GetMultipleThicknessFacesCount	Gets the number of faces with multiple thickness in this shell feature.
 IAccessSelections	Gains access to the selections that define this shell feature.
 IGetFacesRemoved	Gets the faces removed in this shell feature.
 IGetMultipleThicknessFaces	Gets the multiple-thickness faces in this shell feature.
 ISetFacesRemoved	Sets the faces to remove in this shell feature.
 ISetMultipleThicknessFaces	Sets the multiple-thickness faces in this shell feature.
 ReleaseSelectionAccess	Releases access to the selections used to define this shell feature.
 SetMultipleThicknessAtIndex	Sets the thickness of the shell at this index in this shell feature.

[Top](#)

See Also

[IShellFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertFeatureShell Method](#)

IShellFeatureData Interface Properties

[See Also](#)

[SolidWorks.Interop.sldworks Namespace](#) : IShellFeatureData Interface

For a list of all members of this type, see [IShellFeatureData members](#).

Public Properties

Name	Description
 Direction	Gets and sets the direction of this shell feature.
 FacesRemoved	Gets the faces removed and sets the faces to remove in this shell feature.
 FacesRemovedCount	Gets the number of faces removed in this shell feature.
 MultipleThicknessFaces	Gets and sets the multiple-thickness faces in this shell feature.
 Thickness	Gets and sets the overall thickness of the shell feature.

[Top](#)

See Also

[IShellFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IModelDoc2::InsertFeatureShell Method](#)

AccessSelections Method (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : AccessSelections Method (IShellFeatureData)

Gains access to the selections that define this shell feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections(  
    ByVal TopDoc As System.Object, _  
    ByVal Component As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)

```
Dim instance As IShellFeatureData  
Dim TopDoc As System.Object  
Dim Component As System.Object  
Dim value As System.Boolean  
  
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(  
    System.object TopDoc,  
    System.object Component  
)
```

C++/CLI

```
System.bool AccessSelections(  
& System.Object^ TopDoc,  
& System.Object^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc
Top-level document (see **Remarks**)

Component
Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections were successfully accessed, false if not

 Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData::AccessSelections](#).

 Example

See the [IShellFeatureData](#) examples.

 Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [IShellFeatureData::ReleaseSelections](#) if you did not

 See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::IAccessSelections Method](#)

 Availability

SOLIDWORKS 2001 FCS, Revision Number 9.0

Direction Property (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : Direction Property (IShellFeatureData)

Gets and sets the direction of this shell feature.

 .NET Syntax

Visual Basic (Declaration)

Property Direction As System.Integer

Visual Basic (Usage)

```
Dim instance As IShellFeatureData  
Dim value As System.Integer  
  
instance.Direction = value  
  
value = instance.Direction
```

C#

```
System.int Direction {get; set;}
```

C++/CLI

```
property System.int Direction {  
    System.int get();
```



```
void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

0 for inward shell, 1 for outward shell

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData.Direction](#).

Example

See the [IShellFeatureData](#) examples.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

FacesRemoved Property (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : FacesRemoved Property (IShellFeatureData)

Gets the faces removed and sets the faces to remove in this shell feature.

.NET Syntax

Visual Basic (Declaration)

```
Property FacesRemoved As System.Object
```

Visual Basic (Usage)



```
Dim instance As IShellFeatureData  
Dim value As System.Object
```

```
instance.FacesRemoved = value
```

```
value = instance.FacesRemoved
```

C#

```
System.Object FacesRemoved {get; set;}
```

C++/CLI

```
property System.Object^ FacesRemoved {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of removed [faces](#)

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData.FacesRemoved](#).

Example

See the [IShellFeatureData](#) examples.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::!GetFacesRemoved Method](#)
[IShellFeatureData::!SetFacesRemoved Method](#)
[IShellFeatureData::FacesRemovedCount Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

FacesRemovedCount Property (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : FacesRemovedCount Property (IShellFeatureData)

Gets the number of faces removed in this shell feature.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property FacesRemovedCount As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IShellFeatureData  
Dim value As System.Integer  
  
value = instance.FacesRemovedCount
```

C#

```
System.int FacesRemovedCount {get;}
```

C++/CLI

```
property System.int FacesRemovedCount {  
    System.int get();  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Number of removed faces

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData::FacesRemovedCount](#).

Example

See the [IShellFeatureData](#) examples.

Remarks

Call this property before calling [IShellFeatureData::!GetFacesRemoved](#) to get the size of the array for that method.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::ISetFacesRemoved Method](#)
[IShellFeatureData::FacesRemoved Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetMultipleThicknessAtIndex Method (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : GetMultipleThicknessAtIndex Method (IShellFeatureData)

Gets the thickness of the shell at the specified index in this shell feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetMultipleThicknessAtIndex( _  
    ByVal Index As System.Integer _  
) As System.Double
```

Visual Basic (Usage)



```
Dim instance As IShellFeatureData  
Dim Index As System.Integer  
Dim value As System.Double  
  
value = instance.GetMultipleThicknessAtIndex(Index)
```

C#

```
System.double GetMultipleThicknessAtIndex(  
    System.int Index  
)
```

C++/CLI

```
System.double GetMultipleThicknessAtIndex(  
    & System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

0-based index for the thickness

Return Value

Shell thickness

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData::GetMultipleThicknessAtIndex](#).

Example

See the [IShellFeatureData](#) examples.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::GetMultipleThicknessFacesCount Method](#)

[IShellFeatureData::IGetMultipleThicknessFaces Method](#)
[IShellFeatureData::ISetMultipleThicknessFaces Method](#)
[IShellFeatureData::SetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::MultipleThicknessFaces Property](#)
[IShellFeatureData::Thickness Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetMultipleThicknessFacesCount Method (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : GetMultipleThicknessFacesCount Method (IShellFeatureData)

Gets the number of faces with multiple thickness in this shell feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetMultipleThicknessFacesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IShellFeatureData  
Dim value As System.Integer
```

```
value = instance.GetMultipleThicknessFacesCount()
```

C#

```
System.int GetMultipleThicknessFacesCount()
```

C++/CLI

```
System.int GetMultipleThicknessFacesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of faces with multiple thickness

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData::GetMultipleThicknessFacesCount](#).

Example

See the [IShellFeatureData](#) examples.

Remarks

Call this method before calling [IShellFeatureData::IGetMultipleThicknessFaces](#) to get the size of the array for that method.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::GetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::ISetMultipleThicknessFaces Method](#)
[IShellFeatureData::SetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::MultipleThicknessFaces Property](#)
[IShellFeatureData::Thickness Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

IAccessSelections Method (IShellFeatureData)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : IAccessSelections Method (IShellFeatureData)

Gains access to the selections that define this shell feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IAccessSelections( _
    ByVal TopDoc As ModelDoc2, _
    ByVal Component As Component2 _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IShellFeatureData
Dim TopDoc As ModelDoc2
Dim Component As Component2
Dim value As System.Boolean

value = instance.IAccessSelections(TopDoc, Component)
```

C#

```
System.bool IAccessSelections(
    ModelDoc2 TopDoc,
    Component2 Component
)
```

C++/CLI

```
System.bool IAccessSelections(
    & ModelDoc2^ TopDoc,
    & Component2^ Component
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

*TopDoc*Top-level document (see **Remarks**)*Component*Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections were successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData.IAccessSelections](#).

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::!ModifyDefinition2](#) if you modified the feature
- [IShellFeatureData::ReleaseSelections](#) if you did not

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::AccessSelections Method](#)

Availability

SOLIDWORKS 2001 FCS, Revision Number 9.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetFacesRemoved Method (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : IGetFacesRemoved Method (IShellFeatureData)

Gets the faces removed in this shell feature.

Visual Basic Syntax

Visual Basic (Declaration)

```
Function IGetFacesRemoved( _  
    ByVal Count As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IShellFeatureData  
Dim Count As System.Integer  
Dim value As System.Object  
  
value = instance.IGetFacesRemoved(Count)
```

C#

```
System.object IGetFacesRemoved(  
    System.int Count  
)
```

C++/CLI

```
System.Object^ IGetFacesRemoved(  
    & System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of removed faces

Return Value

- in-process, unmanaged C++: Pointer to an array of removed [faces](#) of size Count
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Call [IShellFeatureData::FacesRemovedCount](#) before calling this method to get the size of the array for this method.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::ISetFacesRemoved Method](#)
[IShellFeatureData::FacesRemoved Property](#)

Availability

IGetMultipleThicknessFaces Method (IShellFeatureData)

[See Also](#)[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : IGetMultipleThicknessFaces Method (IShellFeatureData)

Gets the multiple-thickness faces in this shell feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetMultipleThicknessFaces( _
    ByVal Count As System.Integer _
) As System.Object
```

Visual Basic (Usage)

```
Dim instance As IShellFeatureData
Dim Count As System.Integer
Dim value As System.Object

value = instance.IGetMultipleThicknessFaces(Count)
```

C#

```
System.object IGetMultipleThicknessFaces(
    System.int Count
)
```

C++/CLI

```
System.Object^ IGetMultipleThicknessFaces(
    & System.int Count
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of multiple-thickness faces

Return Value

- in-process, unmanaged C++: Pointer to an array of multiple-thickness [faces](#) of size Count
- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

Call [IShellFeatureData::GetMultipleThicknessFacesCount](#) before calling this method to get the size of the array for this method.See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::GetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::ISetMultipleThicknessFaces Method](#)
[IShellFeatureData::SetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::MultipleThicknessFaces Property](#)
[IShellFeatureData::Thickness Property](#)

Availability

ISetFacesRemoved Method (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : ISetFacesRemoved Method (IShellFeatureData)

Sets the faces to remove in this shell feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetFacesRemoved( _  
    ByVal Count As System.Integer, _  
    ByRef FaceArray As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As IShellFeatureData  
Dim Count As System.Integer  
Dim FaceArray As System.Object  
  
instance.ISetFacesRemoved(Count, FaceArray)
```

C#

```
void ISetFacesRemoved(  
    System.int Count,  
    ref System.object FaceArray  
)
```

C++/CLI

```
void ISetFacesRemoved(  
& System.int Count,  
& System.Object^% FaceArray  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of faces

FaceArray

- in-process, unmanaged C++: Pointer to an array of [faces](#) to remove of size Count
- VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::IGetFacesRemoved Method](#)
[IShellFeatureData::FacesRemoved Property](#)
[IShellFeatureData::FacesRemovedCount Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISetMultipleThicknessFaces Method (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : ISetMultipleThicknessFaces Method (IShellFeatureData)

Sets the multiple-thickness faces in this shell feature.

Visual Basic Syntax

Visual Basic (Declaration)

```
Sub ISetMultipleThicknessFaces( _  
    ByVal Count As System.Integer, _  
    ByRef FaceArray As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As IShellFeatureData  
Dim Count As System.Integer  
Dim FaceArray As System.Object  
  
instance.ISetMultipleThicknessFaces(Count, FaceArray)
```

C#

```
void ISetMultipleThicknessFaces(  
    System.int Count,  
    ref System.object FaceArray  
)
```

C++/CLI

```
void ISetMultipleThicknessFaces(  
& System.int Count,  
& System.Object^% FaceArray  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of faces

FaceArray

- in-process, unmanaged C++: Pointer to an array of [faces](#) to set to multiple thickness of size Count

• VBA, VB.NET, C#, and C++/CLI: Not supported

See [In-process Methods](#) for details about this type of method.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::IGetMultipleThicknessFaces Method](#)
[IShellFeatureData::GetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::GetMultipleThicknessFacesCount Method](#)
[IShellFeatureData::SetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::MultipleThicknessFaces Property](#)
[IShellFeatureData::Thickness Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

MultipleThicknessFaces Property (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : MultipleThicknessFaces Property (IShellFeatureData)

Gets and sets the multiple-thickness faces in this shell feature.

Visual Basic Syntax

Property MultipleThicknessFaces As System.Object



```
Dim instance As IShellFeatureData
Dim value As System.Object

instance.MultipleThicknessFaces = value

value = instance.MultipleThicknessFaces
```

```
System.Object MultipleThicknessFaces {get; set;}
```

```
property System.Object^ MultipleThicknessFaces {
    System.Object^ get();
    void set ( & System.Object^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of multiple-thickness [faces](#)

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData::MultipleThicknessFaces](#).

Example

See the [IShellFeatureData](#) examples.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::GetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::GetMultipleThicknessFacesCount Method](#)
[IShellFeatureData::IGetMultipleThicknessFaces Method](#)
[IShellFeatureData::ISetMultipleThicknessFaces Method](#)
[IShellFeatureData::SetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::MultipleThicknessFaces Property](#)
[IShellFeatureData::Thickness Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

ReleaseSelectionAccess Method (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : ReleaseSelectionAccess Method (IShellFeatureData)

Releases access to the selections used to define this shell feature.

.NET Syntax

Sub ReleaseSelectionAccess()

```
Dim instance As IShellFeatureData

instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData::ReleaseSelectionAccess](#).

Example

See the [IShellFeatureData](#) examples.

Remarks

[IShellFeatureData::AccessSelections](#) and [IShellFeatureData::!AccessSelections](#) put the model in a rollback state to allow access to the selections that define the feature.

Use this method to restore the rollback state if you did not modify the feature, or use [IFeature::ModifyDefinition](#) or [IFeature::!ModifyDefinition2](#) if you did modify the feature.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SetMultipleThicknessAtIndex Method (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : SetMultipleThicknessAtIndex Method (IShellFeatureData)

Sets the thickness of the shell at this index in this shell feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub SetMultipleThicknessAtIndex( _
    ByVal Index As System.Integer, _
    ByVal Thickness As System.Double _
)
```

Visual Basic (Usage)

Copy Code

```
Dim instance As IShellFeatureData
Dim Index As System.Integer
Dim Thickness As System.Double
```

```
instance.SetMultipleThicknessAtIndex(Index, Thickness)
```

C#

```
void SetMultipleThicknessAtIndex(  
    System.int Index,  
    System.double Thickness  
)
```

C++/CLI

```
void SetMultipleThicknessAtIndex(  
& System.int Index,  
& System.double Thickness  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

0-based index for new thickness

Thickness

New thickness

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData::SetMultipleThicknessAtIndex](#).

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::GetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::GetMultipleThicknessFacesCount Method](#)
[IShellFeatureData::ISetMultipleThicknessFaces Method](#)
[IShellFeatureData::MultipleThicknessFaces Property](#)
[IShellFeatureData::Thickness Property](#)
[IShellFeatureData::IGetMultipleThicknessFaces Method](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Thickness Property (IShellFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShellFeatureData Interface](#) : Thickness Property (IShellFeatureData)

Gets and sets the overall thickness of the shell feature.

.NET Syntax

Visual Basic (Declaration)

Property Thickness As System.Double

Visual Basic (Usage)



```
Dim instance As IShellFeatureData  
Dim value As System.Double
```

```
instance.Thickness = value
```

```
value = instance.Thickness
```

C#

```
System.double Thickness {get; set;}
```

C++/CLI

```
property System.double Thickness {  
    System.double get();
```

```
void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Shell thickness

Visual Basic for Applications (VBA) Syntax

See [ShellFeatureData::Thickness](#).

Example

See the [IShellFeatureData](#) examples.

See Also

[IShellFeatureData Interface](#)
[IShellFeatureData Members](#)
[IShellFeatureData::GetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::GetMultipleThicknessFacesCount Method](#)
[IShellFeatureData::GetMultipleThicknessFaces Method](#)
[IShellFeatureData::SetMultipleThicknessFaces Method](#)
[IShellFeatureData::SetMultipleThicknessAtIndex Method](#)
[IShellFeatureData::MultipleThicknessFaces Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

IShutOffSurfaceFeatureData (Type)

IShutOffSurfaceFeatureData Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : IShutOffSurfaceFeatureData Interface

Allows access to a shut-off surface feature.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

Public Interface IShutOffSurfaceFeatureData

Visual Basic (Usage)

Dim instance As [IShut0ffSurfaceFeatureData](#)

C#

public interface IShutOffSurfaceFeatureData

C++/CLI

public interface class IShutOffSurfaceFeatureData

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData](#).

Example

[Get Shut-Off Surface Data \(VBA\)](#)
[Get Shut-Off Surface Data \(VB.NET\)](#)
[Get Shut-Off Surface Data \(C#\)](#)

Accessors

[IFeature::GetDefinition](#) and [IFeature::!GetDefinition](#)

Access Diagram

[ShutOffSurfaceFeatureData](#)

See Also

[IShutOffSurfaceFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertMoldShutOffSurface Method](#)

IShutOffSurfaceFeatureData Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : IShutOffSurfaceFeatureData Interface

For a list of all members of this type, see [IShutOffSurfaceFeatureData members](#).

Public Methods

Name	Description
AccessSelections	Gains access to the selections that define this shut-off surface feature.
FlipFaceTangentTo	Indicates to create the patch on the opposite tangent face.

	GetEdgeCount	Gets the number of edges that form a closed loop.
	GetFaceTangentTo	Gets the tangent face for the specified loop where to create the patch.
	GetLoopCount	Gets the number of closed loops for all of the patches.
	GetLoopEdgeCount	Gets the number of edges in the specified loop.
	IGetEdges	Gets the edges that form closed loops to use for the patches.
	IGetLoopEdges	Gets the edges in the specified loop.
	ISetEdges	Sets the edges to use to form closed loops for patches.
	ReleaseSelectionAccess	Releases access to the selections that define this shut-off surface feature.
	SetAllPatchTypes	Sets the type of patch for all loops for this shut-off surface feature.
	Status	Gets the status of the shut-off surface feature.

[Top](#)

See Also

[IShutOffSurfaceFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager.InsertMoldShutOffSurface Method](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IShutOffSurfaceFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : IShutOffSurfaceFeatureData Interface

The following tables list the members exposed by [IShutOffSurfaceFeatureData](#).

Public Properties

Name	Description
 Edges	Gets or sets the edges that form closed loops for the patches.
 Knit	Gets or sets whether to knit the patches in this shut-off surface feature.
 LoopEdges	Gets the edges in the specified loop in this shut-off surface feature.
 LoopPatchType	Gets and sets the type of patch for the specified loop for this shut-off surface feature.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Gains access to the selections that define this shut-off surface feature.
 FlipFaceTangentTo	Indicates to create the patch on the opposite tangent face.
 GetEdgeCount	Gets the number of edges that form a closed loop.
 GetFaceTangentTo	Gets the tangent face for the specified loop where to create the patch.
 GetLoopCount	Gets the number of closed loops for all of the patches.
 GetLoopEdgeCount	Gets the number of edges in the specified loop.
 IGetEdges	Gets the edges that form closed loops to use for the patches.
 IGetLoopEdges	Gets the edges in the specified loop.
 ISetEdges	Sets the edges to use to form closed loops for patches.
 ReleaseSelectionAccess	Releases access to the selections that define this shut-off surface feature.
 SetAllPatchTypes	Sets the type of patch for all loops for this shut-off surface feature.
 Status	Gets the status of the shut-off surface feature.

[Top](#)

See Also

[IShutOffSurfaceFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertMoldShutOffSurface Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

IShutOffSurfaceFeatureData Interface Properties

[See Also](#)

[SolidWorks.Interop.sldworks Namespace](#) : IShutOffSurfaceFeatureData Interface

For a list of all members of this type, see [IShutOffSurfaceFeatureData members](#).

Public Properties

Name	Description
 Edges	Gets or sets the edges that form closed loops for the patches.
 Knit	Gets or sets whether to knit the patches in this shut-off surface feature.
 LoopEdges	Gets the edges in the specified loop in this shut-off surface feature.
 LoopPatchType	Gets and sets the type of patch for the specified loop for this shut-off surface feature.

[Top](#)

See Also

[IShutOffSurfaceFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IFeatureManager::InsertMoldShutOffSurface Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

AccessSelections Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : AccessSelections Method (IShutOffSurfaceFeatureData)

Gains access to the selections that define this shut-off surface feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections(  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim TopDoc As ModelDoc2  
Dim Component As Component2  
Dim value As System.Boolean  
  
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(  
    ModelDoc2 TopDoc,  
    Component2 Component  
)
```

C++/CLI

```
System.bool AccessSelections(
& ModelDoc2^ TopDoc,
& Component2^ Component
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc
Top-level document (see **Remarks**)

Component
Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections were successfully accessed, false if not

 Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::AccessSelections](#).

 Example

See [IShutOffSurfaceFeatureData](#) examples.

 Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [IShutOffSurfaceFeatureData::ReleaseSelectionAccess](#) if you did not

 See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)

 Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Edges Property (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : Edges Property (IShutOffSurfaceFeatureData)

Gets or sets the edges that form closed loops for the patches.

 .NET Syntax

Visual Basic (Declaration)

Property Edges As System.Object

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData
Dim value As System.Object

instance.Edges = value

value = instance.Edges
```

C#

```
System.Object Edges {get; set;}
```

C++/CLI

```
property System.Object^ Edges {
    System.Object^ get();
    void set ( &    System.Object^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of [edges](#)

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::Edges](#).

Example

See [IShutOffSurfaceFeatureData](#) examples.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::GetEdgeCount Method](#)
[IShutOffSurfaceFeatureData::GetLoopEdgeCount Method](#)
[IShutOffSurfaceFeatureData::IGetEdges Method](#)
[IShutOffSurfaceFeatureData::ISetEdges Method](#)
[IShutOffSurfaceFeatureData::LoopEdges Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

FlipFaceTangentTo Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : FlipFaceTangentTo Method (IShutOffSurfaceFeatureData)

Indicates to create the patch on the opposite tangent face.

.NET Syntax

Visual Basic (Declaration)

```
Sub FlipFaceTangentTo( _
    ByVal Index As System.Integer _
)
```

Visual Basic (Usage)



```
Dim instance As IShutoffSurfaceFeatureData
Dim Index As System.Integer

instance.FlipFaceTangentTo(Index)
```

C#

```
void FlipFaceTangentTo(
    System.int Index
)
```

C++/CLI

```
void FlipFaceTangentTo(
    & System.int Index
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index
Index of the loop to use to create the patch

Visual Basic for Applications (VBA) Syntax

See [ShutoffSurfaceFeatureData::FlipFaceTangentTo](#).

Example

See [IShutoffSurfaceFeatureData](#) examples.

Remarks

This method is only available when the type of patch is set to swPatchTypeTangent. See [IShutoffSurfaceFeatureData::LoopPatchType](#) and [IShutoffSurfaceFeatureData::SetAllPatchTypes](#).

See Also

[IShutoffSurfaceFeatureData Interface](#)
[IShutoffSurfaceFeatureData Members](#)
[IShutoffSurfaceFeatureData::GetFaceTangentTo Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetEdgeCount Method (IShutoffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutoffSurfaceFeatureData Interface](#) : GetEdgeCount Method (IShutoffSurfaceFeatureData)

Gets the number of edges that form a closed loop.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEdgeCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IShutoffSurfaceFeatureData
Dim value As System.Integer

value = instance.GetEdgeCount()
```

C#

```
System.int GetEdgeCount()
```

C++/CLI

```
System.int GetEdgeCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of edges

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::GetEdgeCount](#).

Example

See [IShutOffSurfaceFeatureData](#) examples.

Remarks

Call this method before calling [IShutOffSurfaceFeatureData::IGetEdges](#) to get the size of the array for that method.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::ISetEdges Method](#)
[IShutOffSurfaceFeatureData::Edges Property](#)
[IShutOffSurfaceFeatureData::GetLoopEdgeCount Method](#)
[IShutOffSurfaceFeatureData::IGetLoopEdges Method](#)
[IShutOffSurfaceFeatureData::LoopEdges Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

GetFaceTangentTo Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : GetFaceTangentTo Method (IShutOffSurfaceFeatureData)

Gets the tangent face for the specified loop where to create the patch.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFaceTangentTo( _  
    ByVal Index As System.Integer _  
) As Face2
```

Visual Basic (Usage)

```
Dim instance As IShutOffSurfaceFeatureData  
Dim Index As System.Integer  
Dim value As Face2
```

```
value = instance.GetFaceTangentTo(Index)
```

C#

```
Face2 GetFaceTangentTo(  
    System.int Index  
)
```

C++/CLI



```
Face2^ GetFaceTangentTo(  
& System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index
Index for the loop where to create the patch

Return Value

[Tangent face](#)

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::GetFaceTangentTo](#).

Remarks

This method is only available when the type of patch is set to swPatchTypeTangent. See [IShutOffSurfaceFeatureData::LoopPatchType](#) and [IShutOffSurfaceFeatureData::SetAllPatchTypes](#).

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::FlipFaceTangentTo Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetLoopCount Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : GetLoopCount Method (IShutOffSurfaceFeatureData)

Gets the number of closed loops for all of the patches.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLoopCount() As System.Integer
```

Visual Basic (Usage)

```
Dim instance As IShutOffSurfaceFeatureData  
Dim value As System.Integer  
  
value = instance.GetLoopCount()
```

C#

```
System.int GetLoopCount()
```

C++/CLI

```
System.int GetLoopCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of loops for the patches



Copy Code

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::GetLoopCount](#).

Example

See [IShutOffSurfaceFeatureData](#) examples.

Remarks

Call this method before calling [IShutOffSurfaceFeatureData::IGetEdges](#) to get the size of the array for that method.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::GetLoopEdgeCount Method](#)
[IShutOffSurfaceFeatureData::IGetLoopEdges Method](#)
[IShutOffSurfaceFeatureData::LoopEdges Property](#)
[IShutOffSurfaceFeatureData::LoopPatchType Property](#)
[IShutOffSurfaceFeatureData::SetAllPatchTypes Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetLoopEdgeCount Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : GetLoopEdgeCount Method (IShutOffSurfaceFeatureData)

Gets the number of edges in the specified loop.

.NET Syntax

Visual Basic (Declaration)

```
Function GetLoopEdgeCount( _  
    ByVal Index As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim Index As System.Integer  
Dim value As System.Integer
```

```
value = instance.GetLoopEdgeCount(Index)
```

C#

```
System.int GetLoopEdgeCount(  
    System.int Index  
)
```

C++/CLI

```
System.int GetLoopEdgeCount(  
& System.int Index  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Number indicating the loop for which to get the number of edges

Return Value

Number of edges in the loop specified by index

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::GetLoopEdgeCount](#).

Example

See [IShutOffSurfaceFeatureData](#) examples.

Remarks

Call this method before calling [IShutOffSurfaceFeatureData::IGetLoopsEdges](#) to get the size of the array for that method.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::GetLoopCount Method](#)
[IShutOffSurfaceFeatureData::IGetEdges Method](#)
[IShutOffSurfaceFeatureData::IGetLoopEdges Method](#)
[IShutOffSurfaceFeatureData::ISetEdges Method](#)
[IShutOffSurfaceFeatureData::Edges Property](#)
[IShutOffSurfaceFeatureData::LoopEdges Property](#)
[IShutOffSurfaceFeatureData::LoopPatchType Property](#)
[IShutOffSurfaceFeatureData::SetAllPatchTypes Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

IGetEdges Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : IGetEdges Method (IShutOffSurfaceFeatureData)

Gets the edges that form closed loops to use for the patches.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetEdges( _  
    ByVal Count As System.Integer _  
) As Edge
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim Count As System.Integer  
Dim value As Edge
```

```
value = instance.IGetEdges(Count)
```

C#

```
Edge IGetEdges(  
    System.int Count  
)
```

C++/CLI

```
Edge^ IGetEdges(  
&    System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count
Number of edges that form loops

Return Value

- in-process, unmanaged C++: Pointer to an array of [edges](#)
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Call [IShutOffSurfaceFeatureData::GetLoopCount](#) before calling this method to get the value for Count.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::GetLoopEdgeCount Method](#)
[IShutOffSurfaceFeatureData::IGetLoopEdges Method](#)
[IShutOffSurfaceFeatureData::ISetEdges Method](#)
[IShutOffSurfaceFeatureData::Edges Property](#)
[IShutOffSurfaceFeatureData::LoopEdges Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetLoopEdges Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : IGetLoopEdges Method (IShutOffSurfaceFeatureData)

Gets the edges in the specified loop.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetLoopEdges( _  
    ByVal Index As System.Integer, _  
    ByVal Count As System.Integer _  
    ) As Edge
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim Index As System.Integer  
Dim Count As System.Integer  
Dim value As Edge  
  
value = instance.IGetLoopEdges(Index, Count)
```

C#

```
Edge IGetLoopEdges(  
    System.int Index,  
    System.int Count  
)
```

C++/CLI

```
Edge^ IGetLoopEdges(  
& System.int Index,  
& System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index of the loop

Count

Number of edges in the loop specified by index

Return Value

- in-process, unmanaged C++: Pointer to an array of [edges](#)
 - VBA, VB.NET, C#, and C++/CLI: Not supported
- See [In-process Methods](#) for details about this type of method.

Remarks

Call [IShutOffSurfaceFeatureData::GetLoopEdgeCount](#) before calling this method to get the value of Count.

Use [IShutOffSurfaceFeatureData::Edges](#) or [IShutOffSurfaceFeatureData::!SetEdges](#) to set the edges for the loops.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::GetEdgeCount Method](#)
[IShutOffSurfaceFeatureData::GetLoopCount Method](#)
[IShutOffSurfaceFeatureData::!GetLoopEdges Method](#)
[IShutOffSurfaceFeatureData::LoopEdges Property](#)
[IShutOffSurfaceFeatureData::!GetEdges Method](#)
[IShutOffSurfaceFeatureData::LoopPatchType Property](#)
[IShutOffSurfaceFeatureData::SetAllPatchTypes Method](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISetEdges Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : ISetEdges Method (IShutOffSurfaceFeatureData)

Sets the edges to use to form closed loops for patches.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetEdges( _  
    ByVal Count As System.Integer, _  
    ByRef EdgeArr As Edge _  
)
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim Count As System.Integer  
Dim EdgeArr As Edge  
  
instance.ISetEdges(Count, EdgeArr)
```

C#

```
void ISetEdges(  
    System.int Count,  
    ref Edge EdgeArr  
)
```

C++/CLI

```
void ISetEdges(  
& System.int Count,
```

& Edge^% [EdgeArr](#)
)

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count
Number of edges
EdgeArr

- in-process, unmanaged C++: Pointer to an array of [edges](#)
- VBA, VB.NET, C#, and C++/CLI: Not supported
See [In-process Methods](#) for details about this type of method.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::GetEdgeCount Method](#)
[IShutOffSurfaceFeatureData::GetLoopEdgeCount Method](#)
[IShutOffSurfaceFeatureData::!GetEdges Method](#)
[IShutOffSurfaceFeatureData::!GetLoopEdges Method](#)
[IShutOffSurfaceFeatureData::Edges Property](#)
[IShutOffSurfaceFeatureData::LoopEdges Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Knit Property (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : Knit Property (IShutOffSurfaceFeatureData)

Gets or sets whether to knit the patches in this shut-off surface feature.

.NET Syntax

Visual Basic (Declaration)

Property Knit As System.Boolean

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim value As System.Boolean
```

```
instance.Knit = value
```

```
value = instance.Knit
```

C#

```
System.bool Knit {get; set;}
```

C++/CLI

```
property System.bool Knit {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to knit the patches, false to not

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::Knit](#).

Example

See [IShutOffSurfaceFeatureData](#) examples.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::SetAllPatchTypes Method](#)
[IShutOffSurfaceFeatureData::LoopPatchType Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

LoopEdges Property (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : LoopEdges Property (IShutOffSurfaceFeatureData)

Gets the edges in the specified loop in this shut-off surface feature.

.NET Syntax

Visual Basic (Declaration)

```
ReadOnly Property LoopEdges( _  
    ByVal Index As System.Integer _  
) As System.Object
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim Index As System.Integer  
Dim value As System.Object
```

```
value = instance.LoopEdges(Index)
```

C#

```
System.object LoopEdges(  
    System.int Index  
) {get;}
```

C++/CLI

```
property System.Object^ LoopEdges {  
    System.Object^ get(System.int Index);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index
Index of the loop

Property Value

Array of [edges](#)

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::LoopEdges](#).

Example

See [IShutOffSurfaceFeatureData](#) examples.

Remarks

Use [IShutOffSurfaceFeatureData::Edges](#) or [IShutOffSurfaceFeatureData::!SetEdges](#) to set the edges for the loops.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::SetAllPatchTypes Method](#)
[IShutOffSurfaceFeatureData::GetLoopCount Method](#)
[IShutOffSurfaceFeatureData::GetLoopEdgeCount Method](#)
[IShutOffSurfaceFeatureData::!GetEdges Method](#)
[IShutOffSurfaceFeatureData::!GetLoopEdges Method](#)
[IShutOffSurfaceFeatureData::Edges Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

LoopPatchType Property (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : LoopPatchType Property (IShutOffSurfaceFeatureData)

Gets and sets the type of patch for the specified loop for this shut-off surface feature.

.NET Syntax

Visual Basic (Declaration)

```
Property LoopPatchType( _  
    ByVal Index As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim Index As System.Integer  
Dim value As System.Integer
```

```
instance.LoopPatchType(Index) = value
```

```
value = instance.LoopPatchType(Index)
```

C#

```
System.int LoopPatchType(  
    System.int Index  
) {get; set;}
```

C++/CLI

```
property System.int LoopPatchType {  
    System.int get(System.int Index);  
    void set (System.int Index, System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Index

Index of the loop for which to set the type of patch

Property Value

Type of patch as defined in [swShutOffSurfacePatchType_e](#)

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::LoopPatchType](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::SetAllPatchTypes Method](#)
[IShutOffSurfaceFeatureData::Knit Property](#)
[IShutOffSurfaceFeatureData::GetLoopCount Method](#)
[IShutOffSurfaceFeatureData::GetLoopEdgeCount Method](#)
[IShutOffSurfaceFeatureData::IGetLoopEdges Method](#)
[IShutOffSurfaceFeatureData::LoopEdges Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ReleaseSelectionAccess Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : ReleaseSelectionAccess Method (IShutOffSurfaceFeatureData)

Releases access to the selections that define this shut-off surface feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ReleaseSelectionAccess()
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::ReleaseSelectionAccess](#).

Example

See [IShutOffSurfaceFeatureData](#) examples.

Remarks

[IShutOffSurfaceFeatureData::AccessSelections](#) puts the model in a rollback state to allow access to the selections that define the feature.

Use this method to restore the rollback state if you did not modify the feature, or use [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you did modify the feature.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

SetAllPatchTypes Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : SetAllPatchTypes Method (IShutOffSurfaceFeatureData)

Sets the type of patch for all loops for this shut-off surface feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub SetAllPatchTypes( _  
    ByVal Type As System.Integer _  
)
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim Type As System.Integer  
  
instance.SetAllPatchTypes(Type)
```

C#

```
void SetAllPatchTypes(  
    System.int Type  
)
```

C++/CLI

```
void SetAllPatchTypes(  
& System.int Type  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Type
Type of patch as defined in [swShutOffSurfacePatchType](#) e

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::SetAllPatchTypes](#).

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)
[IShutOffSurfaceFeatureData::LoopPatchType Property](#)
[IShutOffSurfaceFeatureData::GetLoopCount Method](#)
[IShutOffSurfaceFeatureData::GetLoopEdgeCount Method](#)
[IShutOffSurfaceFeatureData::GetLoopEdges Method](#)
[IShutOffSurfaceFeatureData::LoopEdges Property](#)
[IShutOffSurfaceFeatureData::Knit Property](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

Status Method (IShutOffSurfaceFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [IShutOffSurfaceFeatureData Interface](#) : Status Method (IShutOffSurfaceFeatureData)

Gets the status of the shut-off surface feature.

.NET Syntax

Visual Basic (Declaration)

```
Function Status() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As IShutOffSurfaceFeatureData  
Dim value As System.Integer  
  
value = instance.Status()
```

C#

```
System.int Status()
```

C++/CLI

```
System.int Status();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Status as defined in [swShutOffSurfaceFeatureStatus_e](#)

Visual Basic for Applications (VBA) Syntax

See [ShutOffSurfaceFeatureData::Status](#).

Example

See [IShutOffSurfaceFeatureData](#) examples.

See Also

[IShutOffSurfaceFeatureData Interface](#)
[IShutOffSurfaceFeatureData Members](#)

Availability

SOLIDWORKS 2005 FCS, Revision Number 13.0

ISilhouetteEdge (Type)

ISilhouetteEdge Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISilhouetteEdge Interface

Allows you to access silhouette edges in drawing documents.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISilhouetteEdge
```

Visual Basic (Usage)

```
Dim instance As ISilhouetteEdge
```

C#

```
public interface ISilhouetteEdge
```

C++/CLI

```
public interface class ISilhouetteEdge
```

Visual Basic for Applications (VBA) Syntax

See [SilhouetteEdge](#).

Example

[Select Silhouette Edge Attached to Note \(C#\)](#)
[Select Silhouette Edge Attached to Note \(VB.NET\)](#)
[Select Silhouette Edge Attached to Note \(VBA\)](#)

Accessors

[IAnnotation::GetAttachedEntities3](#)
[ISelectionMgr::GetSelectedObject6](#)
[IView::GetPolylines7](#) and [IView::IGetPolylines7](#)
[IView::GetVisibleComponents](#) and [IView::IGetVisibleComponents](#)
[IView::GetVisibleEntities](#) and [IView::IGetVisibleEntities](#)

Access Diagram

[SilhouetteEdge](#)

See Also

[ISilhouetteEdge Members](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISelectionMgr::GetSelectedObjectsFace Method](#)
[IView Interface](#)

ISilhouetteEdge Interface Members

[See Also](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISilhouetteEdge Interface

The following tables list the members exposed by [ISilhouetteEdge](#).

Public Methods

Name	Description
 GetCurve	Gets the curve for this silhouette edge.
 GetEndPoint	Gets the end point of this silhouette edge.
 GetFace	Gets the face for this silhouette edge.
 GetStartPoint	Gets the start point of this silhouette edge.
 GetView	Gets the drawing view for this silhouette edge.
 Select	Obsolete. Superseded by ISilhouetteEdge::Select2 .
 Select2	Selects the silhouette edge in the active drawing view.

[Top](#)

See Also

[ISilhouetteEdge Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISelectionMgr::GetSelectedObjectsFace Method](#)
[IView Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISilhouetteEdge Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISilhouetteEdge Interface

For a list of all members of this type, see [ISilhouetteEdge members](#).

Public Methods

Name	Description
 GetCurve	Gets the curve for this silhouette edge.
 GetEndPoint	Gets the end point of this silhouette edge.
 GetFace	Gets the face for this silhouette edge.
 GetStartPoint	Gets the start point of this silhouette edge.
 GetView	Gets the drawing view for this silhouette edge.
 Select	Obsolete. Superseded by ISilhouetteEdge::Select2 .
 Select2	Selects the silhouette edge in the active drawing view.

[Top](#)

See Also

[ISilhouetteEdge Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[ISelectionMgr::GetSelectedObjectsFace Method](#)
[IView Interface](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetCurve Method (ISilhouetteEdge)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISilhouetteEdge Interface](#) : GetCurve Method (ISilhouetteEdge)

Gets the curve for this silhouette edge.

.NET Syntax

Visual Basic (Declaration)

Function GetCurve() As Curve

Visual Basic (Usage)



```
Dim instance As ISilhouetteEdge  
Dim value As Curve
```

```
value = instance.GetCurve()
```

C#

```
Curve GetCurve()
```

C++/CLI

```
Curve^ GetCurve();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Curve](#)

Visual Basic for Applications (VBA) Syntax

See [SilhouetteEdge::GetCurve](#).

Remarks

After getting the curve, then you can create annotations on that curve.

See Also

[ISilhouetteEdge Interface](#)
[ISilhouetteEdge Members](#)
[ISilhouetteEdge::GetEndPoint Method](#)
[ISilhouetteEdge::GetStartPoint Method](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetEndPoint Method (ISilhouetteEdge)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISilhouetteEdge Interface](#) : GetEndPoint Method (ISilhouetteEdge)

Gets the end point of this silhouette edge.

.NET Syntax

Visual Basic (Declaration)

```
Function GetEndPoint() As MathPoint
```

Visual Basic (Usage)



```
Dim instance As ISilhouetteEdge  
Dim value As MathPoint
```

```
value = instance.GetEndPoint()
```

C#

```
MathPoint GetEndPoint()
```

C++/CLI

```
MathPoint^ GetEndPoint();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[End point](#)

Visual Basic for Applications (VBA) Syntax

See [SilhouetteEdge::GetEndPoint](#).

See Also

[ISilhouetteEdge Interface](#)
[ISilhouetteEdge Members](#)
[ISilhouetteEdge::GetStartPoint Method](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetFace Method (ISilhouetteEdge)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISilhouetteEdge Interface](#) : GetFace Method (ISilhouetteEdge)

Gets the face for this silhouette edge.

.NET Syntax

Visual Basic (Declaration)

Function GetFace() As Face2

Visual Basic (Usage)



```
Dim instance As ISilhouetteEdge  
Dim value As Face2
```

```
value = instance.GetFace()
```

C#

```
Face2 GetFace()
```

C++/CLI

```
Face2^ GetFace();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Face](#)

Visual Basic for Applications (VBA) Syntax

See [SilhouetteEdge::GetFace](#).

See Also

[ISilhouetteEdge Interface](#)
[ISilhouetteEdge Members](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetStartPoint Method (ISilhouetteEdge)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISilhouetteEdge Interface](#) : GetStartPoint Method (ISilhouetteEdge)

Gets the start point of this silhouette edge.

.NET Syntax

Visual Basic (Declaration)

```
Function GetStartPoint() As MathPoint
```

Visual Basic (Usage)



```
Dim instance As ISilhouetteEdge  
Dim value As MathPoint
```

```
value = instance.GetStartPoint()
```

C#

```
MathPoint GetStartPoint()
```

C++/CLI

```
MathPoint^ GetStartPoint();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Start point](#)

Visual Basic for Applications (VBA) Syntax

See [SilhouetteEdge.GetStartPoint](#).

See Also

[ISilhouetteEdge Interface](#)
[ISilhouetteEdge Members](#)
[ISilhouetteEdge.GetEndPoint Method](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetView Method (ISilhouetteEdge)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISilhouetteEdge Interface](#) : GetView Method (ISilhouetteEdge)

Gets the drawing view for this silhouette edge.

.NET Syntax

Visual Basic (Declaration)

```
Function GetView() As View
```

Visual Basic (Usage)



```
Dim instance As ISilhouetteEdge  
Dim value As View
```

```
value = instance.GetView()
```

C#

View GetView()

C++/CLI

View^ GetView();

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

[Drawing view](#)

Visual Basic for Applications (VBA) Syntax

See [SilhouetteEdge.GetView](#).

See Also

[ISilhouetteEdge Interface](#)
[ISilhouetteEdge Members](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Select Method (ISilhouetteEdge)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISilhouetteEdge Interface](#) : Select Method (ISilhouetteEdge)

Obsolete. Superseded by [ISilhouetteEdge.Select2](#).

.NET Syntax

Visual Basic (Declaration)

```
Function Select( _  
    ByVal Append As System.Boolean, _  
    ByVal Data As SelectData _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISilhouetteEdge  
Dim Append As System.Boolean  
Dim Data As SelectData  
Dim value As System.Boolean  
  
value = instance.Select(Append, Data)
```

C#

```
System.bool Select(  
    System.bool Append,  
    SelectData Data  
)
```

C++/CLI

```
System.bool Select(  
& System.bool Append,  
& SelectData^ Data  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Append

True appends this selection to the selection list, false replaces the selection list with this selection
Data
[SelectData](#) object

Return Value

True if the selection is successful, false if not

Visual Basic for Applications (VBA) Syntax

See [SilhouetteEdge::Select](#).

See Also

[ISilhouetteEdge Interface](#)
[ISilhouetteEdge Members](#)

Availability

SOLIDWORKS 2008 FCS, Revision Number 16.0

[SOLIDWORKS API Help](#)

[Send comments](#) on this topic.

Select2 Method (ISilhouetteEdge)

[See Also](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISilhouetteEdge Interface](#) : Select2 Method (ISilhouetteEdge)

Selects the silhouette edge in the active drawing view.

.NET Syntax

Visual Basic (Declaration)

```
Function Select2( _  
    ByVal Append As System.Boolean, _  
    ByVal Data As SelectData _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISilhouetteEdge  
Dim Append As System.Boolean  
Dim Data As SelectData  
Dim value As System.Boolean  
  
value = instance.Select2(Append, Data)
```

C#

```
System.bool Select2(  
    System.bool Append,  
    SelectData Data  
)
```

C++/CLI

```
System.bool Select2(  
& System.bool Append,  
& SelectData^ Data  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Append
True appends this selection to the selection list, false replaces the selection list with this selection
Data
[SelectData](#) object

Return Value

True if the selection is successful, false if not

Visual Basic for Applications (VBA) Syntax

See [SilhouetteEdge::Select2](#).

Example

[Select Silhouette Edge Attached to Note \(C#\)](#)
[Select Silhouette Edge Attached to Note \(VB.NET\)](#)
[Select Silhouette Edge Attached to Note \(VBA\)](#)

See Also

[ISilhouetteEdge Interface](#)
[ISilhouetteEdge Members](#)

Availability

SOLIDWORKS 2014 FCS, Revision Number 22.0