

SOLIDWORKS API (.NET VBA C#) — Reference (259/337): ISimpleHoleFeatureData- ISimpleHoleFeatureData2

SOLIDWORKS API Documentation (converted from CHM)

ISimpleHoleFeatureData (Type)

ISimpleHoleFeatureData Interface

[See Also](#) [Members](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISimpleHoleFeatureData Interface

Obsolete. Superseded by [ISimpleHoleFeatureData2](#).

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISimpleHoleFeatureData
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData
```

C#

```
public interface ISimpleHoleFeatureData
```

C++/CLI

```
public interface class ISimpleHoleFeatureData
```

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData](#).

See Also

[ISimpleHoleFeatureData Members](#)
[SolidWorks.Interop.sldworks Namespace](#)

ISimpleHoleFeatureData Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISimpleHoleFeatureData Interface

The following tables list the members exposed by [ISimpleHoleFeatureData](#).

Public Properties

Name	Description
 Depth	Obsolete. Superseded by ISimpleHoleFeatureData2::Depth .
 Diameter	Obsolete. Superseded by ISimpleHoleFeatureData2::Diameter .
 DraftAngle	Obsolete. Superseded by ISimpleHoleFeatureData2::DraftAngle .
 DraftOutward	Obsolete. Superseded by ISimpleHoleFeatureData2::DraftOutward .
 DraftWhileExtruding	Obsolete. Superseded by ISimpleHoleFeatureData2::DraftWhileExtruding .
 Face	Obsolete. Superseded by ISimpleHoleFeatureData2::Face .
 IFace	Obsolete. Superseded by ISimpleHoleFeatureData2::IFace .
 IVertex	Obsolete. Superseded by ISimpleHoleFeatureData2::IVertex .
 ReverseDirection	Obsolete. Superseded by ISimpleHoleFeatureData2::ReverseDirection .
 ReverseOffset	Obsolete. Superseded by ISimpleHoleFeatureData2::ReverseOffset .
 SurfaceOffset	Obsolete. Superseded by ISimpleHoleFeatureData2::SurfaceOffset .
Type	Obsolete. Superseded by ISimpleHoleFeatureData2::Type .



[Vertex](#)

Obsolete. Superseded by [ISimpleHoleFeatureData2::Vertex](#).

[Top](#)

Public Methods

Name	Description
 AccessSelections	Obsolete. Superseded by ISimpleHoleFeatureData2::AccessSelections .
 IAccessSelections	Obsolete. Superseded by ISimpleHoleFeatureData2::IAccessSelections .
 ReleaseSelectionAccess	Obsolete. Superseded by ISimpleHoleFeatureData2::ReleaseSelectionAccess .

[Top](#)

See Also

[ISimpleHoleFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISimpleHoleFeatureData Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : [ISimpleHoleFeatureData Interface](#)

For a list of all members of this type, see [ISimpleHoleFeatureData members](#).

Public Methods

Name	Description
 AccessSelections	Obsolete. Superseded by ISimpleHoleFeatureData2::AccessSelections .
 IAccessSelections	Obsolete. Superseded by ISimpleHoleFeatureData2::IAccessSelections .
 ReleaseSelectionAccess	Obsolete. Superseded by ISimpleHoleFeatureData2::ReleaseSelectionAccess .

[Top](#)

See Also

[ISimpleHoleFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ISimpleHoleFeatureData Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : [ISimpleHoleFeatureData Interface](#)

For a list of all members of this type, see [ISimpleHoleFeatureData members](#).

Public Properties

Name	Description
 Depth	Obsolete. Superseded by ISimpleHoleFeatureData2::Depth .
 Diameter	Obsolete. Superseded by ISimpleHoleFeatureData2::Diameter .
 DraftAngle	Obsolete. Superseded by ISimpleHoleFeatureData2::DraftAngle .
 DraftOutward	Obsolete. Superseded by ISimpleHoleFeatureData2::DraftOutward .
 DraftWhileExtruding	Obsolete. Superseded by ISimpleHoleFeatureData2::DraftWhileExtruding .
 Face	Obsolete. Superseded by ISimpleHoleFeatureData2::Face .
 IFace	Obsolete. Superseded by ISimpleHoleFeatureData2::IFace .
 IVertex	Obsolete. Superseded by ISimpleHoleFeatureData2::IVertex .
 ReverseDirection	Obsolete. Superseded by ISimpleHoleFeatureData2::ReverseDirection .

 ReverseOffset	Obsolete. Superseded by ISimpleHoleFeatureData2::ReverseOffset
 SurfaceOffset	Obsolete. Superseded by ISimpleHoleFeatureData2::SurfaceOffset
 Type	Obsolete. Superseded by ISimpleHoleFeatureData2::Type
 Vertex	Obsolete. Superseded by ISimpleHoleFeatureData2::Vertex

[Top](#)

See Also

[ISimpleHoleFeatureData Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

AccessSelections Method (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : AccessSelections Method (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::AccessSelections](#).

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections( _
    ByVal TopDoc As System.Object, _
    ByVal Component As System.Object _
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData
Dim TopDoc As System.Object
Dim Component As System.Object
Dim value As System.Boolean
```

```
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(
    System.object TopDoc,
    System.object Component
)
```

C++/CLI

```
System.bool AccessSelections(
    & System.Object^ TopDoc,
    & System.Object^ Component
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Component

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::AccessSelections](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

Depth Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : Depth Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::Depth](#).

.NET Syntax

Visual Basic (Declaration)

Property Depth As System.Double

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As System.Double
```

```
instance.Depth = value
```

```
value = instance.Depth
```

C#

```
System.double Depth {get; set;}
```

C++/CLI

```
property System.double Depth {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::Depth](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

Diameter Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : Diameter Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::Diameter](#).

.NET Syntax

Visual Basic (Declaration)

Property Diameter As System.Double

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As System.Double
```

```
instance.Diameter = value
```

```
value = instance.Diameter
```

C#

```
System.double Diameter {get; set;}
```

C++/CLI

```
property System.double Diameter {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::Diameter](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DraftAngle Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : DraftAngle Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::DraftAngle](#).

.NET Syntax

Visual Basic (Declaration)

```
Property DraftAngle As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As System.Double
```

```
instance.DraftAngle = value
```

```
value = instance.DraftAngle
```

C#

```
System.double DraftAngle {get; set;}
```

C++/CLI

```
property System.double DraftAngle {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::DraftAngle](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

DraftOutward Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : DraftOutward Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::DraftOutward](#).

.NET Syntax

Visual Basic (Declaration)

```
Property DraftOutward As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As System.Boolean
```

```
instance.DraftOutward = value
```

```
value = instance.DraftOutward
```

C#

```
System.bool DraftOutward {get; set;}
```

C++/CLI

```
property System.bool DraftOutward {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::DraftOutward](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

DraftWhileExtruding Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : DraftWhileExtruding Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::DraftWhileExtruding](#).

.NET Syntax

Visual Basic (Declaration)

```
Property DraftWhileExtruding As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As System.Boolean
```

```
instance.DraftWhileExtruding = value
```

```
value = instance.DraftWhileExtruding
```

C#

```
System.bool DraftWhileExtruding {get; set;}
```

C++/CLI

```
property System.bool DraftWhileExtruding {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::DraftWhileExtruding](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Face Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : Face Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::Face](#).

.NET Syntax

Visual Basic (Declaration)

Property Face As System.Object

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData
Dim value As System.Object
```

```
instance.Face = value
```

```
value = instance.Face
```

C#

```
System.object Face {get; set;}
```

C++/CLI

```
property System.Object^ Face {
    System.Object^ get();
    void set ( & System.Object^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::Face](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IAccessSelections Method (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : IAccessSelections Method (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::IAccessSelections](#).

.NET Syntax

Visual Basic (Declaration)

```
Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc, _  
    ByVal Component As Component _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim TopDoc As ModelDoc  
Dim Component As Component  
Dim value As System.Boolean  
  
value = instance.IAccessSelections(TopDoc, Component)
```

C#

```
System.bool IAccessSelections(  
    ModelDoc TopDoc,  
    Component Component  
)
```

C++/CLI

```
System.bool IAccessSelections(  
& ModelDoc^ TopDoc,  
& Component^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Component

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::IAccessSelections](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IFace Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : IFace Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::IFace](#).

.NET Syntax

Visual Basic (Declaration)

```
Property IFace As Face
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As Face  
  
instance.IFace = value
```

```
value = instance.IFace
```

C#

```
Face IFace {get; set;}
```

C++/CLI

```
property Face^ IFace {  
    Face^ get();  
    void set ( &    Face^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::IFace](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

IVertex Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : IVertex Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::IVertex](#).

.NET Syntax

Visual Basic (Declaration)

```
Property IVertex As Vertex
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As Vertex  
  
instance.IVertex = value  
value = instance.IVertex
```

C#

```
Vertex IVertex {get; set;}
```

C++/CLI

```
property Vertex^ IVertex {  
    Vertex^ get();  
    void set ( &    Vertex^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::IVertex](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

ReleaseSelectionAccess Method (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : ReleaseSelectionAccess Method (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::ReleaseSelectionAccess](#).

.NET Syntax

Visual Basic (Declaration)

```
Sub ReleaseSelectionAccess()
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::ReleaseSelectionAccess](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

ReverseDirection Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : ReverseDirection Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::ReverseDirection](#).

.NET Syntax

Visual Basic (Declaration)

```
Property ReverseDirection As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As System.Boolean  
  
instance.ReverseDirection = value  
value = instance.ReverseDirection
```

C#

```
System.bool ReverseDirection {get; set;}
```

C++/CLI

```
property System.bool ReverseDirection {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::ReverseDirection](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

ReverseOffset Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : ReverseOffset Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::ReverseOffset](#).

.NET Syntax

Visual Basic (Declaration)

Property ReverseOffset As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData
Dim value As System.Boolean
```

```
instance.ReverseOffset = value
```

```
value = instance.ReverseOffset
```

C#

```
System.bool ReverseOffset {get; set;}
```

C++/CLI

```
property System.bool ReverseOffset {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::ReverseOffset](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

SurfaceOffset Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : SurfaceOffset Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::SurfaceOffset](#).

.NET Syntax

Visual Basic (Declaration)

Property SurfaceOffset As System.Double

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As System.Double  
  
instance.SurfaceOffset = value  
value = instance.SurfaceOffset
```

C#

```
System.double SurfaceOffset {get; set;}
```

C++/CLI

```
property System.double SurfaceOffset {  
    System.double get();  
    void set ( &    System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::SurfaceOffset](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Type Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : Type Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::Type](#).

.NET Syntax

Visual Basic (Declaration)

Property Type As System.Integer

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As System.Integer  
  
instance.Type = value  
value = instance.Type
```

C#

```
System.int Type {get; set;}
```

C++/CLI

```
property System.int Type {  
    System.int get();
```

```
void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::Type](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

SOLIDWORKS API Help

[Send comments](#) on this topic.

Vertex Property (ISimpleHoleFeatureData)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData Interface](#) : Vertex Property (ISimpleHoleFeatureData)

Obsolete. Superseded by [ISimpleHoleFeatureData2::Vertex](#).

.NET Syntax

Visual Basic (Declaration)

Property Vertex As System.Object

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData  
Dim value As System.Object
```

```
instance.Vertex = value
```

```
value = instance.Vertex
```

C#

```
System.object Vertex {get; set;}
```

C++/CLI

```
property System.Object^ Vertex {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData::Vertex](#).

See Also

[ISimpleHoleFeatureData Interface](#)
[ISimpleHoleFeatureData Members](#)

ISimpleHoleFeatureData2 (Type)

ISimpleHoleFeatureData2 Interface

[See Also](#) [Members](#) [Example](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISimpleHoleFeatureData2 Interface

Allows access to a simple hole feature.

NOTE: Click the **Members** link, located near the top of the topic, to see this interface's methods and properties.

.NET Syntax

Visual Basic (Declaration)

```
Public Interface ISimpleHoleFeatureData2
```

Visual Basic (Usage)

```
Dim instance As ISimpleHoleFeatureData2
```

C#

```
public interface ISimpleHoleFeatureData2
```

C++/CLI

```
public interface class ISimpleHoleFeatureData2
```

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2](#).

Example

- [Set New End Condition for Simple Hole Feature \(VBA\)](#)
- [Set New End Condition for Simple Hole Feature \(VB.NET\)](#)
- [Set New End Condition for Simple Hole Feature \(C#\)](#)

Accessors

[IFeature::GetDefinition](#) and [IFeature::IGetDefinition](#)

Access Diagram

[SimpleHoleFeatureData2](#)

See Also

- [ISimpleHoleFeatureData2 Members](#)
- [SolidWorks.Interop.sldworks Namespace](#)
- [IWizardHoleFeatureData2 Interface](#)
- [SimpleHole2 Method](#)

ISimpleHoleFeatureData2 Interface Members

[See Also](#) [Properties](#) [Methods](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISimpleHoleFeatureData2 Interface

The following tables list the members exposed by [ISimpleHoleFeatureData2](#).

Public Properties

Name	Description
AssemblyFeatureScope	Gets or sets whether to use scope for this assembly simple hole feature.
AutoSelect	Gets or sets whether to automatically select all or only specific bodies for the simple hole feature to affect in a multibody body.

[AutoSelectComponents](#)

Gets or sets whether to auto-select all components that this assembly simple hole feature affects in model.

[Depth](#)

Gets or sets the depth of this simple hole feature.

[Diameter](#)

Gets or sets the diameter of this simple hole feature

[DraftAngle](#)

Gets or sets the draft angle for this simple hole feature.

[DraftOutward](#)

Gets or sets whether to draft the simple hole feature outward.

[DraftWhileExtruding](#)

Gets or sets whether to draft the simple hole feature while extruding.

[Face](#)

Gets or sets the end-condition face of this simple hole feature.

[FeatureScope](#)

Gets or sets whether to use scope for the simple hole feature in a multibody part.

[FeatureScopeBodies](#)

Gets or sets the solid bodies that the simple hole feature affects in a multibody part.

[IFace](#)

Gets or sets the end-condition face of this simple hole feature.

[IVertex](#)

Gets or sets the end-condition vertex of this simple hole feature.

[PropagateFeatureToParts](#)

Gets whether to propagate this assembly simple hole feature to the parts that it affects in this model.

[ReverseDirection](#)

Gets or sets whether to reverse the direction of the cut.

[ReverseOffset](#)

Gets or sets whether to reverse the offset from the surface.

[SurfaceOffset](#)

Gets or sets the depth of this simple hole feature offset from the surface.

[TranslateSurface](#)

Gets or sets whether to translate the surface of this simple hole.

[Type](#)

Gets or sets the end-condition of the simple hole.

[Vertex](#)

Gets or sets the end-condition vertex of this simple hole feature.

[Top](#)

Public Methods

Name	Description
 AccessSelections	Gains access to the selections used to define the simple hole feature.
 GetDirectionReference	Gets the direction of the cut extrude for this simple hole feature.
 GetEndConditionReference	Gets the reference entity that defines the end condition for this simple hole feature.
 GetFeatureScopeBodiesCount	Gets the number of solid bodies affected by the simple hole feature in a multibody part.
 IAccessSelections	Gains access to the selections used to define the simple hole feature.
 IGetFeatureScopeBodies	Gets the solid bodies that the simple hole feature affects in a multibody part.
 ISetFeatureScopeBodies	Sets the solid bodies that the simple hole feature affects in the multibody part.
 ReleaseSelectionAccess	Releases access to the selections that define the simple hole feature.
 SetDirectionReference	Sets the direction of the cut extrude for this simple hole feature.
 SetEndConditionReference	Sets the reference entity that defines the end condition for this simple hole feature.

[Top](#)

See Also

[ISimpleHoleFeatureData2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IWizardHoleFeatureData2 Interface](#)
[SimpleHole2 Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISimpleHoleFeatureData2 Interface Methods

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : [ISimpleHoleFeatureData2 Interface](#)

For a list of all members of this type, see [ISimpleHoleFeatureData2 members](#).

Public Methods

Name	Description
 AccessSelections	Gains access to the selections used to define the simple hole feature.
 GetDirectionReference	Gets the direction of the cut extrude for this simple hole feature.
 GetEndConditionReference	Gets the reference entity that defines the end condition for this simple hole feature.
 GetFeatureScopeBodiesCount	Gets the number of solid bodies affected by the simple hole feature in a multibody part.
 IAccessSelections	Gains access to the selections used to define the simple hole feature.
 IGetFeatureScopeBodies	Gets the solid bodies that the simple hole feature affects in a multibody part.
 ISetFeatureScopeBodies	Sets the solid bodies that the simple hole feature affects in the multibody part.
 ReleaseSelectionAccess	Releases access to the selections that define the simple hole feature.
 SetDirectionReference	Sets the direction of the cut extrude for this simple hole feature.
 SetEndConditionReference	Sets the reference entity that defines the end condition for this simple hole feature.

[Top](#)

See Also

[ISimpleHoleFeatureData2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IWizardHoleFeatureData2 Interface](#)
[SimpleHole2 Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISimpleHoleFeatureData2 Interface Properties

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) : ISimpleHoleFeatureData2 Interface

For a list of all members of this type, see [ISimpleHoleFeatureData2 members](#).

Public Properties

Name	Description
 AssemblyFeatureScope	Gets or sets whether to use scope for this assembly simple hole feature.
 AutoSelect	Gets or sets whether to automatically select all or only specific bodies for the simple hole feature to affect in a multibody body.
 AutoSelectComponents	Gets or sets whether to auto-select all components that this assembly simple hole feature affects in model.
 Depth	Gets or sets the depth of this simple hole feature.
 Diameter	Gets or sets the diameter of this simple hole feature
 DraftAngle	Gets or sets the draft angle for this simple hole feature.
 DraftOutward	Gets or sets whether to draft the simple hole feature outward.
 DraftWhileExtruding	Gets or sets whether to draft the simple hole feature while extruding.
 Face	Gets or sets the end-condition face of this simple hole feature.
 FeatureScope	Gets or sets whether to use scope for the simple hole feature in a multibody part.
 FeatureScopeBodies	Gets or sets the solid bodies that the simple hole feature affects in a multibody part.
 IFace	Gets or sets the end-condition face of this simple hole feature.
 IVertex	Gets or sets the end-condition vertex of this simple hole feature.
 PropagateFeatureToParts	Gets whether to propagate this assembly simple hole feature to the parts that it affects in this model.
 ReverseDirection	Gets or sets whether to reverse the direction of the cut.
 ReverseOffset	Gets or sets whether to reverse the offset from the surface.
 SurfaceOffset	Gets or sets the depth of this simple hole feature offset from the surface.
 TranslateSurface	Gets or sets whether to translate the surface of this simple hole.
Type	Gets or sets the end-condition of the simple hole.



[Vertex](#)

Gets or sets the end-condition vertex of this simple hole feature.

[Top](#)

See Also

[ISimpleHoleFeatureData2 Interface](#)
[SolidWorks.Interop.sldworks Namespace](#)
[IWizardHoleFeatureData2 Interface](#)
[SimpleHole2 Method](#)

SOLIDWORKS API Help

[Send comments on this topic.](#)

AccessSelections Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : AccessSelections Method (ISimpleHoleFeatureData2)

Gains access to the selections used to define the simple hole feature.

.NET Syntax

Visual Basic (Declaration)

```
Function AccessSelections( _  
    ByVal TopDoc As System.Object, _  
    ByVal Component As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim TopDoc As System.Object  
Dim Component As System.Object  
Dim value As System.Boolean  
  
value = instance.AccessSelections(TopDoc, Component)
```

C#

```
System.bool AccessSelections(  
    System.object TopDoc,  
    System.object Component  
)
```

C++/CLI

```
System.bool AccessSelections(  
& System.Object^ TopDoc,  
& System.Object^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Top-level document (see **Remarks**)

Component

Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections were successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::AccessSelections](#).

Example

See [ISimpleHoleFeatureData2](#) examples.

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [ISimpleHoleFeatureData2::ReleaseSelectionAccess](#) if you did not

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::IAccessSelections Method](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

AssemblyFeatureScope Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : AssemblyFeatureScope Property (ISimpleHoleFeatureData2)

Gets or sets whether to use scope for this assembly simple hole feature.

.NET Syntax

Visual Basic (Declaration)

Property AssemblyFeatureScope As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Boolean
```

```
instance.AssemblyFeatureScope = value
```

```
value = instance.AssemblyFeatureScope
```

C#

```
System.bool AssemblyFeatureScope {get; set;}
```

C++/CLI

```
property System.bool AssemblyFeatureScope {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to use feature scope, false to not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::AssemblyFeatureScope](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)

[ISimpleHoleFeatureData2::AutoSelect Property](#)
[ISimpleHoleFeatureData2::AutoSelectComponents Property](#)
[ISimpleHoleFeatureData2::PropagateFeatureToParts Property](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

AutoSelect Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : AutoSelect Property (ISimpleHoleFeatureData2)

Gets or sets whether to automatically select all or only specific bodies for the simple hole feature to affect in a multibody body.

.NET Syntax

Visual Basic (Declaration)

Property AutoSelect As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Boolean
```

```
instance.AutoSelect = value
```

```
value = instance.AutoSelect
```

C#

```
System.bool AutoSelect {get; set;}
```

C++/CLI

```
property System.bool AutoSelect {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to automatically select all bodies, false to select specific bodies for [ISimpleHoleFeatureData2::FeatureScopeBodies](#) or [ISimpleHoleFeatureData2::IGetFeatureScopeBodies](#)

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::AutoSelect](#).

Remarks

This property is only available when [ISimpleHoleFeatureData2::FeatureScope](#) is true.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::GetFeatureScopeBodiesCount Method](#)
[ISimpleHoleFeatureData2::IGetFeatureScopeBodies](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

AutoSelectComponents Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : AutoSelectComponents Property (ISimpleHoleFeatureData2)

Gets or sets whether to auto-select all components that this assembly simple hole feature affects in model.

.NET Syntax

Visual Basic (Declaration)

```
Property AutoSelectComponents As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Boolean
```

```
instance.AutoSelectComponents = value
```

```
value = instance.AutoSelectComponents
```

C#

```
System.bool AutoSelectComponents {get; set;}
```

C++/CLI

```
property System.bool AutoSelectComponents {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to auto-select all affected components, false to not (use the selected components only or set [ISimpleHoleFeatureData2::AutoSelect](#) to true)

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::AutoSelectComponents](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::AssemblyFeatureScope Property](#)
[ISimpleHoleFeatureData2::PropagateFeatureToParts Property](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Depth Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : Depth Property (ISimpleHoleFeatureData2)

Gets or sets the depth of this simple hole feature.

.NET Syntax

Visual Basic (Declaration)

```
Property Depth As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Double
```

```
instance.Depth = value
```

```
value = instance.Depth
```

C#

```
System.double Depth {get; set;}
```

C++/CLI

```
property System.double Depth {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Hole depth

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::Depth](#).

Remarks

This property only supports getting the depth of a blind hole. To get the depth of holes with other types of end conditions, you could:

- use [ExtrudeFeatureData2::GetDepth](#) to get the length of the extrusion.
- analyze the curves and edges of the hole to get the depth or thickness of it at a specific point.
- use [SimpleHoleFeatureData2::SurfaceOffset](#) for a hole with a depth that is offset from the surface.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Diameter Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : Diameter Property (ISimpleHoleFeatureData2)

Gets or sets the diameter of this simple hole feature

.NET Syntax

Visual Basic (Declaration)

```
Property Diameter As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Double
```

```
instance.Diameter = value
```

```
value = instance.Diameter
```

C#

```
System.double Diameter {get; set;}
```

C++/CLI

```
property System.double Diameter {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Hole diameter

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::Diameter](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

DraftAngle Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : DraftAngle Property (ISimpleHoleFeatureData2)

Gets or sets the draft angle for this simple hole feature.

.NET Syntax

Visual Basic (Declaration)

```
Property DraftAngle As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2
Dim value As System.Double

instance.DraftAngle = value
value = instance.DraftAngle
```

C#

```
System.double DraftAngle {get; set;}
```

C++/CLI

```
property System.double DraftAngle {
    System.double get();
    void set ( & System.double value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Draft angle

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::DraftAngle](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::DraftOutward Property](#)
[ISimpleHoleFeatureData2::DraftWhileExtruding Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

DraftOutward Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : DraftOutward Property (ISimpleHoleFeatureData2)

Gets or sets whether to draft the simple hole feature outward.

.NET Syntax

Visual Basic (Declaration)

Property DraftOutward As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Boolean  
  
instance.DraftOutward = value  
  
value = instance.DraftOutward
```

C#

```
System.bool DraftOutward {get; set;}
```

C++/CLI

```
property System.bool DraftOutward {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True drafts the simple hole feature outward, false does not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::DraftOutward](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::DraftAngle Property](#)
[ISimpleHoleFeatureData2::DraftWhileExtruding Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

DraftWhileExtruding Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : DraftWhileExtruding Property (ISimpleHoleFeatureData2)

Gets or sets whether to draft the simple hole feature while extruding.

.NET Syntax

Visual Basic (Declaration)

Property DraftWhileExtruding As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2
Dim value As System.Boolean

instance.DraftWhileExtruding = value
value = instance.DraftWhileExtruding
```

C#

```
System.bool DraftWhileExtruding {get; set;}
```

C++/CLI

```
property System.bool DraftWhileExtruding {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True drafts the simple hole feature while extruding, false does not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::DraftWhileExtruding](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::DraftAngle Property](#)
[ISimpleHoleFeatureData2::DraftOutward Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Face Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : Face Property (ISimpleHoleFeatureData2)

Gets or sets the end-condition face of this simple hole feature.

.NET Syntax

Visual Basic (Declaration)

Property Face As System.Object

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2
Dim value As System.Object

instance.Face = value
value = instance.Face
```

C#

```
System.Object Face {get; set;}
```

C++/CLI

```
property System.Object^ Face {  
    System.Object^ get();  
    void set ( &    System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

End condition [face](#) or NULL if the operation fails

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::Face](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::IFace Property](#)
[ISimpleHoleFeatureData2::IVertex Property](#)
[ISimpleHoleFeatureData2::Vertex Property](#)
[ISimpleHoleFeatureData2::GetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::SetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::Type Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

FeatureScope Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : FeatureScope Property (ISimpleHoleFeatureData2)

Gets or sets whether to use scope for the simple hole feature in a multibody part.

.NET Syntax

Visual Basic (Declaration)

```
Property FeatureScope As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Boolean
```

```
instance.FeatureScope = value
```

```
value = instance.FeatureScope
```

C#

```
System.bool FeatureScope {get; set;}
```

C++/CLI

```
property System.bool FeatureScope {  
    System.bool get();
```

```
void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True only the specified bodies in the multibody part are affected by the feature, false all of the bodies in the multibody part are affected by the feature

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::FeatureScope](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::GetFeatureScopeBodiesCount Method](#)
[ISimpleHoleFeatureData2::GetFeatureScopeBodies Method](#)
[ISimpleHoleFeatureData2::SetFeatureScopeBodies Method](#)
[ISimpleHoleFeatureData2::AutoSelect Property](#)
[ISimpleHoleFeatureData2::FeatureScopeBodies Property](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

FeatureScopeBodies Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : FeatureScopeBodies Property (ISimpleHoleFeatureData2)

Gets or sets the solid bodies that the simple hole feature affects in a multibody part.

.NET Syntax

Visual Basic (Declaration)

Property FeatureScopeBodies As System.Object

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Object
```

```
instance.FeatureScopeBodies = value
```

```
value = instance.FeatureScopeBodies
```

C#

```
System.object FeatureScopeBodies {get; set;}
```

C++/CLI

```
property System.Object^ FeatureScopeBodies {  
    System.Object^ get();  
    void set ( & System.Object^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Array of solid [bodies](#) that the simple hole feature affects

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::FeatureScopeBodies](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::GetFeatureScopeBodiesCount Method](#)
[ISimpleHoleFeatureData2::GetFeatureScopeBodies Method](#)
[ISimpleHoleFeatureData2::SetFeatureScopeBodies Method](#)
[ISimpleHoleFeatureData2::AutoSelect Property](#)
[ISimpleHoleFeatureData2::FeatureScope Property](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetDirectionReference Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : GetDirectionReference Method (ISimpleHoleFeatureData2)

Gets the direction of the cut extrude for this simple hole feature.

.NET Syntax

Visual Basic (Declaration)

```
Function GetDirectionReference( _  
    ByRef Ref1 As System.Object, _  
    ByRef Type1 As System.Integer, _  
    ByRef Ref2 As System.Object, _  
    ByRef Type2 As System.Integer _  
) As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim Ref1 As System.Object  
Dim Type1 As System.Integer  
Dim Ref2 As System.Object  
Dim Type2 As System.Integer  
Dim value As System.Integer  
  
value = instance.GetDirectionReference(Ref1, Type1, Ref2, Type2)
```

C#

```
System.int GetDirectionReference(  
    out System.object Ref1,  
    out System.int Type1,  
    out System.object Ref2,  
    out System.int Type2  
)
```

C++/CLI

```
System.int GetDirectionReference(  
& [Out] System.Object^ Ref1,  
& [Out] System.int Type1,  
& [Out] System.Object^ Ref2,  
& [Out] System.int Type2  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ref1

First reference entity (see **Remarks**)

Type1

Type of reference entity as defined by [swSelectType_e](#)

Ref2

Second reference entity (see **Remarks**)

Type2

Type of reference entity as defined by [swSelectType_e](#)

Return Value

Number of reference entities used to define the direction of this hole feature

 Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::GetDirectionReference](#).

 Remarks

Sometimes one reference entity defines a direction; for example, an edge or axis. Other times, two reference entities define a direction; for example, two vertices or two sketch points.

If...	Then...
One reference entity defined the direction	Ref2 is NULL and the return value is 1
Two reference entities defined the direction	Both Ref1 and Ref2 are non-NULL and return value is 2

Valid reference entities for Ref1 and Ref2:

- line segment
- edge
- axis
- vertex
- face
- plane
- sketch point

See [Accessing Selections that Define Features](#) for additional details.

 See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::SetDirectionReference Method](#)
[ISimpleHoleFeatureData2::ReverseDirection Property](#)

 Availability

SOLIDWORKS 2004 SP1, Revision Number 12.1

SOLIDWORKS API Help [Send comments on this topic.](#)

GetEndConditionReference Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : GetEndConditionReference Method (ISimpleHoleFeatureData2)

Gets the reference entity that defines the end condition for this simple hole feature.

 .NET Syntax

Visual Basic (Declaration)

```
Function GetEndConditionReference( _  
    ByRef ReferenceType As System.Integer _  
) As System.Object
```

Visual Basic (Usage)

```
Dim instance As ISimpleHoleFeatureData2  
Dim ReferenceType As System.Integer  
Dim value As System.Object
```

```
value = instance.GetEndConditionReference(ReferenceType)
```

C#



```
System.Object GetEndConditionReference(  
    out System.int ReferenceType  
)
```

C++/CLI

```
System.Object^ GetEndConditionReference(  
& [Out] System.int ReferenceType  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

ReferenceType

Reference type as defined in [swSelectionReferenceTypes_e](#)

Return Value

Reference entity

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::GetEndConditionReference](#).

Example

See [ISimpleHoleFeatureData2](#) examples.

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::SetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::Face Property](#)
[ISimpleHoleFeatureData2::IFace Property](#)
[ISimpleHoleFeatureData2::IVertex Property](#)
[ISimpleHoleFeatureData2::Vertex Property](#)
[ISimpleHoleFeatureData2::Type Property](#)

Availability

SOLIDWORKS 2003 SP1, Revision Number 11.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

GetFeatureScopeBodiesCount Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : GetFeatureScopeBodiesCount Method (ISimpleHoleFeatureData2)

Gets the number of solid bodies affected by the simple hole feature in a multibody part.

.NET Syntax

Visual Basic (Declaration)

```
Function GetFeatureScopeBodiesCount() As System.Integer
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Integer  
  
value = instance.GetFeatureScopeBodiesCount()
```

C#

```
System.int GetFeatureScopeBodiesCount()
```

C++/CLI

```
System.int GetFeatureScopeBodiesCount();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Return Value

Number of solid bodies affected

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::GetFeatureScopeBodiesCount](#).

Remarks

Call this method before calling [ISimpleHoleData2::IGetFeatureScopeBodies](#) to get the size of the array for that method.

If [ISimpleHoleFeatureData2::FeatureScope](#) is false, then count is 0.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::IGetFeatureScopeBodies Method](#)
[ISimpleHoleFeatureData2::FeatureScopeBodies Property](#)
[ISimpleHoleFeatureData2::AutoSelect Property](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IAccessSelections Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : IAccessSelections Method (ISimpleHoleFeatureData2)

Gains access to the selections used to define the simple hole feature.

.NET Syntax

Visual Basic (Declaration)

```
Function IAccessSelections( _  
    ByVal TopDoc As ModelDoc2, _  
    ByVal Component As Component2 _  
    ) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim TopDoc As ModelDoc2  
Dim Component As Component2  
Dim value As System.Boolean  
  
value = instance.IAccessSelections(TopDoc, Component)
```

C#

```
System.bool IAccessSelections(  
    ModelDoc2 TopDoc,  
    Component2 Component  
)
```

C++/CLI

```
System.bool IAccessSelections(  
& ModelDoc2^ TopDoc,  
& Component2^ Component  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

TopDoc

Top-level document (see **Remarks**)

Component

Component in which the feature is to be modified (see **Remarks**)

Return Value

True if the selections were successfully accessed, false if not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::IAccessSelections](#).

Remarks

To modify a feature in a...	Then...
Part	- TopDoc argument is the IModelDoc2 for the part - Component argument is NULL
Assembly	- TopDoc is the IModelDoc2 object for the assembly - Component argument is the IComponent2 object in which the feature is to be modified

This method puts the model into a rollback state to allow access to the selections that define this feature. You must use either of the following methods to restore the rollback state:

- [IFeature::ModifyDefinition](#) or [IFeature::IModifyDefinition2](#) if you modified the feature
- [ISimpleHoleFeatureData2::ReleaseSelectionAccess](#) if you did not

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::AccessSelections Method](#)

Availability

SOLIDWORKS 2001Pus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IFace Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : IFace Property (ISimpleHoleFeatureData2)

Gets or sets the end-condition face of this simple hole feature.

.NET Syntax

Visual Basic (Declaration)

Property IFace As Face2

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As Face2
```

```
instance.IFace = value
```

```
value = instance.IFace
```

C#

```
Face2 IFace {get; set;}
```

C++/CLI

```
property Face2^ IFace {  
    Face2^ get();  
    void set ( &    Face2^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

End condition [face](#) or NULL if the operation fails

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::IFace](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::Face Property](#)
[ISimpleHoleFeatureData2::Vertex Property](#)
[ISimpleHoleFeatureData2::Vertex Property](#)
[ISimpleHoleFeatureData2::GetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::SetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::Type Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IGetFeatureScopeBodies Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : IGetFeatureScopeBodies Method (ISimpleHoleFeatureData2)

Gets the solid bodies that the simple hole feature affects in a multibody part.

.NET Syntax

Visual Basic (Declaration)

```
Function IGetFeatureScopeBodies( _  
    ByVal Count As System.Integer _  
) As Body2
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim Count As System.Integer  
Dim value As Body2  
  
value = instance.IGetFeatureScopeBodies(Count)
```

C#

```
Body2 IGetFeatureScopeBodies(  
    System.int Count  
)
```

C++/CLI

```
Body2^ IGetFeatureScopeBodies(  
&    System.int Count  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of bodies that this simple hole feature affects

Return Value

- in-process, unmanaged C++: Pointer to an array of [bodies](#) that this simple hole feature affects
- VBA, VB.NET, C#, and C++/CLI: Not supported
See [In-process Methods](#) for details about this type of method.

Remarks

Before calling this method, call [ISimpleHoleFeatureData2::GetFeatureScopeBodiesCount](#) to get the size of the array.

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::ISetFeatureScopeBodies Method](#)
[ISimpleHoleFeatureData2::AutoSelect Property](#)
[ISimpleHoleFeatureData2::FeatureScope Property](#)
[ISimpleHoleFeatureData2::FeatureScopeBodies Property](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ISetFeatureScopeBodies Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : ISetFeatureScopeBodies Method (ISimpleHoleFeatureData2)

Sets the solid bodies that the simple hole feature affects in the multibody part.

.NET Syntax

Visual Basic (Declaration)

```
Sub ISetFeatureScopeBodies( _  
    ByVal Count As System.Integer, _  
    ByRef BodyArr As Body2 _  
)
```

Visual Basic (Usage)

```
Dim instance As ISimpleHoleFeatureData2  
Dim Count As System.Integer  
Dim BodyArr As Body2  
  
instance.ISetFeatureScopeBodies(Count, BodyArr)
```

C#

```
void ISetFeatureScopeBodies(  
    System.int Count,  
    ref Body2 BodyArr  
)
```

C++/CLI

```
void ISetFeatureScopeBodies(  
& System.int Count,  
& Body2^% BodyArr  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Count

Number of bodies that this simple hole feature affects

BodyArr

Array of [bodies](#) that this simple hole feature affects

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::ISetFeatureScopeBodies](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::GetFeatureScopeBodiesCount Method](#)
[ISimpleHoleFeatureData2::GetFeatureScopeBodies Method](#)
[ISimpleHoleFeatureData2::AutoSelect Property](#)
[ISimpleHoleFeatureData2::FeatureScope Property](#)
[ISimpleHoleFeatureData2::FeatureScopeBodies Property](#)

Availability

SOLIDWORKS 2004 FCS, Revision Number 12.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

IVertex Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : IVertex Property (ISimpleHoleFeatureData2)

Gets or sets the end-condition vertex of this simple hole feature.

.NET Syntax

Visual Basic (Declaration)

Property IVertex As Vertex

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As Vertex
```

```
instance.IVertex = value
```

```
value = instance.IVertex
```

C#

```
Vertex IVertex {get; set;}
```

C++/CLI

```
property Vertex^ IVertex {  
    Vertex^ get();  
    void set ( & Vertex^ value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

End-condition [vertex](#) or NULL if the operation fails

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::IVertex](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::IVertex Property](#)
[ISimpleHoleFeatureData2::IFace Property](#)
[ISimpleHoleFeatureData2::Face Property](#)
[ISimpleHoleFeatureData2::SetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::GetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::Type Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

PropagateFeatureToParts Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : PropagateFeatureToParts Property (ISimpleHoleFeatureData2)

Gets whether to propagate this assembly simple hole feature to the parts that it affects in this model.

.NET Syntax

Visual Basic (Declaration)

Property PropagateFeatureToParts As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Boolean
```

```
instance.PropagateFeatureToParts = value
```

```
value = instance.PropagateFeatureToParts
```

C#

```
System.bool PropagateFeatureToParts {get; set;}
```

C++/CLI

```
property System.bool PropagateFeatureToParts {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to propagate this assembly simple hole feature to the parts that it affects in the model, false to not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::PropagateFeatureToParts](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::AssemblyFeatureScope Property](#)
[ISimpleHoleFeatureData2::AutoSelect Property](#)
[ISimpleHoleFeatureData2::AutoSelectComponents Property](#)

Availability

SOLIDWORKS 2009 FCS, Revision Number 17.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ReleaseSelectionAccess Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : ReleaseSelectionAccess Method (ISimpleHoleFeatureData2)

Releases access to the selections that define the simple hole feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub ReleaseSelectionAccess()
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
instance.ReleaseSelectionAccess()
```

C#

```
void ReleaseSelectionAccess()
```

C++/CLI

```
void ReleaseSelectionAccess();
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::ReleaseSelectionAccess](#).

Example

See [ISimpleHoleFeatureData2](#) examples.

Remarks

[ISimpleHoleFeatureData2::AccessSelections](#) and [ISimpleHoleFeatureData2::!AccessSelections](#) put the model in a rollback state to allow access to the selections that define the feature.

Use this method to restore the rollback state if you did not modify the feature, or use [IFeature::ModifyDefinition](#) or [IFeature::!ModifyDefinition2](#) if you did modify the feature.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ReverseDirection Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : ReverseDirection Property (ISimpleHoleFeatureData2)

Gets or sets whether to reverse the direction of the cut.

.NET Syntax

Visual Basic (Declaration)

Property ReverseDirection As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2
Dim value As System.Boolean

instance.ReverseDirection = value
value = instance.ReverseDirection
```

C#

```
System.bool ReverseDirection {get; set;}
```

C++/CLI

```
property System.bool ReverseDirection {
    System.bool get();
    void set ( & System.bool value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True reverses the direction of the cut, false does not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::ReverseDirection](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::GetDirectionReference Method](#)
[ISimpleHoleFeatureData2::SetDirectionReference Method](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

ReverseOffset Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : ReverseOffset Property (ISimpleHoleFeatureData2)

Gets or sets whether to reverse the offset from the surface.

.NET Syntax

Visual Basic (Declaration)

Property ReverseOffset As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2
Dim value As System.Boolean

instance.ReverseOffset = value
value = instance.ReverseOffset
```

C#

```
System.bool ReverseOffset {get; set;}
```

C++/CLI

```
property System.bool ReverseOffset {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True reverses the offset from the surface, false does not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::ReverseOffset](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeature2::SurfaceOffset Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

SetDirectionReference Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : SetDirectionReference Method (ISimpleHoleFeatureData2)

Sets the direction of the cut extrude for this simple hole feature.

.NET Syntax

Visual Basic (Declaration)

```
Function SetDirectionReference( _  
    ByVal Ref1 As System.Object, _  
    ByVal Ref2 As System.Object _  
) As System.Boolean
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim Ref1 As System.Object  
Dim Ref2 As System.Object  
Dim value As System.Boolean  
  
value = instance.SetDirectionReference(Ref1, Ref2)
```

C#

```
System.bool SetDirectionReference(  
    System.object Ref1,  
    System.object Ref2  
)
```

C++/CLI

```
System.bool SetDirectionReference(  
& System.Object^ Ref1,  
& System.Object^ Ref2  
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

Ref1

First reference entity (see **Remarks**)

Ref2

Second reference entity (see **Remarks**)

Return Value

True if the direction for the cut is set, false if not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::SetDirectionReference](#).

Remarks

Sometimes one reference entity defines a direction; for example, an edge or axis. Other times, two reference entities define a direction; for example, two vertices or two sketch points.

Valid reference entities for Ref1 and Ref2:

- line segment
- edge
- axis
- vertex
- face
- plane
- sketch point

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)

[ISimpleHoleFeatureData2 Members](#)

[ISimpleHoleFeatureData2::GetDirectionReference Method](#)

[ISimpleHoleFeatureData2::ReverseDirection Property](#)

Availability

SOLIDWORKS 2004 SP1, Revision Number 12.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

SetEndConditionReference Method (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : SetEndConditionReference Method (ISimpleHoleFeatureData2)

Sets the reference entity that defines the end condition for this simple hole feature.

.NET Syntax

Visual Basic (Declaration)

```
Sub SetEndConditionReference( _  
    ByVal PDisp As System.Object _  
)
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim PDisp As System.Object  
  
instance.SetEndConditionReference(PDisp)
```

C#

```
void SetEndConditionReference(  
    System.object PDisp  
)
```

```
void SetEndConditionReference(
& System.Object^ PDisp
)
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Parameters

PDisp
Reference entity

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::SetEndConditionReference](#).

Example

See [ISimpleHoleFeatureData2](#) examples.

Remarks

Valid end conditions are defined in [swSelectionReferenceTypes](#) [e](#).

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::GetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::Face Property](#)
[ISimpleHoleFeatureData2::IFace Property](#)
[ISimpleHoleFeatureData2::IVertex Property](#)
[ISimpleHoleFeatureData2::Vertex Property](#)
[ISimpleHoleFeatureData2::Type Property](#)

Availability

SOLIDWORKS 2003 SP1, Revision Number 11.1

SOLIDWORKS API Help

[Send comments on this topic.](#)

SurfaceOffset Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : SurfaceOffset Property (ISimpleHoleFeatureData2)

Gets or sets the depth of this simple hole feature offset from the surface.

.NET Syntax

Visual Basic (Declaration)

```
Property SurfaceOffset As System.Double
```

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2
Dim value As System.Double
```

```
instance.SurfaceOffset = value
```

```
value = instance.SurfaceOffset
```

C#

```
System.double SurfaceOffset {get; set;}
```

C++/CLI

```
property System.double SurfaceOffset {  
    System.double get();  
    void set ( & System.double value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Offset from the surface

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::SurfaceOffset](#).

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::Depth Property](#)
[ISimpleHoleFeatureData2::ReverseOffset Property](#)
[ISimpleHoleFeatureData2::TranslateSurface Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

TranslateSurface Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : TranslateSurface Property (ISimpleHoleFeatureData2)

Gets or sets whether to translate the surface of this simple hole.

.NET Syntax

Visual Basic (Declaration)

Property TranslateSurface As System.Boolean

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Boolean
```

```
instance.TranslateSurface = value
```

```
value = instance.TranslateSurface
```

C#

```
System.bool TranslateSurface {get; set;}
```

C++/CLI

```
property System.bool TranslateSurface {  
    System.bool get();  
    void set ( & System.bool value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

True to translate the surface of this simple hole, false to not

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::TranslateSurface](#).

Remarks

To use a true offset, this property should be false.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::SurfaceOffset Property](#)
[ISimpleHoleFeatureData2::ReverseOffset Property](#)

Availability

SOLIDWORKS 2007 FCS, Revision Number 15.0

SOLIDWORKS API Help

[Send comments on this topic.](#)

Type Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : Type Property (ISimpleHoleFeatureData2)

Gets or sets the end-condition of the simple hole.

.NET Syntax

Visual Basic (Declaration)

Property Type As System.Integer

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2  
Dim value As System.Integer
```

```
instance.Type = value
```

```
value = instance.Type
```

C#

```
System.int Type {get; set;}
```

C++/CLI

```
property System.int Type {  
    System.int get();  
    void set ( & System.int value);  
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

Type of end-condition as defined in [swEndConditions_e](#)

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::Type](#).

Example

See [ISimpleHoleFeatureData2](#) examples.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::GetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::SetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::Face Property](#)
[ISimpleHoleFeatureData2::IFace Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0

SOLIDWORKS API Help

[Send comments](#) on this topic.

Vertex Property (ISimpleHoleFeatureData2)

[See Also](#)



[SolidWorks.Interop.sldworks Namespace](#) > [ISimpleHoleFeatureData2 Interface](#) : Vertex Property (ISimpleHoleFeatureData2)

Gets or sets the end-condition vertex of this simple hole feature.

.NET Syntax

Visual Basic (Declaration)

Property Vertex As System.Object

Visual Basic (Usage)



```
Dim instance As ISimpleHoleFeatureData2
Dim value As System.Object

instance.Vertex = value
value = instance.Vertex
```

C#

```
System.object Vertex {get; set;}
```

C++/CLI

```
property System.Object^ Vertex {
    System.Object^ get();
    void set ( & System.Object^ value);
}
```

NOTE: See [Differences Between Unmanaged C++ and C++/CLI Code](#).

Property Value

End-condition [vertex](#) or NULL if the operation fails

Visual Basic for Applications (VBA) Syntax

See [SimpleHoleFeatureData2::Vertex](#).

Remarks

See [Accessing Selections that Define Features](#) for additional details.

See Also

[ISimpleHoleFeatureData2 Interface](#)
[ISimpleHoleFeatureData2 Members](#)
[ISimpleHoleFeatureData2::IVertex Property](#)
[ISimpleHoleFeatureData2::IFace Property](#)
[ISimpleHoleFeatureData2::Face Property](#)
[ISimpleHoleFeatureData2::SetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::GetEndConditionReference Method](#)
[ISimpleHoleFeatureData2::Type Property](#)

Availability

SOLIDWORKS 2001Plus FCS, Revision Number 10.0